

MICROMASTER 440

Electronic Device Description (EDD)

General

This EDD has the following version identifier:

- DEVICE_REVISION: 210
- DD_REVISION: 14

With the EDD, the MICROMASTER 440 can be parameterized and diagnosed using the SIMATIC Process Device Manager (SIMATIC PDM). Further, the frequency inverter can be diagnosed via the SIMATIC PCS7 Asset Management.

Hardware requirements

This EDD is only suitable for use with the MICROMASTER 440 frequency inverter, firmware release V2.10 and V2.11.

Software requirements

This EDD is released for use with the following software packages:

- SIMATIC PDM from version V6.0 SP3 (**Important hint: PDM versions \geq V8.1 are not supported with this EDD-File**)
- SIMATIC PCS7 from version 7.1.1 and higher

Known constraints

When using EDD within the scope of the PCS7 Asset Management, the following must be observed:

1.) When selecting the "Diagnostics" view within the diagnostic faceplate, the following message "Data being updated, please wait...!" is displayed at the lower edge of the faceplate although the displayed data are not being updated. If you wish to see the actual device data, then the update must be manually activated using the "Update" button.