


SIMATIC FM 350-1

Getting Started

Edition 11/2002

First Steps in Commissioning



This guide uses a specific example to introduce you to starting up your FM 350-1 module. It uses four steps to lead to a functioning application in which you count the switching operations of a contact and become familiar with and test the basic functions of the hardware and software of your FM 350-1. The references to the manual are intended to give you an initial overview of the information in the manual. The references refer to the “FM 350-1 Function Module” manual with the number A5E00073040-02.

The time required to work through the example will be approximately 1 to 2 hours, depending on how experienced you are.

Requirements

The following requirements must be fulfilled:

- You must have an S7-300 station comprising a power supply module and a CPU.
- STEP 7 (≥V5.0) is correctly installed on your programming device (the example given in this Getting Started was carried out with STEP 7 V5.2).
- You have set up a project for the S7-300 station.
- The programming device must be connected to the CPU.
- You must have an FM 350-1 module, the configuration package for the FM 350-1, and the necessary accessories such as a bus connector, front connector, sensors or switches, and wiring material.

Installing the Configuration Package on the Programming Device (Manual Chapter 4)

The configuration package contains a configuration tool for the FM 350-1, the functions (FC) and the data structure (UDT) required, and a sample program.

Insert the CD in the CD drive.

Under Windows start the dialog for installing software by double-clicking the “Add/Remove Programs” symbol in “Control Panel”.


Click [Install...](#) , start the Setup.exe file on the CD in the FMx50-1\Disk1 folder and follow the instructions of the installation program.

Installing and Wiring the FM 350-1 (Manual Chapter 2 and 3)

To connect the 24-V sensor used in the example you must insert the coding key on the module in position D before you insert the FM 350-1. This sets the adjustment to the sensor level (you will find more information on the coding key in Sections 1.3 and 2.2 of the manual).

Plug the bus connector supplied with the FM 350-1 into the bus connector on the CPU. Hang the FM 350-1 into the rail, swing it downwards, and screw it in place (you will find more detailed instructions in Section 2.2 of the manual).

Wire up the front connector as follows (you will find the full pin assignment of the front connector in Chapter 3 of the manual).



Insert the front connector in the FM 350-1 and snap it into place.

Test: Switch on the voltage on the power supply module. The red LED SF lights up. After you have switched on the power supply module for the first time, the FM 350-1 is in the preset default state (refer to Section 3.3 of the manual for default settings).

Assigning Parameters to the FM 350-1

Open your project in the SIMATIC Manager.

Open the configuration table (HW Config) in your project.

From the hardware catalog select the FM 350-1 with the correct order number and drag it to the required slot (in the example: slot 4).

Select the following setting in the FM 350-1 object properties in the Basic Parameters tab:

- Reaction to CPU stop: STOP

Call the parameter assignment screen forms by double-clicking on this FM 350-1. To do this, you may have to close the dialog asking you to save the configuration with **OK**.

Select the following settings by clicking on the buttons in the parameter assignment screen forms (please leave all other settings unchanged, as they are not yet required for commissioning):

- Operating Modes: Continuous Counting, Hardware Gate, 0 to +32 Bit
- Encoders: 24V Initiator, P Switch
- Inputs: Level-Controlled Hardware Gate
- Process interrupt enable: not possible as deselected in basic parameters
- Outputs: DO0 Inactive, DO1 Inactive

Enter the FM 350-1 parameter assignments in your configuration using the menu command **File > Save** and close the parameter assignment window.

Save the configuration created by you in your project using **Station > Save and Compile**.

Download the configuration with the CPU in STOP mode using the menu command **PLC > Download To Module**.

The data are now downloaded directly to the CPU and into the FM 350-1. The red LED SF extinguishes. From now on, as long as the configuration remains buffered in the CPU, the data will be transferred from the CPU to the FM 350-1 every time the CPU switches from STOP to RUN.

Test: You can now run simple tests without a program:

Close the gate contact: the green LED I0 lights up.

Close and open the count contact several times: you can monitor the state of the least significant bit of the FM 350-1 counter via the green LED CR.

Note that a mechanical count contact can bounce.

When you open the gate contact, the gate LED I0 extinguishes and no more switching operations are counted (the timing diagram for this function can be found in Section 8.3.7 of the manual).

Integrating into the User Program

Open the library FMx50LIB in the SIMATIC Manager using the menu command **File > Open...Libraries**.

Copy the functions FC 2 and FC 1 and the user-defined data type UDT 1 from the “**Blocks**” container of the FMx50LIB library to the “**Blocks**” container of your project.

Insert DB 1 as DB with data type UDT 1 into the “**Blocks**” container using the menu command **Insert > S7 Block > Data Block**.

Open the popup menu in HW Config by clicking with the right mouse button on the FM 350-1 entry. Using the **Object Properties** menu command start the **Properties – FM350-1 COUNTER** screen form.

Using the **Mod Addr...** button you can now automatically enter the module address (MOD_ADR) (in the example: 256 corresponds to 100 Hex), the channel address (CH-ADR) and the channel length set under **Addresses** in the channel data block.

You can achieve this by clicking the [Select DB](#) button in the [Module Address for DB](#) screen form. Click and select the [DB 1](#) in the [Open](#) dialog which was started. By clicking [OK](#) the values are stored in [DB 1](#) and the [Open](#) and [Module address for DB](#) screen forms are automatically closed. Exit the [Properties – FM350-1 COUNTER](#) screen form with [OK](#).

Alternatively you can also supply these parameters to [DB 1](#) in [OB100](#) (see manual, Section 5.1).

Open [OB 1](#) in your project.

Call [FC 2](#) ([FC CNT_CNTL1](#)) in [OB 1](#) and supply parameters to [FC 2](#) (see manual, Section 5.1):

```
CALL FC 2
      DB_NO := 1
      :
      :
```

Assign all remaining parameters of [FC 2](#) with free memory bits.

Save [OB1](#) using the menu command [File > Save](#).

Select all the blocks in your project (apart from [VAT](#) and [UDT](#)).

Download your program to the CPU using the menu command [PLC > Download](#).

Test: Using the “Monitoring and Modifying Variables” application you can now monitor the count value and the gate, for example:

In your project select the “Blocks” container. Insert the variable table [VAT1](#) using the menu command [Insert > S7 Block > Variable Table](#) and confirm with [OK](#).

Open the variable table [VAT1](#) and enter the following variables in the “Address” column:

[db1.dbd34](#) (actual count value)

[db1.dbx43.6](#) (status of internal gate)

Save the variable table [VAT1](#) using the menu command [Table > Save](#).

Switch online using the menu command [PLC > Connect To > Configured CPU](#).

Switch to monitoring using the menu command [Variable > Monitor](#).

Switch the CPU to [RUN-P](#).

Generate pulses with the count contact and monitor the count value with relation to the state of your gate contact.

Diagnosics

Errors can occur as a result of incorrect operation, incorrect wiring, or contradictory parameter assignments which the [FM 350-1](#) displays with the error LED [SF](#).

Refer to Section 5.3 and Chapter 12 of the manual for information on how you can diagnose errors and messages.

Example

In the [zEn23_01_FMx50-1](#) project you will find another example which you can use to guide you and which you can adapt to your application.