SIEMENS

SICAM SICAM SCC Human-Machine Interface (HMI)

V9.06

Manual

E50417-H8976-C501-B5

Preface	
Open Source Software	
Table of Contents	
Product Overview	1
Installation and Uninstallation	2
Working with SICAM SCC	3
Graphic Objects	4
Topological Coloring	5
SICAM Add-In	6
Components and Functions	7
Client-Server Systems	8
Redundancy	9
Different SICAM PAS Versions	10
WinCC Web Navigator	11
System Time	12
Converting Projects from Previous Versions	13
Components and Functions of Earlier SICAM PAS CC/SCC Versions	14
Appendix	A
Literature	
Index	



NOTE

For your own safety, observe the warnings and safety instructions contained in this document, if available.

Disclaimer of Liability

Subject to changes and errors. The information given in this document only contains general descriptions and/or performance features which may not always specifically reflect those described, or which may undergo modification in the course of further development of the products. The requested performance features are binding only when they are expressly agreed upon in the concluded contract. Document version: E50417-H8976-C501-B5.05 Edition: 05.2020

Version of the product described: V9.06

Copyright

Copyright © Siemens 2020. All rights reserved. The disclosure, duplication, distribution and editing of this document, or utilization and communication of the content are not permitted, unless authorized in writing. All rights, including rights created by patent grant or registration of a utility model or a design, are reserved.

Trademarks

SIPROTEC, DIGSI, SIGRA, SIGUARD, SIMEAS SAFIR, SICAM, and MindSphere are trademarks of Siemens. Any unauthorized use is prohibited.

Preface

Purpose of the Manual

This document provides all necessary information for installation, for commissioning, as well as details regarding the functionality of SICAM SCC.

Target Audience

This manual is mainly intended for commissioning engineers, programmers and users of SICAM SCC. Basic knowledge of SIMATIC WinCC is required.

Scope

This manual is valid for SICAM SCC V9.06.

Standards

SICAM SCC has been developed in compliance with ISO 9001:2008 standard.

Additional Support

For questions about the system, contact your Siemens sales partner.

Customer Support Center

Our Customer Support Center provides a 24-hour service.

Siemens AG Customer Support Center Humboldtstrasse 59 90459 Nuremberg Germany E-mail: support.energy@siemens.com

Training Courses

Inquiries regarding individual training courses should be addressed to our Training Center:

Siemens AG	Phone: +49 (911) 433-7415
Siemens Power Academy TD	Fax: +49 (911) 433-7929
Humboldtstrasse 59	E-mail: poweracademy@siemens.com
90459 Nuremberg	Internet: www.siemens.com/poweracademy
Germany	

Notes on Safety

This document is not a complete index of all safety measures required for operation of the equipment (module or device). However, it comprises important information that must be followed for personal safety, as well as to avoid material damage. Information is highlighted and illustrated as follows according to the degree of danger:



DANGER

DANGER means that death or severe injury will result if the measures specified are not taken.

♦ Comply with all instructions, in order to avoid death or severe injuries.



WARNING

WARNING means that death or severe injury may result if the measures specified are not taken.

♦ Comply with all instructions, in order to avoid death or severe injuries.



CAUTION

CAUTION means that medium-severe or slight injuries can occur if the specified measures are not taken.

♦ Comply with all instructions, in order to avoid moderate or minor injuries.

NOTICE

NOTICE means that property damage can result if the measures specified are not taken.

♦ Comply with all instructions, in order to avoid property damage.



NOTE

Important information about the product, product handling or a certain section of the documentation which must be given attention.

Qualified Electrical Engineering Personnel

Only qualified electrical engineering personnel may commission and operate the equipment (module, device) described in this document. Qualified electrical engineering personnel in the sense of this document are people who can demonstrate technical qualifications as electrical technicians. These persons may commission, isolate, ground and label devices, systems and circuits according to the standards of safety engineering.

Proper Use

The equipment (device, module) may be used only for such applications as set out in the catalogs and the technical description, and only in combination with third-party equipment recommended and approved by Siemens.

Problem-free and safe operation of the product depends on the following:

- Proper transport
- Proper storage, setup and installation
- Proper operation and maintenance

When electrical equipment is operated, hazardous voltages are inevitably present in certain parts. If proper action is not taken, death, severe injury or property damage can result:

- The equipment must be grounded at the grounding terminal before any connections are made.
- All circuit components connected to the power supply may be subject to dangerous voltage.

- Hazardous voltages may be present in equipment even after the supply voltage has been disconnected (capacitors can still be charged).
- Operation of equipment with exposed current-transformer circuits is prohibited. Before disconnecting the equipment, ensure that the current-transformer circuits are short-circuited.
- The limiting values stated in the document must not be exceeded. This must also be considered during testing and commissioning.

Open Source Software

The product contains, among other things, Open Source Software developed by third parties. The Open Source Software used in the product and the license agreements concerning this software can be found in the Readme_OSS. These Open Source Software files are protected by copyright. Your compliance with those license conditions will entitle you to use the Open Source Software as foreseen in the relevant license. In the event of conflicts between Siemens license conditions and the Open Source Software license conditions, the Open Source Software conditions shall prevail with respect to the Open Source Software portions of the software. The Open Source Software is licensed royalty-free. Insofar as the applicable Open Source Software License Conditions provide for it you can order the source code of the Open Source Software from your Siemens sales contact – against payment of the shipping and handling charges – for a period of at least 3 years after purchase of the product. We are liable for the product including the Open Source Software contained in it pursuant to the license conditions applicable to the product. Any liability for the Open Source Software beyond the program flow intended for the product is explicitly excluded. Furthermore any liability for defects resulting from modifications to the Open Source Software by you or third parties is excluded. We do not provide any technical support for the product if it has been modified.

Table of Contents

	Preface		3
	Open Sourc	ce Software	7
1	Product Ov	verview	
2	Installation	Installation and Uninstallation	
	2.1	Installation Requirements	22
	2.2	Installing SIMATIC WinCC	
	2.2.1	Installation	
	2.2.2	Licensing	25
	2.3	Installing SICAM SCC Components	26
	2.3.1	Design Variants	
	2.3.2	Installation	
	2.3.3	Licensing	28
	2.3.4	Automated Installation	
	2.4	Uninstalling SICAM SCC Components	
	2.4.1	Removing the license	
	2.4.2	Uninstallation	
	2.4.3	Protection against data loss	
	2.5	Uninstalling SIMATIC WinCC	
	2.5.1	Removing the License	
	2.5.2	Uninstallation	
	2.5.3	Protection against data loss	
	2.5.4	Virtualization	
3	Working wi	ith SICAM SCC	33
	3.1	Demo Project	
	3.2	Creating a New Project	35
	3.2.1	Creating a New WinCC Project	35
	3.2.2	Defining Project Properties	36
	3.2.3	Defining Computer Properties	
	3.2.4	Initializing a WinCC Project	43
	3.2.4.1	SICAM PAS Station	
	3.2.4.2	SICAM RTUS IEC 60870-5-104 Devices	
	3.2.4.4	IEC 61850 Devices	60
	3.2.5	Connection Parameters	73
	3.3	Creating a Control Diagram	
	3.3.1	Creating a New Diagram	
	3.3.2	Using SICAM Switch Controls	

3.3.3	Using Connectors and Connection Points	
3.3.4	Displaying a Measured Value	
3.3.5	Inserting an Acknowledge button	
3.4	Creating an overview diagram	
3.5	Creating a List View	92
3.6	Creating a Button Bar	
3.6.1	Inserting an Event List Button	
3.6.2	Inserting a Quit Button	
3.7	Creating a Start Screen	96
3.8	Setting up User Authorizations	
Graphic Obj	ects	
4.1	Overview	
4.2	Design of Graphic Objects	
4.2.1	SICAM Graphic Objects	
4.2.2	ActiveX Controls	
4.3	Using Graphic Objects	
4 4	SICAM Switch Controls	108
4.4.1	Representation Style of SICAM Switch Controls	
4.4.2	Process Connection of SICAM Switch Controls	
4.4.3	Advanced Properties of SICAM Switch Controls	
4.4.4	Colors of SICAM Switch Controls	
4.4.5	Picture of SICAM Switch Controls	
4.4.6	Runtime Dialogs of SICAM Switch Controls	
4.4.7	Substituting the Switch Position	
4.4.8	Defining Object Properties	
4.4.9	Operation with Self-Created Dialogs	133
4.4.10	Operation via Keyboard	
4.4.11	Interfaces for Project-Specific Dialogs	
4.4.11.1	SetControlCommand Function	
4.4.11.2	GetControistate Function Event OnProcDataChange	
4 5	Anwendungsheisniele für die Funktionen	142
4.5.1	Script for Event OnProcDataChange	
4.6	SICAM Electrical Device Control	144
4 7	SICAM Bay Overview	145
4.7.1	Representation Style of Bay Overview	
4.7.2	Tag Connection to Bay Overview	
4.7.3	Colors of Bay Overview	
4.7.4	Picture of Bay Overview	
4.8	Measured/Metered Value Display	
4.8.1	Style of the Numeric Display	
4.8.2	Tag Connection of the Numeric Display	
4.8.3	Advanced Properties of the Numeric Display	156
4.8.4	Limit Values of the Numeric Display	
4.8.5	Color of the Numeric Display	158
4.8.6	Font of the Numeric Display	

	4.8.7	Runtime Dialogs of the Numeric Display	
	4.8.8	Representing Measured Values for the Invalid State	163
	4.8.9	Support of Controllable Analogue Process Value (CDC = APC)	
5	Topological	Coloring	165
	5.1	Introduction	166
	5.2	Topological Elements	
	5.2.1	General	
	5.2.2	SICAM Electrical Device Control	169
	5.2.2.1	Description of Functions	
	5.2.2.2	Graphical representation Properties of SICAM Electrical Device Controls	1/0 171
	5.2.2.4	Tag Connection of the Feeder	
	5.2.2.5	Creating Structure Tags	
	5.2.3	SICAM Switch Controls	179
	5.2.4	SICAM Bay Overview	179
	5.2.5	Connector	180
	5.2.6	Node	
	5.3	Parameterization	
	5.3.1	Data Analysis	
	5.3.2	Data Model	181
	5.3.3	Settings	
	5.3.4	Parameterizing Elements and Symbols	
	5.3.5	Notes on Configuration	188
	5.4	Cross-Picture References	190
	5.5	Using Topological Coloring	
	5.6	Using Picture Windows	
	5.7	Debugging	
	5.7.1	General Information	199
	5.7.2	Error Messages	
	5.8	Application Examples	
	5.8.1	Switchgear trucks	
6	SICAM Add-	-In	
	6.1	Overview	
	6.2	SICAM Menu	
	6.3	SICAM Toolbar	207
	6.4	Performing Settings	208
	6.4.1	General Information	208
	6.4.2	Tasks	
	6.5	Predefined Tasks	
	6.6	Creating User-Defined Tasks	
	6.6.1	Upgrade V5.1 Measured Value Objects	
	6.6.2	Upgrade of V5.10 Controls	
	6.6.3	Edit Items of a Listbox or Combobox	
	6.7	Replacing a Graphic Object in the Library	

7

Component	s and Functions	233
7.1	System Overview	234
7.1.1	Connection to SICAM PAS/PQS	
7.1.2	Connection to SICAM RTUs or IEC 61850/IEC 60870-5-104	236
7.1.3	Configuration for Improved Message Display in the Case of Redundancy	238
7.2	Data Import	250
7.2.1	SICAM Import/Export Wizard	250
7.2.2	SICAM Wizard	
7.2.3	Configuring an IEC 60870-5-104 Connection During Runtime	274
7.2.4	SICAM IEC 104 XML Creator	275
7.2.4.1	General Procedure	275
7.2.4.2	Parameters and Data Types	
7.2.4.3	Creating a Parameter File	
7.3	SICAM Communication Connection - Tag Management	280
7.3.1	SICAM PAS PROTOCOL SUITE	280
7.3.2	SICAM IEC COMMUNICATION SUITE	
7.3.3	IEC 61850 Connection	
7.3.4	IEC 61850: Treatment of data with set Test Bit	
7.4	Alarm Logging	286
7.4.1	Alarm Logging System	
7.4.2	SICAM Normalization DLL	286
7.4.3	Using the Alarm Logging Extension	
7.4.4	Value Texts	
7.4.5	Message Coloring	290
7.4.6	Flexible Configuration of the Alarm Logging System	294
7.5	Dynamic Alarm Filter (DAF)	
7.5.1	Overview	
7.5.2	Starting the Dynamic Alarm Filter Function	
7.5.3	Configuration	
7.5.4	Mapping	304
7.5.5	Assignment Tables	
7.6	SICAM Functions	308
7.61	Commands	308
7.6.1.1	Command for Floating Point Values.	
7.6.1.2	Command for Digital Values	
7.6.1.3	Command Execute	
7.6.2	Substituting Values	310
7.6.2.1	Overview	
7.6.2.2	Substituting Floating Point Values	
7.0.2.5	Object Specific Plecking	212
7.0.5	Object-Specific Biocking	212
7.0.4 7641	Overview	313
7.6.4.2	Creating a Message - Text from the Text Library	
7.6.4.3	Creating a Message - with Text Transfer	
7.6.4.4	Acknowledging A Message in the Warning Message List	313
7.6.5	Function for Copying Tag Values	
7.6.6	Using SICAM Functions	314
7.6.7	Global Actions	

7.6.8	Testing SICAM Functions	315
7.6.9	Calling the SICAM PQ Analyzer	
7.6.9.1	Call from a Diagram	319
7.6.9.2	Call from the Event List	322
7.7	System Control	325
7.7.1	Administrative Tags	
7.7.2	Initiator Category	326
7.7.3	Message List Filter	
7.7.4	Switching Authority	331
7.7.5	Bay/Telecontrol Blocking	
7.7.5.1	Device-Specific Blocking	
7.7.5.2	Object-Specific Blocking	
/./.5.3	Ignoring Bay Blocking	
/./.0	Charactering a General Interrogation in Case of IEC 61850 Connection	
/././ 7 7 7 1	Changing Device Parameters via IEC 61850	
7.7.7.2	Modifying Individual Device Parameters/Settings Online	
7 8	SICAM SCC Runtime Data Server	338
7 9	Language Settings	330
7.91	Language Setting for SICAM Graphic Objects	
792	Switching the Language During Runtime	341
7 10	Communication with SICAM DISTO	343
7.10	SNIMP - SICAM Notwork Manager (NWM)	345
7 11 1		
7 11 2	SICAM Notwork Manager - Dialog	
7.11.2		
7.11.5	Extending the MIR Container	
7 11 5	Separate Network Card for SNMP	
7 11 6	Configuring SNMP (Example)	350
7.11.6.1	Defining Agents	
7.11.6.2	Configuring MIB Objects	
7.11.6.3	Creating Linked Variables	
7.11.6.4	Starting the Runtime and Opening the Tag Management	
Client-Serve	r Systems	
8.1	Configuration of the Graphic Objects	
8.2	Configuration of the Functions	
8.3	Configuration of the SIMATIC WinCC Components	
Podundancy		375
0 1	Overview	
י.י סס	Dedundancy with a SICAM DAS System	
y.∠	Redundancy with a SICAM PAS System	
9.2.1	Connection to 2 SICAM PAS Systems	
9.2.2	Redundant SICAM SCC System	379
9.3	Redundancy with SICAM RTUs	
9.3.1	Connection to Redundant SICAM RTU Substation Controllers	
9.3.2	Redundant SICAM SCC System	
Different SIC	CAM PAS Versions	
10.1	Overview	

	10.2	Introduction	
	10.3	Use Cases from Daily Practice	
11	WinCC Web	Navigator	391
	11.1	- Overview	
	11.2	Prerequisites	
	11.3	WinCC Web Navigator with SICAM SCC	
	11.3.1	Making SICAM SCC Plug-Ins Available	
	11.3.2	Publishing Process Diagrams	
	11.3.3	Installing Users for the WinCC Web Navigator	
	11.3.4	Configuring the WinCC Web Navigator Server	397
	11.3.5	Configuring the WinCC Web Navigator Client	398
12	System Time	e	401
	12.1	Overview	402
	12.2	Updating Time Zones	403
	12.3	Time Synchronization	404
	12.3.1	Network Time Protocol Daemon	404
	12.3.2	Configuration File for NTPD	405
	12.3.3	Clock Driver for Telecontrol Protocols (Shared Memory Clock Driver)	408
	12.3.4	Example – External Radio Clock as Timer	
13	Converting	Projects from Previous Versions	415
	13.1	Converting Projects Independently of the Version	
	13.2	Making Adjustments for V9.06	417
	13.3	Making Adjustments for V9.04	
	13.4	Converting Topology, V9.00	419
	13.5	Converting Projects, V8.04	
	13.6	Converting Projects, V8.03	
	13.7	Converting Projects, V8.02	
	13.8	Converting Projects, V8.01 or Earlier	423
	13.9	Converting Projects, V8.00 or Earlier	424
	13.10	Converting SICAM PAS/PAS CC Projects, V5.0 and V6.0	425
	13.11	Converting Projects, V6.0x	426
	13.12	Converting Projects, V5.11	
	13.13	Converting Projects, V5.10 or later	428
	13.14	Converting Projects, V5.10 or earlier	429
	13.15	Converting a SICAM WinCC Project	430
14	Component	s and Functions of Earlier SICAM PAS CC/SCC Versions	
	14.1	Double/Redundant Configuration in V5/V6 Projects	432
	14.1.1	Connection to 2 SICAM PAS Systems	
	14.1.2	Redundant SICAM SCC System	
	14.2	Circuit Breaker and Disconnector	
	14.2.1	Graphical Representation of Circuit Breakers and Disconnectors	443
	14.2.2	Tag Connection of the Circuit Breakers and Disconnectors	
	14.2.3	Colors of Circuit Breaker and Disconnector	

14.2.4	Advanced Properties of the Circuit Breaker and Disconnector	447
14.2.5	Controlling Synchronized Switching for the SICAM PAS Connection	449
14.2.6	Synchronized Switching for Direct Connection of Devices	451
14.2.7	Runtime Dialogs of Circuit Breakers and Disconnectors	452
14.2.8	Substituting the Switch Position	460
14.2.9	Defining Object Properties	460
14.2.10	Circuit Breaker/Disconnector with C Script	463
14.2.11	Indirect Addressing	464
14.2.12	Addressing Using Tag and Server Prefixes	466
14.2.13	Operation via Keyboard	469
14.2.14	Controlling Runtime Dialogs for Controls (Switching Device Objects)	472
14.2.15	Response to the Change of the CommandID Attribute	474
14.3	Bay Overview	
14.3.1	Properties of the Bay Overview	477
14.3.2	Tag Connection to Bay Overview	478
14.4	Showing Texts in Runtime Dialogs	
14.4.1	Showing Static Texts	481
14.4.2	Showing Dynamic Texts	482
14.5	IX State Sync Application	486
14.6	Measured-Value Display Using the Script/Project Function	491
14.6.1	Defining the Measured-Value Output	491
14.6.2	Substitute Functionality	493
14.7	Introduction to the SIMATIC WinCC Configuration Tool	495
14.7.1	Installing the SIMATIC WinCC Configuration Tool	495
14.7.2	Creating an Excel Project Folder	496
14.7.2.1	Project Folder with Connection to an Existing SIMATIC WinCC Project	
14.7.2.2	Project Folder without Connection to an Existing SIMATIC WinCC Project Project Folder with Connection to a New SIMATIC WinCC Project	502
14.7.2.5	Working with the SIMATIC WinCC Configuration Tool	
14.8	Madifying the Channel Version	
14.8.1	Creating a Project Folder	505 506
14.8.1.2	Selecting a Channel	
14.8.1.3	Writing Connections Back into the SIMATIC WinCC Project	511
14.8.2	Editing Structure Types	
14.8.2.1	Modifying Structure Types	517 519
14.0.2.2	Deleting Structure Types/Tags	
Appendix		521
A.1	Structures	522
A.2	Quality Codes of Variables	531
A.3	Character Conversion	532
A.4	Additional Information in Message Lists	536
A.5	Performance Measurements	543
Literature		545
Index		547

1 Product Overview

What is SICAM SCC?

SICAM SCC (SICAM Station Control Center) is the Human-Machine Interface (HMI) for the following power automation systems:

- SICAM PAS/PQS
- SICAM RTUs
- IEC 61850 devices
- IEC 60870-5-104 devices

SICAM SAS comprises:

- SIMATIC WinCC process visualization system
- SICAM SCC components

SIMATIC WinCC provides standard function modules for the display of graphic diagrams and views for alarms, archiving and logging. Based on its powerful process interface, fast display refresh rates and safe data archiving functions, it provides for high availability.

SICAM SCC Components

SICAM SCC comprises the following components:

- SICAM graphic object library
- Alarm system extension
- SICAM Import/Export Wizard, SICAM PAS Wizard, and SICAM IEC Wizard
- SICAM Functions
- SICAM Normalization DLLs
- SICAM PAS PROTOCOL SUITE and SICAM IEC COMMUNICATION SUITE
- SICAM Valpro (evaluation of archives for measured and metered values)

SICAM graphic object library

The SICAM graphic object library includes objects for the representation of typical substation control and protection equipment (e. g. switchgears). These graphic objects are used for the creation of station diagrams. The SICAM graphic object library includes e.g. several typical graphic objects for switchgears. Graphic objects can be dragged and dropped from the library to a station diagram.

They already include dynamic display properties. For example, a circuit breaker provides all dynamic features required for the representation of the process states ON, OFF, Intermediate Position, Fault Position, Not Topical, PAS not OK, Bay Blocking, Substituted and Telecontrol Blocking.

You can quickly and efficiently define the topology parameters of your system in the Graphics Designer.

Alarm system extension

The alarm system extension ensures that data is logged and archived in correct chronological order. The SICAM PAS normalization DLL evaluates the data and assigns it related items of process information. In order to assign process information, the normalization DLL accesses the SIMATIC WinCC text library. Texts can be customized in the text library to meet individual requirements. The information in the event list is of great significance.

SICAM Wizard



NOTE

Use the SICAM Import/Export Wizard as the standard wizard (see 7.2.1 SICAM Import/Export Wizard). If required, you can start the SICAM PAS Wizard or the SICAM IEC Wizard from the context menu of the SICAM Import/Export Wizard.

The SICAM Wizard supports you in the creation of a new project or in updating an existing WinCC project. The following wizards are available:

- SICAM PAS Wizard for the connection of SICAM PAS
- SICAM IEC Wizard for the connection of SICAM RTUs, IEC 61850 and IEC 61870-5-104 devices

You can perform the following tasks using the SICAM Wizard:

- Creating the SICAM-specific structure types
 You can create the structure types required in a SICAM system for structured tags.
 These structure types are required for data exchange with SICAM PAS, SICAM RTUs, IEC 61850 and IEC 60870-5-104 devices.
- Importing the tags from SICAM PAS, SICAM RTUs, IEC 61850 and IEC 60870-5-104 devices You transfer the information to SICAM SCC.
 This enables you to visualize items of information from these systems under SICAM SCC, i. e. for use in process diagrams.
- Creating administrative tags for SICAM PAS Creating the SICAM-specific Alarm Logging system You create a SICAM-specific Alarm Logging system in SICAM SCC. The SICAM graphic object library provides objects for the following lists:
 - Event list
 - Warning message list
 - Protection message list

These SICAM-specific lists are stored in the SICAM graphic object library. You can configure messages in this Alarm Logging system.

- Importing messages from the import files This enables you to visualize messages in SICAM SCC in the Alarm Logging system.
- IImporting the SICAM graphic object library into the project
 Load the SICAM graphic object library into your current project.
 Use the SICAM graphic object library for visualizing station diagrams under SICAM SCC.
- Creating the measured-value and metered-value archives for process data Create a Tag Logging system under SICAM SCC. The SICAM SCC Tag Logging system comprises:
 - a measured-value archive
 - a metered-value archive

You can import metered and measured value tags into this Tag Logging system.

• Adding a communication driver

You can add a communication driver and thus define the transmission path to SICAM PAS, SICAM RTUs, IEC 61850 and IEC 60870-5-104 devices.

SICAM functions

The SICAM functions (VB or C scripts) complement the library of SIMATIC WinCC functions. They are available as project-specific functions in the corresponding folders.

Use the SICAM functions in station diagrams. For example, you can execute commands via these actions.

SICAM Graphics Designer Extension

The Graphics Designer enables you to define several graphic objects simultaneously by means of defined tasks. Predefined tasks are available.

SICAM Valpro

SICAM Valpro has been designed for the processing, display and printing of archived measured and metered values.

SICAM Valpro interacts with the SICAM SCC Tag Logging system.

SICAM Valpro can be used independently of SICAM SCC.

For a more detailed description regarding SICAM Valpro, refer to /5/ SICAM Valpro, Measured/Metered Value Processing Utility SICAM Valpro.

Redundant system

To provide fail safety, a SICAM SCC system can be implemented in redundant configuration.

If one of the two SICAM SCC servers fails, the client computers automatically switch over from the failed server to the active SICAM SCC server. Based on this concept, proper process monitoring and operation is always ensured.

A redundant SICAM PAS system or SICAM RTUs are supported.

2 Installation and Uninstallation

2.1	Installation Requirements	22
2.2	Installing SIMATIC WinCC	25
2.3	Installing SICAM SCC Components	26
2.4	Uninstalling SICAM SCC Components	30
2.5	Uninstalling SIMATIC WinCC	31

2.1 Installation Requirements

Operating System and SIMATIC WinCC

SICAM SCC V9.06 is a 32-bit-application. The table below indicates possible combinations of the operating system and SIMATIC WinCC.

Windows	SIMATIC WinCC		
	V7.3	V7.4 SP1	V7.5 SP1
7 Professional 32-bit SP1 ¹	x	х	
7 Ultimate 32-bit SP1 ¹			
7 Enterprise 32-bit SP1 ¹			
7 Professional 64-bit ¹	x	х	
7 Ultimate 64-bit SP1 ¹			
7 Enterprise 64-bit SP1 ¹			
8.1 Professional 32-bit ¹	x	х	
8.1 Enterprise 32-bit			
8.1 Professional 64-bit ¹	x	х	
8.1 Enterprise 64-bit ¹			
10 Professional 64-bit ¹		х	х
10 Enterprise 64-bit ¹			
10 loT Enterprise LTSB 64-bit ¹			
2008 Server SP2 32-bit ¹	x		
2008 Server R2 SP1 64-bit ¹	x	х	
2012 Server R2 64-bit	x	х	x
2016 Server 64-bit		x	x
2019 Server 64-Bit		х	x

SIMATIC WinCC must be licensed and the latest update for the installed WinCC version must be installed. You can find a list of the necessary updates in the corresponding Readme file. You can download the update packages from the following website: *SIEMENS Industry Online Support (SIOS)*.

Microsoft .NET Framework

Before installing WinCC, make sure that .NET Framework is installed in the correct version depending on the operating system:

- Windows 10
 Microsoft .NET Framework 3.5 is required in order to be able to install SQL Management Studio
- Windows Server 2012 R2

Microsoft .NET Framework 4.6.1 (install this version later, if required)

Windows 10 / Windows Server 2016
 Microsoft .NET Framework 4.7

Microsoft Visual C++ Redistributable Packet VCRedist 2008 SP1 (x86)

Microsoft has discontinued support for the 2008 version of Visual Studio. Therefore, this version of the Visual C++ Redistributables can no longer be included on the SICAM SCC DVD.

In order to be able to use projects from older versions with SICAM SCC V9.06, components of these versions are partially included on the SICAM SCC DVD, e.g. for the connection to SICAM PAS V5.11 and V6.0 extensions for the alarm system and communication channels are included.

¹ These operating systems can be installed as standard version or as MUI version.

These components are not further developed. The Visual C++ Redistributables of version 2008 SP1 are necessary for operation. You can download this package from the Microsoft Internet pages: https://www.microsoft.com/en-us/download/details.aspx?id=26368

• Install the version for x86 operating systems.

SICAM Valpro has not yet been upgraded to a newer version of Visual C++ and also requires these Microsoft runtime components.

Ports Required for Operating SICAM SCC

Certain ports are required in order to be able to operate SICAM SCC with SICAM DISTO, IEC 60870-5-104 communication drivers, IEC 61850 communication drivers and SNMP. For more detailed information, refer to SICAM / SIPROTEC, System Hardening for Substation Automation and Protection.

Basic Hardware

CPU			
Windows 7	Client	3 GHz/Multi Core	
	Single-user system:	3.5 GHz/Multi Core	
Windows 8.1	Client	3 GHz/Multi Core	
Windows 10	Single-user system:	3.5 GHz/Multi Core	
Windows Server 2008 R2	Single-user system:	3.5 GHz/Multi Core	
Windows Server 2012 R2	Server:	3.5 GHz/Multi Core	
Windows Server 2016			
Primary storage			
Windows 7	Client	32-bit: 2 GB, 64-bit: 4 GB	
	Single-user system:	32-bit: 2 GB, 64-bit: 4 GB	
Windows 8.1	Client	32-bit: 2 GB, 64-bit: 4 GB	
	Single-user system:	32-bit: 2 GB, 64-bit: 4 GB	
Windows 10 (64-bit)	Client	4 GB	
	Single-user system:	4 GB	
Windows Server 2003	Single-user system:	32-bit: 2 GB, 64-bit: 4 GB	
	Server:	32-bit: 2 GB, 64-bit: 4 GB	
Windows Server 2008 R2	Single-user system:	8 GB	
Windows Server 2012 R2	Server:	8 GB	
Windows Server 2016			
Hard disk capacity			
	Client:	1.5 GB	
	Server:	10 GB	
Virtual primary storage			
	1.5 times primary storage		
Primary storage for Windows prin	iter spooler		
	100 MB		
Graphics card			
	32 MB, True Color (32 Bit), 1024 x 768 or 1366x768		
	recommended for FullHD (1980x1080) or later		

Miscellaneous

Monitor suitable for graphics card Dual-layer DVD drive USB port for licensing Keyboard Mouse

Sequence of Installation

SICAM SCC consists of the following 2 software packages:

- SIMATIC WinCC
- SICAM SCC components

Install the 2 software packages one after the other. Hotfixes and Service Packs are available on the SIOS portal from SIEMENS DI. Check if there is a newer Hotfix or an update available for one of your installed components.

The components must be installed in the following order:

- ♦ Install the SIMATIC WinCC process visualization system.
- ♦ License SIMATIC WinCC to make the program executable.
- ♦ Install the SICAM SCC components.
- ♦ License the SICAM SCC components to make them executable.



NOTE

To ensure that all the components function correctly, they must be installed in the following order:

- Install the program package using the setup routine. Exit it as soon as the package has been completely installed.
- License the program components.

2.2 Installing SIMATIC WinCC

Install SIMATIC WinCC on your computer using a setup routine. Local administrator rights are required to perform the installation. Following installation, SIMATIC WinCC must be licensed in order to make the software executable.

NOTE

On a computer with installed licenses, do not run any routines which would modify the partitioning or the structure of the hard disk(s).

Hard-disk maintenance routines, e. g. routines for the repair, defragmentation or partitioning of your hard disk, must be avoided. If you use routines of this type, you run the risk of losing your license! Make sure you temporarily transfer your license back to the license USB stick prior to running a hard disk maintenance routine.

2.2.1 Installation

Before installing SIMATIC WinCC, you must install MS Message Queuing. To install this component, follow the instructions on the SIMATIC WinCC installation DVD.

To install SIMATIC WinCC, proceed as follows:

- \diamond ~ Insert the DVD with SIMATIC WinCC into your DVD drive.
- ♦ Select Start > Run.
- ♦ Enter X:\Start. In this input sequence, X is the letter of your DVD drive.
- ♦ Click OK.
- ♦ Select Install SIMATIC WinCC.
- Follow the installation instructions until the Installation type dialog opens. Select the Package installation and click Next >.
- ♦ In the Program packages dialog, select the WinCC Installation and click Next >.
- ♦ Continue to follow the instructions until the setup routine requests your license.
- ♦ Answer the question whether the license shall be installed during the installation procedure with No. The setup routine skips the licensing.
- ♦ Restart the computer after the installation is completed.

2.2.2 Licensing

You license the product by transferring the license from the license USB stick to your computer. To install your SIMATIC WinCC license, proceed as follows:

- ♦ Plug the license USB stick included in the scope of delivery into the USB interface.
- ♦ Start the Automation License Manager.
- ♦ Transfer the license from the license USB stick to your hard disk.

2.3 Installing SICAM SCC Components

You can install SICAM SCC components on your computer by means of a setup routine. During the installation procedure, the setup routine transfers all the necessary data to your computer. Following installation, the SICAM SCC components must be licensed in order to make them executable.



NOTE

On a computer with installed licenses, do not run any routines which would modify the partitioning or the structure of the hard disk(s).

Hard-disk maintenance routines, e. g. routines for the repair, defragmentation or partitioning of your hard disk, must be avoided. If you use routines of this type, you run the risk of losing your license! Make sure you temporarily transfer your license back to the license USB stick prior to running a hard disk maintenance routine.

2.3.1 Design Variants

To execute the SICAM SCC components you can choose between the following options:

- Demo Mode
- Trial Mode
- Licensed Version

In order to be able to execute all these variants, both SIMATIC WinCC and the SICAM SCC components must be installed. The decision as to which variant you want to use must be made upon the licensing of the SICAM SCC components.



NOTE

If SIMATIC WinCC is not licensed, the restrictions for the non-licensed SIMATIC WinCC apply in addition to the restrictions for non-licensed SICAM SCC components, see SIMATIC WinCC Information System.

Demo Mode

No license for the SICAM SCC components is required for using the Demo mode. The Demo mode is only available for SICAM SCC V8 components (or higher). Components of older SICAM SCC versions, which are still included in the scope of delivery for compatibility reasons, do not support this mode. The following restrictions apply in Demo mode:

- Configuration
 - A note pops up in Demo mode 30 minutes after the start of configuration in the Graphics Designer.
 You can save your picture or exit the Graphics Designer without saving. You must restart the
 Graphics Designer in order to be able to carry out configuration steps during another 30 minutes.
 - A note concerning the use of the Demo mode pops up in the Graphics Designer before saving pictures. This note disappears after 30 seconds and the picture is saved.
 - When calling up a wizard, a note informs you that the license is missing. You have the option to
 activate the trial license. The Demo mode is activated if you click Skip to reject the license. The
 wizards cannot be started in Demo mode.
 - You can also operate the SNMP functions (SICAM Network Manager) using the Trial license or operate them for 30 minutes in Demo mode.

- Runtime
 - When starting the runtime, a note pops up to inform you that the license is missing. You have the option to activate the Trial license. The Demo mode is activated if you click Skip to reject the license. A note pops up to inform you that the software is running in Demo mode.
 - In the Alarm Logging lists, all the logged alarms in the Status and Cause columns are additionally marked with the Demo mode attribute.
 - After using a switching device object, a note is shown every 5 minutes to inform you that you are working in Demo mode. In order to be able to continue operation within the picture, you must click OK to close this note.

Trial Mode

If no applicable license could be found on your computer when starting a SICAM SCC component such as the SICAM PAS Wizard, SICAM SCC offers a trial mode license via the **Automation License Manager**. If you activate this trial mode license, you can use the SICAM SCC component for 14 days. The trial mode license expires after this period. In order to continue to use the full scope of SICAM SCC, you must transfer a standard license without a time limit for the SICAM SCC components, see 2.3.3 Licensing. The trial mode license can only be activated once. The SICAM SCC components change over to Demo mode assoon as the Trial mode period has expired. The SICAM Wizard cannot be started in Demo mode.

Licensed Version

In order to be able to use the **licensed version**, the licenses for the SICAM SCC components must be transferred to your computer, see 2.3.3 Licensing.

2.3.2 Installation



NOTE

Before installing the SICAM SCC components, you must install the SIMATIC WinCC updates. The SIMATIC WinCC updates are available from the *SIEMENS Industry Online Support (SIOS)*. A list of the updates required is provided in the corresponding Readme file.

To install the SICAM SCC components:

- ♦ Insert the SICAM SCC DVD into your DVD drive.
- ♦ Click Start > Run.
- Enter X:\Setup. In this input sequence, X is the letter of your DVD drive.
- ♦ Click OK.

You can select the appropriate components during the custom setup procedure.

♦ Follow the installation instructions.



[Installation_Userdefined, 2, en_US] Figure 2-1 Custom Setup



NOTE

To install only the SICAM Valpro SICAM SCC component on a computer, SIMATIC WinCC does not need to be installed on this computer. During the installation, select only the **Valpro** component.

2.3.3 Licensing

To install the license for your SICAM SCC components:

- ♦ Plug the license USB stick included in the scope of delivery into the USB interface.
- ♦ Start the Automation License Manager.
- ♦ Transfer the license from the license USB stick to your hard disk.

2.3.4 Automated Installation

The SICAM SCC setup also provides (in addition to the standard installation) an automated installation via installation scripts or batch files. The default installation is installed if you choose the automated installation process.

To install SICAM SCC unattended and without user interaction, the following commands are supported:

```
    Installation:
        <Installation medium>\Setup.exe /si
        With changed installation path:
        <Installation medium>\Setup.exe /si "INSTALLDIR=D:\Siemens\...\SCC"
```

• Uninstallation:

```
<Installation medium>\Setup.exe /sx
<SICAM installation directory>\SCC\Setup\Setup.exe /arp /sx
```

```
The default setting for the SICAM installation directory is: %Program-Files(x86)%\Siemens Energy\SICAM
```

e.g. under Windows 7 (64-bit): C:\Program Files (x86)\Siemens Energy\SICAM

You can use the environment variable **%ProgramFiles%** or **%ProgramFiles(x86)%** instead of the textual path and enter it e.g. directly in the address bar of the Windows Explorer or use it in the Windows command line. The variable is automatically translated into the actual path by the system.

You can modify the SICAM SCC installation directory, if required.



NOTE

C:\Program Files (x86) or **C:\Program Files** must be used depending on the operating system (64-bit or 32-bit). The setup uses the registered directory name.



NOTE

Uninstallation via command line is only available if SICAM SCC has also been installed in this mode. During automated installation, the setup does not check if SIMATIC WinCC is installed. Ensure that a SIMATIC WinCC version is installed which is approved for SICAM SCC.



NOTE

Installation via command line installs the standard scope. Adding further components by changing the installation is not possible. In this case, uninstall SICAM SCC and re-install it in normal mode.

2.4 Uninstalling SICAM SCC Components

You can remove the SICAM SCC components from your computer using the uninstall routine. All data installed by the SICAM SCC setup routine will be deleted during uninstallation. You can remove the license for SICAM SCC without using the uninstall routine.

2.4.1 Removing the license

Durch die Übertragung der Lizenz von Ihrem Rechner auf den Lizenz-USB-Stick entfernen Sie die Lizenzierung.



NOTE

The license can also be transferred to another removable medium, e. g. a memory stick.

To remove the license of your SICAM SCC components:

- ♦ Plug the license USB stick included in the scope of delivery into the USB interface.
- ♦ Start the Automation License Manager.
- ♦ Transfer the license from the hard disk to the license USB stick.

2.4.2 Uninstallation

To uninstall the SICAM SCC components:

- Click Start > Settings > Control Panels > Add/Remove Programs.
- ♦ Select SICAM SCC in the list of programs.
- ♦ Click **Remove** to start the uninstall routine.
- ♦ Follow the uninstallation instructions.

2.4.3 Protection against data loss

The uninstallation routine does not remove any files created by the user. Directories including such data are therefore not removed.

2.5 Uninstalling SIMATIC WinCC

SIMATIC WinCC can be removed from your computer using the uninstall routine. During this procedure, all data installed by the setup routine of SIMATIC WinCC will be deleted.

2.5.1 Removing the License

You remove the licensing by transferring the license from your computer to the license USB stick. To remove the license for SIMATIC WinCC, proceed as follows:

- \diamond Plug the license USB stick included in the scope of delivery into the USB interface.
- ♦ Start the Automation License Manager.
- ♦ Transfer the license from the hard disk to the license USB stick.

2.5.2 Uninstallation

There are 2 options to uninstall WinCC: Via the **WinCC product DVD** or via the **Windows Control Panel**.

To uninstall WinCC via the product DVD, proceed as follows:

- ♦ Start the WinCC product DVD.
- ♦ If the autorun function of the operating system is enabled, the DVD is started automatically. If the autorun function is not enabled, start the **Setup.exe** program on the DVD.
- ♦ Follow the on-screen instructions.
- ♦ Select the setup type Uninstall.
- ♦ Select the components to be uninstalled.

To uninstall WinCC via the Control Panel (alternative), proceed as follows:

- ♦ Open the Windows Control Panel via the Start menu.
- ♦ Double-click Add/Remove Programs.
- ♦ Click Modify or Remove Programs.
- ♦ Select the desired entry and click **Remove** or **Modify**.
 The names of all the WinCC components installed start with "SIMATIC WinCC".
- ♦ If WinCC options are installed, uninstall these options first and then uninstall the WinCC version.

Uninstalling Microsoft SQL Server

After uninstalling WinCC you must uninstall the SQL Server instance "WinCC".

♦ Click Control Panel > Programs and Features and select Microsoft SQL Server xxxx for uninstallation.

2.5.3 Protection against data loss

The uninstallation routine does not remove any files created by the user. Directories including such data are therefore not removed.

2.5.4 Virtualization

SICAM SCC supports virtualization with VMWare®.

3 Working with SICAM SCC

3.1	Demo Project	34
3.2	Creating a New Project	35
3.3	Creating a Control Diagram	75
3.4	Creating an overview diagram	87
3.5	Creating a List View	92
3.6	Creating a Button Bar	93
3.7	Creating a Start Screen	96
3.8	Setting up User Authorizations	99

3.1 Demo Project

As soon as SICAM SCC has been installed, a WinCC demo project is available under ...\SICAM\SCC\Samples\. All the major functions of SICAM SCC are implemented in this demo project.

In addition, the demo project includes sample configurations for the functionalities described in this manual. You can simply transfer these sample configurations for use in your projects.

This paragraph provides an example for the implementation of certain functions from the demo project. The demo project provides the following options:

- The demo project is fully dynamized.
- Tags can be modified using the SIMATIC WinCC tag simulation.
- Switch statuses can be simulated in a SICAM structure tag window.
- A field is executable together with the data of the SICAM PAS V8.0 demo project.



NOTE

The demo project is executable with SIMATIC WinCC V7.4 and must neither be edited nor started with an older SIMATIC WinCC version. Read the notes in the file **How to use the demo project.pdf** (in the **DemoSCC** folder).

3.2 Creating a New Project

For each new WinCC project, you must perform frequently repeated operator actions. These actions must be performed in the correct order, because each step is based on the previous one.

If SICAM PAS is mentioned in this section, the same applies to SICAM RTUs and to IEC 61850 and IEC 60870-5-104 devices. Differences will be pointed out.

How to proceed

To create a new WinCC project, you must execute the following steps one after the other:

- Creating a new WinCC project
- Defining computer properties
 Select the WinCC components to be started during runtime. Select the desired runtime language. During the import process, the data is imported in the runtime language defined.
 - Starting the SICAM Wizard

(SICAM Import/Export Wizard, SICAM PAS Wizard, or SICAM IEC Wizard)

The SICAM Wizard supports you in creating a WinCC project by importing configuration data from the target systems. You can visualize items of information from the target systems under SICAM SCC, i. e. for use in process diagrams. In addition to this, it integrates the SICAM-specific extensions into the new WinCC project.



NOTE

If you use the SICAM Import/Export Wizard, you must not use one of the other Wizards additionally - and vice versa. Otherwise the project could be damaged.



NOTE

The SICAM Wizard supports you in creating a new WinCC project. This wizard is an autonomous application started via the WinCC Explorer.

To start the SICAM Wizard:

- To open the WinCC Explorer, click Start > Siemens Energy > SICAM > SCC > SCC.
- In the WinCC Explorer, double-click the SICAM Wizard.



NOTE

The configuration of the SICAM TOOLBOX II and the SCD/ICD/CID files must not include special characters such as \ddot{a} , \ddot{o} , \ddot{u} or β .

If special characters are included, you must modify the coding of the XML file. Change the entry <**?xml version="1.0" encoding="UTF-8"?>** in the first line as follows: <**?xml version="1.0" encoding="iso8859-1"?>**

3.2.1 Creating a New WinCC Project

How to proceed

To create a new WinCC project, click **File > New** in the WinCC Explorer.

Creating a new project

To create a new project, proceed as follows:

Click **File > New** in the WinCC Explorer.

3.2 Creating a New Project

Select your project type from the **WinCC Explorer** dialog, e.g. **single-user project**, and then click **OK** to confirm.



[pascc301, 1, en_US]

Figure 3-1 Selecting a single-user project

♦ The **Create a new project** dialog opens. Specify a **project path** and enter the project name.

Create New Project		×		
Project name: Demo_SCC				
Project path: C:\Users\Public\Documents\Siemens\WinCCProjects New subfolder:				
Demo_SCC				
Help Create	Can	icel		

[pascc302, 1, en_US]

Figure 3-2 Creating a new project

♦ Click Create to create the new project.

3.2.2 Defining Project Properties

In the project properties you define e.g. the operating mode, the design and the hotkeys. You can define **Logon** and **Logoff** hotkeys for your project.

- Logon: Opens a window for logging on a user during Runtime
- Logoff: Opens a window for logging off a user during Runtime

To open the Project Properties dialog:
- ♦ Right-click the project in the WinCC Explorer.
- ♦ Select **Properties** in the context menu.

Project Properties X							
	Operating	g Mode	User Interface ar		terface and	nd Design	
	General	Update Cycl	es	Sho	rtcuts	Options	
	Short speci	cuts are key com fic actions within	bination WinCC.	is to whic	h you can a	assign	
	Actions:						
	Log on				A	Assign	
	Hard copy	n diala an			STRG +	L	
	nunume system	n dialogs			Previously	assigned to:	
	Click here to assign the specified shortcut to the action.						
			ОК	A	bbrechen]	

[pascc302a, 1, en_US]

Figure 3-3 Example, assigning hotkeys

- ♦ For example, you can assign hotkeys for the Logon and Logoff actions.
- ♦ Click **OK** to close the dialog.

3.2.3 Defining Computer Properties

How to proceed

To define the computer properties:

- ♦ Open the **Computer properties** dialog in the WinCC Explorer.
- ♦ Check the computer name in the General tab.
- ♦ Activate the required runtime components in the Startup tab.
- ♦ Select the language of the runtime system in the **Parameters** tab.
- ♦ Set the desired parameters in the **Graphics Runtime** tab.

Opening the Computer properties Dialog

To open the **Computer properties** dialog:

- ♦ Select the **Computer** level in the WinCC Explorer.
- ♦ Right-click the name of the computer.
- ♦ Select Properties in the context menu.



[pascc303, 2, en_US] Figure 3-4 Opening the **Computer properties** Dialog

Checking the Computer Name

In the Computer properties dialog, click the General tab. Next, check whether the correct name of your computer is indicated in the Computer name entry field.

The computer name is entered automatically when creating a new WinCC project.

♦ Enter the name of your computer unless the name has already been entered automatically.

Computer properties	×
General Startup Parameters Graphics Runtime Runtime	
Computer Name: SCCCL35 Use Local Computer Name	
Computer Type: Server WinCC Client	
Server List:	
Name of the computer in the network	
OK Abbrechen Hilfe	

[pascc304, 1, en_US]

Figure 3-5 Checking the Computer Name

Activating Runtime Components

To activate the runtime components:

- ♦ In the Computer properties dialog, click the Startup tab.
- ♦ In the WinCC Runtime Start Up Order section, you can select each runtime component by clicking on the corresponding checkbox. Select further components (if required).

Working with SICAM SCC

3.2 Creating a New Project

Computer properties X						
General Startup Parameters Graphics Runtime Runtime						
WinCC Runtime Start Up <u>O</u> rder:	1					
Alam Logging Runtime Tag Logging Runtime Report Runtime Graphics Runtime Message Sequence Report /SEQPROT User Archive						
	Edi <u>t</u>					
Additional Tasks/Applications:						
	<u>A</u> dd					
	<u>R</u> emove					
	Up					
	<u>D</u> own					
	<u>E</u> dit					
Sequence of WinCC tasks that are started when the WinCC project is activate	ed.					
OK Cance	el Help					

[pascc305, 1, en_US]

Figure 3-6 Activating All Runtime Components

Defining the Runtime Language

It is important to define the runtime language before starting the SICAM Wizard. You specify in which language column of the text library the message texts will be arranged and in which language e.g. the message classes will be created.

To define the runtime language:

- ♦ In the **Computer properties** dialog click the **Parameters** tab.
- ♦ Select the desired language from the **Runtime Default Language** drop-down list box.

Computer properties X						
General Startup Parameters Graphics Runtime Runtime						
Runtime Language: English (United States)	\sim					
Runtime Default Language: English (United States)	~					
Start Information:						
Edit						
Disable Keys:	_					
PLC clock setting:	•					
Central time and date formatting: Configure individual components ISO8601-Force format for all components						
OK Cancel Help)					

[pascc365, 1, en_US]

Figure 3-7 Defining the Runtime Language

Setting the Graphics Runtime Parameters

To set the parameters of the graphics runtime:

♦ In the **Computer properties** dialog, click the **Graphics Runtime** tab.

Working with SICAM SCC

3.2 Creating a New Project

	Startup F	Parameters	Graphics Runtin	ne Runtime		
Project Fi	le:					
C:\Users	<pre>>\Public\D</pre>	locuments\3	Siemens\WinCCF	rojects\Demo_SCC	\Demo_SCC.mcp	
Start Pict	ure:			Start Configuratio	on Menu and Toolbars:	
Window /	Attributes:			Tum Off:		
Title Bord Max Minit Full Scro	der imize mize Screen oll Bar			Alt-F4 Alt-F4 Move Minimize Maximize Close		
	n Distan		•	lades and set Dist	han Mindaun	*
	refin				deu	
Match	n case Control					
Characte	erietice:				L	
Cillaracia				Window on ton:	Keine	
Nom	al		_	Window on top:	Keine	
Norm Norm	al al without	rollback	т	Window on top: ab or alpha cursor:	Keine Keine	
Nom Nom Exter	al al without nded	rollback	T Rur	Window on top: ab or alpha cursor: ntime cursor on/off:	Keine Keine Keine	
Norm Norm Norm Exter Keys:	al al without nded	rollback	T Rur I	Window on top: ab or alpha cursor: ntime cursor on/off: Navigation forward:	Keine Keine Keine Keine	
Norm Norm Exter Keys: Ctrl	al al without nded Up	rollback : Keine	T Rur I Na	Window on top: ab or alpha cursor: ntime cursor on/off: Navigation forward: vigation backward:	Keine Keine Keine Keine Keine	
Norm Norm Keys: Alt	al without nded Up Down	rollback : Keine : Keine	T Rur I Na Naviga	Window on top: ab or alpha cursor: ntime cursor on/off: Navigation forward: vigation backward: ion to start picture:	Keine Keine Keine Keine Keine	
Norm Norm Exter Keys: Ctrl Alt Shift	al without nded Up Down Left	rollback : Keine : Keine : Keine	T Rur Na Naviga	Window on top: ab or alpha cursor: time cursor on/off: Navigation forward: vigation backward: tion to start picture: Retrieve picture:	Keine Keine Keine Keine Keine Keine	
Norm Norm Exter Keys: Ctrl Alt Shift	al without Inded Up Down Left Right	rollback : Keine : Keine : Keine	T Rur Na Naviga	Window on top: ab or alpha cursor: ntime cursor on/off: Navigation forward: vigation backward: ion to start picture: Retrieve picture: Store picture:	Keine Keine Keine Keine Keine Keine Keine	
Norm Norm Exter Keys: Ctrl Alt Shift Tun	al without Inded Down Left Right n on during	rollback : Keine : Keine : Keine g activation	T Rur Na Naviga Buffer siz	Window on top: ab or alpha cursor: ntime cursor on/off: Navigation forward: vigation backward: ion to start picture: Retrieve picture: Store picture: re (No. of pictures):	Keine Keine Keine Keine Keine Keine Keine Keine 30	

[pascc306, 1, en_US]

Figure 3-8 Setting the **Graphics Runtime** Parameters



NOTE

After you have created a start screen in the Graphics Designer, enter its name (e.g. start.PDL) in the **Start screen** entry field of the **Graphics Runtime** tab.

Setting Runtime Parameters

To set the parameters of the graphics runtime:

♦ In the **Computer properties** dialog, click the **Runtime** tab.

Computer properties				×
General Startup Parameters	Graphics Runtime	Runtime		
VBS Debug Options - Graphics: VBS Debug Options - Global Script: Start debugger Start debugger Display error dialog Display error dialog Design settings: Use "WinCC Classic" design Disable shadow Disable background picture / history in picture object Runtime options: Enable monitor keyboard Hardware accelerated graphics representation (Direct2D)				
Activate the runtime system dialogs				_
Picture cache <u>p</u> ath:				
Use picture cache:	Preferred	\sim		
Mouse pointer:				
Action configured:				۶
Editable I/O field and action configured:				F
Editable I/O field:				[
Editable text list object and action configured:				7
Editable text list object:			>	L
		ОК	Cancel Help	>

[sc_prop_runtime, 1, en_US]

Figure 3-9 Setting the **Runtime** Parameters

♦ Click **OK** to close the dialog.

3.2.4 Initializing a WinCC Project

Initialize the new WinCC project with the SICAM Import/Export Wizard, see 7.2.1 SICAM Import/Export Wizard.

i

NOTE

Use the SICAM Import/Export Wizard as the standard wizard (see 7.2.1 SICAM Import/Export Wizard). If required, you can start the SICAM PAS Wizard or the SICAM IEC Wizard from the context menu of the SICAM Import/Export Wizard.

In case you use the old Wizards, be aware of the **station type** which you want to connect to SICAM SCC. The procedures are almost identical and only differ with regard to certain points. The following station types are possible:

- SICAM PAS station, initialization using the SICAM PAS Wizard, see 3.2.4.1 SICAM PAS Station
- SICAM PAS/PQS station or SITIPE, initialization using the SICAM Import/Export Wizard, see 7.2.1 SICAM Import/Export Wizard
- SICAM RTUs, initialization using the SICAM IEC Wizard, see 3.2.4.2 SICAM RTUs
- IEC 60870-5-104 devices, initialization using the SICAM IEC Wizard, see3.2.4.3 IEC 60870-5-104 Devices
- IEC 61850 devices, initialization using the SICAM IEC Wizard, see 3.2.4.4 IEC 61850 Devices
- SICAM SAS station, initialization using the SICAM Global Wizard, see /10/ SICAM SCC for SICAM SAS.

The following section describes details of and differences between the procedures to be applied for the individual station types.

The wizards must**not** be started in the Runtime mode of SIMATIC WinCC. SIMATIC WinCC editors must neither be started nor exited while a wizard is active. They interrupt the interfacing of the wizard, and changes cannot be performed.

The task of the wizard is to import configuration data into a SIMATIC WinCC project and update this data. The update function cannot be used in order to replace existing station data in a SIMATIC WinCC project by completely different data. This also refers to deleted or newly created devices in SICAM PAS or TOOLBOX II projects and SCD files. In these cases you must delete and re-import the imported data using the corresponding wizard.

The **Create SICAM Alarm Logging System** option on pages 4/5 should only be selected to re-create the SICAM Alarm Logging System. To do this, the Alarm Logging message blocks must be removed first. Otherwise, the column headers in the alarm lists may disappear.

Volume Requirements

You can use 8 different IEC 61850 imports as well as 8 T104 imports. You can execute

- 8 different IEC 61850 imports as well as
- 8 IEC 60870-5-104 imports.

1 Import corresponds to:

- 1 SXD file,
- 1 SCL-compliant file (SCD, ICD, CID, or IID) or
- 1 folder with XML files (max. 255)

ProjectIDs are assigned automatically during import, starting with 10.

For SICAM PAS the following applies: 1 import = 1 station. Thus, for mixed operation 9 PAS stations can be imported (max. 25 with PXD import only). For PAS connections the ProjectID is assigned manually in PAS Config.

Hence a maximum of 25 stations (import-data files) can be imported.

The ProjectIDs must be different (they are configured in SICAM PAS). For mixed import with IEC 61850/ IEC 60870-5-104 stations you have to ensure that the ProjectIDs are unique.



NOTE

For IEC 61850 and IEC 60870-5-104 there is a limit of 255 devices per import (station).

3.2.4.1 SICAM PAS Station

Starting the SICAM PAS Wizard

NOTE

Use the SICAM Import/Export Wizard as the standard wizard (see 7.2.1 SICAM Import/Export Wizard). If required, you can start the SICAM PAS Wizard or the SICAM IEC Wizard from the context menu of the SICAM Import/Export Wizard.

- In the WinCC Explorer, double-click SICAM PAS Wizard.
 The SICAM PAS Wizard starts.
- ♦ In the first dialog, click Next.

Entering Station Names and Selecting Parameters

- ♦ In the **1/5** dialog, enter a **name** for the new station and select the **parameters**.
- ♦ Click Next.

Importing Station Data and Selecting Functions

In the **2/5** dialog, enter the components to be imported into the SICAM SCC project using the SICAM PAS Wizard.

- ♦ Select the Import/Update option.
- ♦ Select the path of the SICAM PAS data directory.
- From the selection list, select the file (e.g. station1.PXD) which includes the corresponding SICAM process tags.
- ♦ Select the **functions**.

ts SICAM PAS Wizard 2/5					\times	
Impo	rt Settings specific to	the station				
St	ation name :	SubstationSouth				
C	Create SICAM comp	ponents in project				
· · · · · · · · · · · · · · · · · · ·	Import / Update					
1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	SICAM PAS data fo	lder:				
a A	D:\Import_Data					
Sold States of States	WinCC.pxd				•	
K. K. Y 0	Delete					
Se	elect Function					
111	SICAM Process	Tags				
in the second	SICAM Archives	3				
TT I	SICAM Message	es				
$ 1 \cdot 1 $						
						_
			< Zurück	Weiter >	Abbrechen	

[pascc313, 2, en_US]

Figure 3-10 Defining the Path and the Name of the Import Components

♦ Click Next.

Defining Station Parameters

♦ Define the station parameters in the **3/5** dialog.

Working with SICAM SCC 3.2 Creating a New Project

ta SICAM PAS Wiza	rd 3/5			×
	-Import Settings specific to	the station		
	Station name :	SubstationSouth		
N 100	Station parameters :			
1 × 4.	Channel Unit:		PAS Data Server	•
	Logical Connection		SubstationSouth	•
			< Zurück Weite	r > Abbrechen

[pascc314, 1, en_US]

Figure 3-11 Defining Station Parameters for SICAM PAS

♦ Click Next.



[[]pascc320, 1, en_US]

Figure 3-12 Note Regarding Connection Parameters

Check the connection parameters after terminating the SICAM PAS Wizard – see 3.2.5 Connection Parameters.

Initializing the Project

- ♦ Define the project-specific settings in the 4/5 dialog.
- ♦ Click Next.
- ♦ In the **5/5** dialog, click **Finish**.

♦ Continue as described in 3.2.5 Connection Parameters.

3.2.4.2 SICAM RTUs

Starting the SICAM IEC Wizard



NOTE

Use the SICAM Import/Export Wizard as the standard wizard (see 7.2.1 SICAM Import/Export Wizard). If required, you can start the SICAM PAS Wizard or the SICAM IEC Wizard from the context menu of the SICAM Import/Export Wizard.

♦ In the first dialog, click Next.

Selecting the Station and Parameters

SICAM IEC Wizard 1	/5	×
	gemeine Einstellungen NinCC Projekt: \\V75-W10\WinCC_Project_Demo_SCC_1\Demo_SCC.mcp	-
	Stationsauswahl : Neue Station im Projekt anlegen Stationstyp TOOLBOX II / IEC 61850 SICAM_RTU Vorhandene Station auswählen Parameter : Sonderzeichenersetzung : SICAM ab V5.0 konform SICAM Reporterausgabe Nur Wamungen/Fehler anzeigen	
	< Zurück Weiter > Abbrech	nen

[pascc311_1703, 1, en_US]

Figure 3-13 Selecting the Station and Parameters

- In the 1/5 dialog, select the Station type (type of the file to be imported).
 TOOLBOX II / IEC 61850
 Import of an *.sxd file with IEC 61850 data from a SICAM TOOLBOX II.
 TOOLBOX II / IEC 60870-5-104
 Import of an *.sxd file with IEC 60870-5-104 data from a SICAM TOOLBOX II.
- ♦ Enter a name for the new station.
- ♦ Select the Parameters.
- ♦ Click Next.

Importing Station Data and Selecting Functions

In the **2/5** dialog, enter the components to be imported into the SICAM SCC project using the SICAM IEC Wizard.

- ♦ Select the Import/Update option.
- \diamond Select the path of the data directory.
- ♦ From the selection list, select the file (e.g. station1.SXD) which includes the corresponding SICAM process tags.
- ♦ Select the **functions**.

📆 SICAM IEC Wizard	2/5	<
	mport Settings specific to the station	
	Station name : SICAM_RTU	
	C Create SICAM components in project	
× 2.	Import / Update TOOL BOX II / IEC 61850 data folder:	
L. K	D:\Import_Data	
	SICAM_RTU.sxd	
~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~	C Delete	
·	Select Function	
	SICAM Process Tags	
	SICAM Archives	
計 1	✓ SICAM Messages	
	< Zurück Weiter > Abbrechen	
[pascc311 1703 2, 1, en US]		_

Figure 3-14 Defining the Path and the Name of the Import Components

♦ Click Next.

#### **Defining Station Parameters**

♦ Define the station parameters in the 3/5 dialog.

🗱 SICAM IEC Wizard 3/5				
	- Import Settings specific to	the station		
	Station name :	Substation_East		
	Station parameters :			
A / A.	Channel Unit:	IEC 61850 Data Server		
	Logical Connection	Substation East		
		< Zurück Weiter > Abbrechen		

[pascc314_1703, 1, en_US]

Figure 3-15 Defining Station Parameters for SICAM RTUs

The Channel Unit is pre-selected according to the selected Station type.

When importing TOOLBOX II data (*.sxd) only information for the selected protocol is imported.

♦ Click Next.

To connect SICAM RTUs, no connection parameters need to be configured. These parameters are included in the SXD file and are stored in a configuration file for the channel.

# Initializing the Project

- ♦ Define the **project-specific settings** in the **4/5** dialog.
- ♦ Click Next.
- ♦ In the 5/5 dialog, click Finish.
- ♦ Continue as described in 3.2.5 Connection Parameters.

## 3.2.4.3 IEC 60870-5-104 Devices



#### NOTE

For importing IEC 60870-5-104 data from a DIGSI/XML file, you require the separate SCC IEC 60870-5-104 data import license.

#### Starting the SICAM IEC Wizard

To start the SICAM IEC Wizard:

♦ In the WinCC Explorer, double-click SICAM IEC Wizard. The SICAM IEC Wizard starts.

locuments/Siemens/WinCCProjects/Demo_SCC_V902_WinCC_V74/Demo_SCC.mcp 🕼 🕼					
File Edit View Tools Help					
□ ▷   ■ ▶   X 晅 頂  出 凸 > 録	?				
🖃 📑 Demo_SCC	Name				
Graphics Designer					
Menus and toolbars					
Tag Logging					
SICAM Network Manager					
SICAM IEC Wizard					
SICAM PAS Wizard					
SICAM TEA-X Wizard					
Global Script					
Text Library	Keine Objekte vorhanden				
\min User Administrator					
Cross-Reference					
() Horn					

[pascc310_1703, 1, en_US]

Figure 3-16 Calling up the SICAM IEC Wizard

♦ Click **Next** in the subsequent dialog.

#### Selecting the Station and Parameters

SICAM IEC Wizard 1/5		$\times$
General S WinCC	Settings Project: CL35\WinCC_Project_Demo_SCC_2\Demo_SCC.mcp	
Select ©	Station : Create new station in project Station type XML / IEC 60870-5-104 SubstationEast Select existing station	
Parame	ters : Replace Special Characters : conform to SICAM from V5x	
	< Zurück Weiter > Abbreche	n I

[scc_104_02, 2, en_US]

Figure 3-17 Selecting the Station and Parameters

- ◇ In the 1/5 dialog, select the Station type (type of the file to be imported).
   · XML / IEC 60870-5-104
   Importing *.xml files from DIGSI
- ♦ Enter a name for the new station.
- ♦ Select the Parameters.
- ♦ Click Next.

# Importing Station Data and Selecting Functions

In the **2/5** dialog, enter the components to be imported into the SICAM SCC project using the SICAM IEC Wizard.

- ♦ Select the Import/Update option.
- Store the XML files for each IEC 60870-5-104 station in a separate subdirectory.
   Select the path where the XML files of the station to be imported are stored.



# NOTE

If more than 255 XML files are stored in the specified path, only the first 255 files are imported.

♦ Select the **functions**.

🚡 SICAM IEC Wizar	rd 2/5	×
	Import Settings specific to the station Station name : SubstationEast Create SICAM components in project Import / Update XML / IEC 60870-5-104 data folder: E:\ImportDaten\T104 C Delete Select Function I SICAM Process Tags I SICAM Archives I SICAM Messages	
	< Zurück Weiter >	Abbrechen

[scc_104_03, 2, en_US] Figure 3-18 Defining the Path of the Import File

♦ Click Next.

# **Defining Station Parameters**

♦ Define the station parameters in the 3/5 dialog.

ta SICAM IEC Wizar	d 3/5		Х
	-Import Settings specific to t	the station	
	Station name :	SubstationEast	
<b>.</b>	Station parameters :		
1 1 20	Channel Unit:	IEC 60870-5-104 Data Server	
. Chil	Logical Connection:	Substation East	
		< Zurück Weiter > Abbrechen	

[scc_104_04, 2, en_US]

Figure 3-19 Defining Station Parameters for IEC 60870-5-104 Devices

The **Channel Unit** is pre-selected according to the selected **Station type**.

The **Logical Connection** is derived from the station name when setting up a new station. It only may be adjusted before the first import.

♦ Click Next.

# **Initializing the Project**

- ♦ Define the **project-specific settings** in the **4/5** dialog.
- ♦ Click Next.
- ♦ In the 5/5 dialog, click Finish.
   The SICAM IEC 60870-5-104 Wizard starts.

# **Editing Device Data**

The **SICAM IEC 60870-5-104 Wizard** provides a mapping interface for the DIGSI/XML import where you can select the information to be created in SICAM SCC. In addition, you can configure device and connection parameters in the Expert view.

		SIEMENS	
evice selecti	on	SICAN	A SCC - IEC104 device mapp
Use	Name	T104 Station	IP-address
V	R7_7SL87_133	0	172.17.17.140:2404
1	R7_7SL87_134	0	192.168.17.141:2404
			Next > Can

Figure 3-20 SICAM IEC 60870-5-104 Wizard, Selecting Devices

i

# NOTE

For the first import all devices from the import directory are displayed. You can only select devices with the same station number. When updating the station, only devices with this station number are displayed.

If only 1 XML file is available in the directory, no device selection is displayed.

- Select the devices whose data you want to import with the SICAM IEC Wizard.
- ♦ Click Next.

The next dialog opens.

♦ Select the Mapping tab.

In the Mapping tab, all the tags from the imported XML files are displayed device-specifically.

# NOTE

#### Updating a Device or the Station

To perform an update of already imported devices or of the complete station with changed device address parameters (XML section **[LANConnection]**), you have to manually adjust the address parameters in the Wizard UI; alternatively, you delete the corresponding devices or the complete station with the Wizard and re-import them before the update.

Since the device address parameters can be adjusted in the Wizard UI, they are stored persistently after the import and considered as reference. Thus, they are not overwritten when import files are changed.

					SIEME	NS SICAM SCC	IEC104 data n	aanni
ice list	Mapping	Device settings	Global settings	Expert view		SICAW SCC.		liappi
* * .							Search for	
Single devices								
	🕑 Moni	toring direction						
R7_7SL87_134	Use	<ul> <li>ASDU</li> </ul>	Name		Alarm logging (3)	Tag management (3)	Tag logging	
		1	FG1_Line\FN1_OM	V_OpVal_3ph\FB1_OpMeas				
		1	FG1_Line\FN1_OM	V_OpVal_3ph\FB1_OpMeas				
		1	FG1_Line\FN1_OM	V_OpVal_3ph\FB1_OpMeas				
	<b>V</b>	1	FG1_Switch\FB1_C	SWI\Pos	<b>V</b>			
		1	FG1_TapChanger\F	B1_YLTC\TapChg				
		1	FG2_ComModule\	FB0_ComModule\RDY				
		1	FG2_ComModule\	FN1_ComChannel\FBComP				
		1	FG2_ComModule\	FN1_ComChannel\FBComP				
		1	FG2_Switch\FB1_C	SWI\Pos				
		1	LLN0_Application\	LEDRs				
	Comr	mand direction						
	Use	ASDU	Name		Alarm logging (1)	Tag management (1)		
		1	c_LLN0_Applicatio	n\ProtOnOff				
		1	c_LLN0_Applicatio	n\SGroup1				
		1	c_LLN0_Applicatio	n\SGroup2				
		1	c_LLN0_Applicatio	n\SGroup3				
		1	c_LLN0_Applicatio	n\SGroup4				
	<b>V</b>	1	c_FG1_Switch\FB1_	CSWI\Pos	<b>V</b>	<b>V</b>		
		1	c_FG2_Switch\FB1_	CSWI\Pos				
		1	c_FG1_TapChanger	\FB1_YLTC\TapChg				
		1	c_FB1_MVAL\SetCr	ntVal				
		1	a EG1 Lina/ENI1 O	M// Enormy 2nh/ED1 OnM		[m]		

[scc_104_06, 2, en_US]

Figure 3-21 SICAM IEC 60870-5-104 Wizard, Selecting Tags

The device list on the left-hand side of the dialog shows all the devices which have been selected in the Use column of the device selection.



# NOTE

You can combine devices to groups in order to be able to select several devices at the same time, see *Figure 3-25*.

♦ Select a device.

The tags of this device are shown in a list on the right-hand side of the window.

In the Alarm logging, Tag Management, and Tag logging columns, select the WinCC components, or in the Use column select the process tags that you want to import with the SICAM IEC Wizard.

Right-clicking the column heading of the **Monitoring direction** or **Command direction** lists opens a context menu. This allows you to show additional columns in the lists in order to display the names modified for SIMATIC WinCC.

By clicking Additional columns you can show or hide all columns at once.

The additional columns are:

- For Alarm Logging: the Message Group and Message Text columns.
- For Tag Management: the columns Variable group and Process information.
- For Tag Logging: the Tag logging hierarchy and Tag logging information columns.

The texts for these columns are created when selecting a process tag for the tags (components).

fil g						
devices						Search for
7SL87 133	onitoring	direction				
7_134 Use	•	ASDU	Name	Alarm logging (3)	Message group	Message text
		1	_ComFault	<b>V</b>	SubstationEast_R7_7SL87_133	ComFault
	1	1	_OprReady	<b>v</b>	SubstationEast_R7_7SL87_133	OprReady
	1	1	FG1_Switch\FB1_CSWI\Pos	<b>√</b>	SubstationEast_R7_7SL87_133	R7_7SL87_133_FG1_Switch\FB1_CSWI\Pe
		1	FB1_MVAL\CntRs1			
		1	FB1_MVAL\ExtError			
		1	FB1_MVAL\SetCntVal			
		1	FG1_Breaker_1pol\FB1_CSWI\Pos			
		1	FG1_Breaker_1pol\FB1_XCBR\DefTr			
	[mm]					
		1	FG1_Breaker_1pol\FB1_XCBR\Pos			
٩		1	FG1_Breaker_1pol\FB1_XCBR\Pos			
•	ommand	1 direction	FG1_Breaker_1pol\FB1_XCBR\Pos			
<ul> <li>✓ Co</li> <li>Use</li> </ul>	ommand	1 direction ASDU	FG1_Breaker_1pol\FB1_XCBR\Pos	arm logging (1) Mess	sage group Mess	age text T
∢ Use	ommand	1 direction ASDU 1	FG1_Breaker_1pol/FB1_XCBR\Pos	arm logging (1) Mess	sage group Mess	age text T
<ul> <li>✓ Co</li> <li>Use</li> </ul>	ommand	1 direction ASDU 1 1	FG1_Breaker_1pol/FB1_XCBR/Pos	arm logging (1) Mess	sage group Mess	age text T
<ul> <li>✓ Cc</li> <li>Use</li> </ul>	ommand	1 direction ASDU 1 1 1	FG1_Breaker_1pol/FB1_XCBR/Pos	arm logging (1) Mess	sage group Mess	age text T
<ul> <li>✓ Co</li> <li>Use</li> </ul>	emmand	1 direction ASDU 1 1 1 1 1	FG1_Breaker_1pol\FB1_XCBR\Pos   Name  Ala  (FG1_Line\FN1_OMV_Energy.3ph\FB1_OPM  (FG1_Line\FN1_OMV_Energy.3ph\FB1_OPM  (FG1_Line\FN1_OMV_Energy.3ph\FB1_OPM  (FG1_Sine\FN1_OMV_Energy.3ph\FB1_OPM  (FG1_Sine\FN1_CSW\F0s)	arm logging (1) Mess	sage group Mess stationEast_R7_7SL87_133 R7_7	age text T SL87_133_c_FG1_Switch\FB1_CSWI\Pos
∢ ♥ Cc Use	emmand	direction ASDU 1 1 1 1 1 1 1	FG1_Breaker_1pol\FB1_XCBR\Pos           III           Name         Ala           c_FG1_Line\FN1_OMV_Energy_3ph\FB1_OpM           c_FG1_Line\FN1_OMV_Energy_3ph\FB1_OpM           c_FG1_Line\FN1_OMV_Energy_3ph\FB1_OpM           c_FG1_Line\FN1_OMV_Energy_3ph\FB1_OpM           c_FG1_Suich\FB1_CSWIPos           c_FG1_TapChanger\FB1_YUTC\TapChg	arm logging (1) Mess	sage group Mess stationEast_R7_7SL87_133 R7_7	age text T SL87_133_c_FG1_Switch\FB1_CSW1\Pos
< ♥ Ca Use	ommand	1 direction ASDU 1 1 1 1 1 1 1 1 1	FG1_Breaker_1pol\FB1_XCBR\Pos Name  ✓ Ala C_FG1_Line\FN1_OMV_Energy_3ph\FB1_OPM C_FG1_Line\FN1_OMV_Energy_3ph\FB1_OPM C_FG1_Line\FN1_OMV_Energy_3ph\FB1_OPM C_FG1_Switch\FB1_CSWI\Pos C_FG1_Switch\FB1_CSWI\Pos	arm logging (1) Mess	sage group Mess stationEast_R7_7SL87_133 R7_7	age text T SL87_133_c_FG1_Switch\FB1_CSWI\Pos
< ♥ Cc Use	ommand	1 direction ASDU 1 1 1 1 1 1 1 1 1 1	FG1_Breaker_1pol/FB1_XCBR/Pos  Name  Ala C_FG1_Line\FN1_OMV_Energy.3ph/FB1_OpM C_FG1_Line\FN1_OMV_Energy.3ph/FB1_OpM C_FG1_Line\FN1_OMV_Energy.3ph/FB1_OpM C_FG1_Switch/FB1_CSWI/Pos C_FG1_Switch/FB1_CSWI/Pos C_LLN0_Application/LEDRs	arm logging (1) Mess	sage group Mess stationEast_R7_7SL87_133 R7_7	age text T SL87_133_c_FG1_Switch\FB1_CSWI\Pos
<ul> <li>✓ Cc</li> <li>Use</li> </ul>		1 direction ASDU 1 1 1 1 1 1 1 1 1 1 1 1 1	FG1_Breaker_1pol\FB1_XCBR\Pos Name  Ala  C_FG1_Line\FN1_OMV_Energy.3ph\FB1_OPM  C_FG1_Line\FN1_OMV_Energy.3ph\FB1_OPM  C_FG1_Line\FN1_OMV_Energy.3ph\FB1_OPM  C_FG1_ENE\FN1_OMV_Energy.3ph\FB1_OPM  C_FG1_Switch\FB1_CSW\Pos  C_FG1_TapChanger\FB1_VIC\TapChg  C_FG2_Switch\FB1_CSW\Pos  C_LLN0_Application\LEDRs  C_LLN0_Application\LEDRs	erm logging (1) Mess	sage group Mess stationEast_R7_7SL87_133 R7_7	age text T SL87_133_c_FG1_Switch\FB1_CSWI\Pos

[scc_104_08, 2, en_US]

Figure 3-22 SICAM IEC 60870-5-104 Wizard, Showing Additional Columns

♦ Activate the **Expert view** in order to select the **Device Settings** and **Global settings** tabs.

## **Device- and Driver-Specific Settings**

♦ Select the **Device settings** tab.

📆 SICAM IEC 60870-5-104 W	fizard	- 🗆 X
Device list	Manning Device settings Global settings	SIEMENS SICAM SCC - IEC104 data mapping
+ 🔍 🗶 🛅 🖕		
4. Simple devices	Topology head component	1.0
T Single devices	Topology redundant head component	NO
R7_75L07_155	Topology subcomponent	NO
K/_/SL8/_134	Topology redundant subcomponent	NO
	Mode data flow	CONTROLLING
	System type	ACP
	Cause of transmission (COT)	2BYTE
	GDK_1703_ADRTYP	PTA
	Topology time master	NO
	Remote IP address	172.17.17.140:2404
	Redundant remote IP address1	0.0.0:0000
	Redundant remote IP address2	0.0.0:0000
	Redundant remote IP address3	0.0.0.00000
	Timeout connection setup t0	30
	Timeout transmit t1	15
	Timeout transmit acknowledge t2	10
	Timeout connection check t3	20
	Max. no. of APDUs until acknowledgement (k)	12
	number of APDUs until acknowledgement (w)	8
	Topology head component Topology head component	
Devices: 1 / 2	Use: 4 / 93 File: E\ImportDaten\T104	< Back Finish Cancel

[scc_104_10, 2, en_US]

Figure 3-23 SICAM IEC 60870-5-104 Wizard, Showing Device Settings

The settings of the selected device are displayed. They correspond to the parameters in the XML file.

♦ Select the Global Settings tab.

ta SICAM IEC 60870-5-104 W	Vizard	– 🗆 X
Device list	Mapping Device settings Global settings If Expert view	SIEMENS SICAM SCC - IEC104 data mapping
+ * X 🗉 🛓	Ignore confirmation/termination	0
A Single devices	Frame throughput	0
R7 7SL87 133	Timeout startup	0
R7 75187 134	Inter COT	0
	IVBit2AS	0
	Originator address state	0
	Own originator address	0
	OV distract	1
	Ring level indication	70
	SSI_32bit send mode	2
	Status mask	fffffffffffffffffffff
	Watchdog interval	0
	GW1703Default	
	Confirmation timeout	5
	IEC controls	NO
	LAN type	ET
	Own IP address	
	Own topology	1,8
	Send cyclic timeset	NO
	Server IP address	
	Server name	
	Standby server IP address	
	Standby server name	
	System time setting	NO
	□ IEC	
	Ignore confirmation/termination Ignore confirmation/termination (COT7, COT10) default = No (Yes = the value is ignored for COT7 and COT10) Values/Ranges: [0] No [1] Yes	< Back Finish Cancel
Devices: 1 / 2	Use: 4 / 93 File: E:\ImportDaten\T104*.xm	l a

[scc_104_11, 2, en_US]

Figure 3-24 SICAM IEC 60870-5-104 Wizard, Showing Global Settings

The general, device-independent settings are displayed.

You can only define these parameters in the first station imported into your project. They are valid for all the IEC 60870-5-104 stations of this project. Changes in other stations are ignored.



# NOTE

The significance of these parameters corresponds to the significance of the parameters in the SICAM TOOLBOX II. No settings are required.

Click Finish to close the dialog.
 This starts the device data import.

#### **Combining Devices into Groups**

After the first start of the SICAM IEC 60870-5-104 Wizard, all previously selected devices (Figure 3-21) are listed in the device list under **Single Devices**. You can now combine devices into groups and then select tags for several devices at the same time.

The settings of the first device of the group are transferred automatically to the devices which are subsequently added to the group.

To combine devices into groups, use the context menu, the Drag&Drop function or the toolbar. Make sure that you only combine devices of the same type and with the same data points. Each device group must be assigned a unique name.

ice list			Mapping	Device settings	Global settings		SIE	MENS SICAM	SCC - IE	EC104 data	mapp
		B								Search for	
R7_75L87_133		Monito									
Single o	devic	es	Use	ASDU	Name 🝷	Alarm logging	Tag management	Tag logging			
10	251.5	1 12/1			FG1 Line\FN1 OMV OpVal 3ph\FB1 OpMeas						
	+	Add to ne	w group	CTRL+N	FG1 Line\FN1 OMV OpVal 3ph\FB1 OpMeas						
		Add to		•	FG1_Line\FN1_OMV_OpVal_3ph\FB1_OpMeas			E			
	R	Remove		Del	FG1_Line\FN1_OMV_OpVal_3ph\FB1_OpMeas			(f ⁽¹⁾ )			
					FG1_TapChanger\FB1_YLTC\EndPosL						
		Rename g	roup	F2	FG1_TapChanger\FB1_YLTC\EndPosR						
	v	<b>C</b> -4	CTDL V		FG1_TapChanger\FB1_YLTC\HigCmd						
	*	Cut		CTRL+X	FG1_TapChanger\FB1_YLTC\LowCmd						
	12	Paste	CTRL+V		FG1_TapChanger\FB1_YLTC\TapChg						
				2	FG1 TapChanger\FB1 YLTC\TapErrRs						
				2	FG2 ComModule/EN1 ComChannel/EBComP		m				
			00	1.0							
			Commi	and direction				17			
			Use	ASDU	Name	Alarm logging	Tag management				
				2	c_LLN0_Application\SGroup3						
				2	c_LLN0_Application\SGroup4						
				2	c_FG1_TapChanger\FB1_YLTC\TapChg						
				2	c_FG1_TapChanger\FB1_YLTC\TapErrRs						
				2	c_FB1_MVAL\SetCntVal						
				Z	c_FG1_Line\FN1_OMV_Energy_3ph\FB1_OpM						
				2	c_FG1_Line\FN1_OMV_Energy_3ph\FB1_OpM						
				2	c_FG1_Line\FN1_OMV_Energy_3ph\FB1_OpM						
				2	c_FG1_Line\FN1_OMV_Energy_3ph\FB1_OpM						
										( m · · ·	C

[scc_104_12, 2, en_US]

Figure 3-25 SICAM IEC 60870-5-104 Wizard, Combining Devices into Groups



# NOTE

The handling of the SICAM IEC 60870-5-104 Wizard is similar to the handling of the Windows Explorer

To edit a device group:

 $\diamond$  Select the device group.

The data points of the devices in the group are displayed.

In the Alarm Logging, Tag Management, and Tag Logging columns, select the tags to be imported using the SICAM IEC Wizard.

The selection applies to all the devices in the group.

The devices of a group cannot be edited individually. If you remove a device from the group, it is displayed under **Single Devices** once again and can be edited separately. The device maintains the current parameter settings.

#### 3.2.4.4 IEC 61850 Devices



# NOTE

For importing IEC 61850 data from an ICD/IID/CID/SCD file, you require the separate **SCD import for IEC** 61850 communication license.



# NOTE

When importing an IEC 61850-SCL file, up to 50 reports per device can be included.



# NOTE

A static dataset can contain at most 499 process data-points. If static data records are used in your protection device connected via IEC 61850, you must make sure that all the information defined in SICAM SCC is also defined in the parameters of the static data record of your device. If information is missing, the driver switches to cyclic polling. In this case, the correct logging of information in your message lists cannot be ensured.



# NOTE

For **IEC 61850 tools** such as the **SysCon**, Client ICD files for SICAM SCC are included on the DVD (directory: ProductEnhancements\IEC61850).

These files can be imported into the SysCon. When assigning information to a SICAM SCC, you can select **SCC-relevant** during the SCD import. This ensures that only the information assigned in SysCon is imported.

# Special Treatment for Enumerated CDC Types

When importing an ENUM tag, a special message is created in the AlarmLogging for each ENUM value. The description of the ENUM value is integrated in the message text. One message of the current ENUM value each is logged as raised, and the previous message is logged as cleared. Enumerated CDCs are e.g. the direction information of a general pickup.

If a general pickup is triggered during operation, all the messages are transmitted to SICAM SCC and are entered in the message lists in case of status changes (e.g. interruption of connection).

Only one single tag is created in the Tag Management. Its runtime value corresponds to the ENUM value. The significance is defined in the device configuration, e.g. in DIGSI, from where it can be transmitted. The ENUMs are also described in the SCL import file.

# Starting the SICAM IEC Wizard

To start the SICAM IEC Wizard:

♦ In the WinCC Explorer, double-click SICAM IEC Wizard. The SICAM IEC Wizard starts.

\land WinCCExplorer - C:\Users\Public\Documents\Siemens\WinCCP	rojects\Demo_SCC_V902_WinCC_V74\Demo_SCC.mcp
File Edit View Tools Help	
🗋 🕞   🔳 🕨   X 🗎 🏢 🖽   出 い 🌫 該 🧱 👔   🖀	?
⊡ 🔂 Demo_SCC	Name
Menus and toolbars	
Tag Logging	
SICAM Network Manager	
👫 SICAM IEC Wizard	
SICAM PAS Wizard	
SICAM TEA-X Wizard	
📲 🖓 🖓 Global Script	
Text Library	Keine Objekte vorhanden
📲 Text Distributor	
🛶 🎁 User Administrator	
🖓 Cross-Reference	
User Archive	

[pascc310_1703, 1, en_US]

Figure 3-26 Calling up the SICAM IEC Wizard

♦ Click Next.

#### Selecting the Station and Parameters

🖏 SICAM IEC Wizard 1/5	Х
General Settings WinCC Project: \\V75-W10\WinCC_Project_Demo_SCC\Demo_SCC.mcp	
Select Station : Create new station in project Station type SCL / IEC 61850 SubstationEast C Select existing station Substation_North Parameters : Replace Special Characters : Conform to SICAM from V5.x	
Show warnings/errors only	

[scc_61850_02, 2, en_US]

Figure 3-27 Selecting the Station and Parameters

- In the 1/5 dialog, select the Station type (type of the file to be imported).
   SCL / IEC 61850
  - Import of SCL-compliant files (*.scd,*.icd,*.cid,*.iid).
- $\diamond$  Enter a **name** for the new station.
- ♦ Select the Parameters.
- ♦ Click Next.

# Importing Station Data and Selecting Functions

In the **2/5** dialog, enter the components to be imported into the SICAM SCC project using the SICAM IEC Wizard.

- ♦ Select the Import/Update option.
- ♦ Select the path under which the ICD/IID/CID/SCD file is stored.

An ICD/CID file includes the data of **one** IEC 61850 device; an SCD file includes the data of one or **several** IEC 61850 devices.

- $\diamond$  Select the file to be imported.
- ♦ Select the **functions**.

🔚 SICAM IEC Wizard	1 2/5	×
	Import Settings specific to the station Station name : SubstationEast C Create SICAM components in project Import / Update SCL / IEC 61850 data folder: D:\Import_Data SysKon_SIP5_SCC.scd C Delete Select Function SICAM Process Tags SICAM Archives SICAM Messages	
	< Back Next > Car	ncel

[scc_61850_03, 2, en_US]

Figure 3-28 Defining the Path and the Name of the Import Components

♦ Click Next.

# **Defining Station Parameters**

 $\diamond$  Define the station parameters in the 3/5 dialog.

🖬 SICAM IEC Wizar	d 3/5		$\times$
	-Import Settings specific to	the station	
	Station name :	SubstationEast	
<b>N</b> (1997)	Station parameters :		
1 / A.	Channel Unit:	IEC 61850 Data Server	
N.65.7	Logical Connection:	Substation East	
State 2			
1.5			
m - 1			
2.35			
P STATE			
		< Back Next > Cancel	

[scc_61850_04, 1, en_US]

Figure 3-29 Defining Parameters for IEC 61850 Devices

The Channel Unit is pre-selected according to the selected Station type.

The **Logical Connection** is derived from the station name when setting up a new station. It only may be adjusted before the first import.

 $\diamond$  Click Next.

To connect IEC 61850 devices, set the connection parameters (when importing an ICD file) in the SICAM IEC61850 Wizard, if required. The connection parameters are included in the CID/SCD file and are applied by the SICAM IEC61850 Wizard.

## **Initializing the Project**

- ♦ Define the project-specific settings in the 4/5 dialog.
- ♦ Click Next.
- ♦ In the 5/5 dialog, click Finish.

The SICAM IEC61850 Wizard starts.

#### **Editing Device Data**

The **SICAM IEC61850 Wizard** provides an SCD import mapping interface where you can select the information to be created in SICAM SCC. In addition, you can configure device and connection parameters in the Expert view.

ta SICAM IEC 61850 Wizard Х _ SIEMENS SICAM SCC - IEC61850 data mapping Device selection Use Name Description Device type IP-address ~ SIP_E SIP_7SL87 7SL87 172.17.17.199 -SIP_J SIP_7SL87 7SL87 172.17.17.198 Next > Cancel 2 / 2 File: D:\Import_Data\SysKon_SIP5_SCC.scd Devices:

[scc_61850_05, 1, en_US]

Figure 3-30 SICAM IEC61850 Wizard, Selecting Devices

If the imported file only contains 1 device the device selection is not displayed.

♦ Click Next.

The next dialog opens.

- ♦ To view all information, activate the Expert view.
- ♦ Select the Mapping tab.

With the options **Telegram addresses** and **Descriptions** you can define the display of the second column. The texts shown for the process tags are transferred from the ICD/SCD file.

ta SICAM IEC 61850 Wizard						-		×
				SIEMENS				
Device list	Mapping Device settings Global	settings 🗹 Expert view		SICA	M SCC - IEC6	51850 data	mappi	ing
+ × X III -	Filter for 🗸 Static dat	asets SCC relevant				Search for		Q
Single devices	Show objects of import file with							
SIP_E (SIP_7SL87) SIP_J (SIP_7SL87)	telegram addresses	IP-ad	dress: 172	2.17.17.199				
	O descriptions	ate SCC-texts Devic	e type: 7SL8	7				
	Monitoring direction	A.I	lancing (2)	T	Tradensian			
	Ose Telegram address	Alarm		lag management (2)	lag logging		_	
		Le JT-tOut-st) (-1						
	Application/LLNU	Contraction Contraction						
		-swautn.stvai						
		stval						
		- NAL						
		-1)/-1						
		stval						$\sim$
	Command direction							
	Use Telegram address	Alarm	logging (2)	Tag management (2)				
	Application/c LL	IO.LEDRs.ctlVal						
	CB1/c CSWI1.Pos	.ctlVal	<ul> <li>Image: A start of the start of</li></ul>	<ul> <li>Image: A start of the start of</li></ul>				
	CB1/c CSWI1.Loc	Sta.ctlVal						
	✓ Dc1/c_CSWI1.Pos	.ctlVal	$\checkmark$	$\checkmark$				
	Tap1/c_YLTC1.Tap	Chg.ctlVal						
	Tap1/c_YLTC1.Tap	Chg.minVal						
	Tap1/c_YLTC1.Tap	Chg.maxVal						
					< Back	Finish	Cance	el
Devices: 1 / 2	Use: 4 / 3	4 File: D:\Import_I	Data\SysKon_S	SIP5_SCC.scd				ы

[scc_61850_06, 1, en_US]

Figure 3-31 SICAM IEC61850 Wizard, Selecting Tags

A list of all the previously selected devices is shown on the left-hand side in the window.



#### NOTE

You can combine devices into groups in order to be able to select several devices at the same time, see *Figure 3-37*.

#### **Static Datasets**

If you activate this option, only the information points are shown that are available via static datasets in the SCD file.

If a device does not support dynamic datasets, you can only select the data for import which are defined in the static datasets. In this case, you cannot deactivate this option.

A static dataset can contain at most 499 process data-points.

#### SCC relevant

If you activate this option, only the information points are shown that have been assigned to one or more clients in SYSCON.

If this option is active, the Static Datasets option will not be considered.

- Select a device.
   The tags of this device are shown in a list on the right-hand side in the window.
- In the Alarm logging, Tag Management and Tag logging columns, select the WinCC components, or in the Use column, select the process tags which you want to import with the SICAM IEC Wizard.

र्देह SICAM IEC 61850 Wizard						_		×
Device list	Manning Davi		iens,	SIEMENS SICAI	M SCC - IEC	61850 data i	mappir	ng
+ 🔍 🕺 🛅 📮	Filter for	✓ Static datasets     ✓ SCC relevation	int			Search for	C	2
SIP_J (SIP_7SL87)	<ul> <li>telegram</li> <li>description</li> </ul>	addresses Update SCC-texts	IP-address: 172 Device type: <b>75L8</b>	2.17.17.199 <b>7</b>				
	Monitoring	g direction	1					
	Use	Description •	Alarm logging (5)	Tag management (5)	Tag logging		^	×
	✓	Anwendung/Allgemein.LED rückgesetzt	~	~				
	~	Anwendung/Allgemein.LED rücksetzen	~	~				
		Anwendung/Allgemein.Schalthoheit						
		ComFault						
		GIStatus						
		LS1/LeistungsschModus (steuerbar)						
	$\checkmark$	LS1/LeistungsschPosition 3-polig	$\checkmark$	$\checkmark$				
		1010 10 10 10 10 10 10 10 10 10 10 10 10	-				~	
	Command	direction						
	Use	Description	Alarm logging (2)	Tag management (2)				
		c_Anwendung/Allgemein.LED rücksetzen						
	<b>v</b>	c_LS1/Steuerung.Befehl mit Rückmeld.	$\checkmark$	$\checkmark$				
		c_LS1/Steuerung.Schalthoheit Station						
	✓	c_Tr1/Steuerung.Befehl mit Rückmeld.	<b>√</b>	$\checkmark$				
		c_Tss1/Stufenschalter.Position						
		c_Tss1/Stufenschalter.Position.minVal						
		c_Tss1/Stufenschalter.Position.maxVal						
					< Back	Finish	Cancel	
Devices: 1 / 2	Use:	7 / 34 File: D:\	Import_Data\SysKon_S	IP5_SCC.scd				

[scc_61850_07, 1, en_US]

Figure 3-32 SICAM SCD Wizard, Showing Descriptions

Right-clicking the column heading of the **Monitoring direction** or **Command direction** lists opens a context menu. This allows you to show additional columns in the lists in order to display the names modified for SIMATIC WinCC.

By clicking Additional columns you can show or hide all the columns simultaneously.

The additional columns are:

- **Clients**: This column shows the name of the Client to which the corresponding information points are assigned.
- **Names of the dataset**: This column shows the name of the data set to which the corresponding information points are assigned.
- For Alarm logging: the Message Group and Message Text columns.
- For Tag management: the Variable group and Process information columns.
- For Tag logging: the Tag logging hierarchy and Tag logging information columns.

The texts for these columns are created when selecting a process tag for the tags (components).

 With Update SCC texts you re-transfer the currently displayed texts for the selected devices of column 2 to the additional text columns.

This overwrites previously edited texts.

# NOTE

Dynamic display features in WinCC diagrams do not work anymore after changing a tag name.

Ta SICAM IEC 61850 Wizard						- 🗆 X
Device list Mapping	g Device setting	s Global settings 🗹 Expert	view	SIEMENS SICAM S	SCC - II	EC61850 data mapping
+ 🖗 🔏 📺 🍦 Filter f	for 🔽	Static datasets SCC relev	ant			Search for
SIP_J (SIP_7SL87) O te	elegram addresses escriptions	Update SCC-texts	IP-address: 172. Device type: <b>7SL87</b>	.17.17.199		
. ─ Ma	onitoring directior					
Use	Descrip	tion 🔺	Alarm logging (5)	Message group	Mescane	Additional columns
	Anwend	dung/Allgemein.LED rückgesetzt	<b>v</b>	SubstationEast_SIP_/SL8/	Ant	Clients
	Anwend	dung/Allgemein.LED rücksetzen	•	SubstationEast_SIP_7SL87	An	Dataset names
	Anwend	dung/Allgemein.Schalthoheit			~	Message group
	ComFai	ult			~	Message text
	GIStatu	s				Variable group
	LS1/Lei	stungsschModus (steuerbar)				Process Information
<	LS1/Lei	stungsschPosition 3-polig	✓	SubstationEast_SIP_7SL87	LS1	Tag logging information
( Con	GIStatus LS1/Leistungssch…M ✓ LS1/Leistungssch…P ✓ Command direction					
Use	Descrip	tion	Alarm logging (2)	Tag management (2)		
	c_Anwe	ndung/Allgemein.LED rücksetzen				
	✓ c_LS1/S	iteuerung.Befehl mit Rückmeld.	$\checkmark$	$\checkmark$		
	c_LS1/S	teuerung.Schalthoheit Station				
	✓ c_Tr1/S	teuerung.Befehl mit Rückmeld.	$\checkmark$	$\checkmark$		
	c_Tss1/	Stufenschalter.Position				
	c_Tss1/	Stufenschalter.Position.minVal				
	c_Tss1/	Stufenschalter.Position.maxVal				
					< Back	Finish Cancel
Devices: 1 / 2	Use:	7 / 34 File: D:	\Import_Data\SysKon_SI	P5_SCC.scd		

[scc_61850_08, 1, en_US]

Figure 3-33 SICAM SCD Wizard, Showing Additional Columns

Texts can only be edited for selected tags.

♦ Double-click the desired cell to edit the text. The tag is displayed later with this text in SIMATIC WinCC, e.g. in the Alarm Logging system.

ta SICAM IEC 61850 Wizard × _ п SIEMENS SICAM SCC - IEC61850 data mapping Device list Expert view Mapping Device settings Global settings + 🔍 🛅 Filter for ... ✓ Static datasets SCC relevant Q Search for . A Single devices Show objects of import file with ... SIP_E (SIP_ IP-address: 172.17.17.199 SIP_J (SIP_7SL87) telegram addresses Update SCC-texts Device type: 7SL87 ○ descriptions Monitoring direction Telegram address Alarm logging (5) Message group Use Message text Tag management \land CB1/CSWI1.LocKey.stVal CB1/CSWI1.LocSta.stVal CB1/CSWI1.Mod.stVal ✓ CB1/CSWI1.Pos.stVal ~ B1/CSWI1.Pos.stVal ✓ CB1/XCBR4.Mod.stVal -CB1/XCBR4.Pos.stVal ✓ CB1/XCBR4.Pos.stVi -SubstationEast SIP CB1/XCBR4.Pos.subVal < Command direction Use Telegram address Alarm logging (2) Tag management (2) Application/c_LLN0.LEDRs.ctlVal CB1/c_CSWI1.Pos.ctlVal -✓ CB1/c_CSWI1.LocSta.ctlVal -✓ Dc1/c_CSWI1.Pos.ctlVal Tap1/c_YLTC1.TapChg.ctlVal Tap1/c_YLTC1.TapChg.minVal Tap1/c_YLTC1.TapChg.maxVal < Back Finish Cancel Devices: 1 / 2 Use: 7 / 34 File: D:\Import_Data\SysKon_SIP5_SCC.scd

[scc_61850_09, 1, en_US]

Figure 3-34 SICAM IEC61850 Wizard, Editing Texts

- $\diamond$  Select the tags for the other devices.
- ♦ Activate the Expert view in order to select the Device Settings and Global settings tabs.

#### **Device- and Driver-Specific Settings**

♦ Select the **Device settings** tab.

SICAM IEC 61850 Wizard					-		×
			SIEMENS		O data		in a
Device list	Mapping Device settings Global settings	Expert view	3	ICAW SCC - IECOTO:	o uata	mapp	ing
+ 🗏 🕺 📋 📮	▼ IFD						
4. Single devices	Remote IP address		172.17.17.199				
	Redundant remote IP address1						
SIP_L (SIP_73L07)	Redundant remote IP address2						
3IP_J (3IP_/3L07)	Redundant remote IP address3						
	OSI ACSE AP title value		1,3,9999,23				
	OSI ACSE AE qualifier		23			mappin	
	Origin identification mode		0				
	Timeout initialize connection		30				
	Timeout connection monitoring		10				
	Timeout activate/confirm		20				
	Timeout confirm/terminate		20				
	Timeout select/execute		35				Cancel
	Timeout services		7				
	Cycle time read request		1				
	Timeout Ping		1				
	Connection ping		0				
	Static or dynamic datasets		0				
	Type of reports		0				
	Report attribute "TrgOpt"		0				
	Report attribute "OptFlds"		0				
	Report attribute "Integrity"		0				
	Buffered reports		1				
	✓ Misc						pin
	ld		0000000-0000-0000-0	000-00000000000			
	UUID		0000000-0000-0000-0	000-00000000000			
	Remote IP address						
	Remote station IP address						
	Values/Ranges: String 15 characters (###.###.###) # = 0 to 9						
				< Back	Finish	Canc	el
Devices: 1 / 2	Use: 7 / 34	File: D:\Import_Data\S	/sKon_SIP5_SCC.scd				

[scc_61850_10, 1, en_US]

Figure 3-35 SICAM IEC61850 Wizard, Showing Device Settings

The settings of the selected device are displayed. They correspond to the parameters in the SICAM TOOLBOX II.

When importing from an ICD file, the IP address of the IEC 61850 device is not imported. You must enter it under **Remote IP** address. No further settings are required.

♦ Select the **Global Settings** tab.

ta SICAM IEC 61850 Wizard		– 🗆 X
		SIEMENS
Device list	Mapping Device settings Global settings	rt view SICAM SCC - IEC61850 data mapping
+ 🛛 🕺 📋 📮 🛛		
4. Single devices	log level	1
	Log all lists	0
SID L (SID 751 97)	Log all server objects	0
SIP_J (SIP_/SLO/)	Log all conversions	0
	Log all raw values	0
	Log all queue operations	0
	Log all controls	0
	Write dump file	0
	Skip reporting	0
	Log statistics	0
	Skip cyclic processing	0
	Log transparent values	0
	Skip 61850 send values	0
	Skip SCC receive values	0
	Ignore 61850 server time	0
	✓ General	
	Server IP address	
	Standby server IP address	
	Show "Additional cause"	1
	Timeout startup	60
	Support substitution	1
	Own originator address	0
	Show originator address	1
	✓ RFC1006	0004
	Local transport SAP	0001
	Buffer segment size	1024
	Log level Log level (1=Debug, 2=Info, 4=Warning, 8=Error). Values/Ranges: Integer [##] 1 to 15	
Davices: 1 / 2	1 / c · 7 / 3/ 5//	< Back Finish Cancel

[scc_61850_11, 1, en_US]

Figure 3-36 SICAM IEC61850 Wizard, Showing Global Settings

The general, device-independent settings are displayed.

You can only define these parameters in the first station imported into your project. They are valid for all stations of this project. Changes in other stations are ignored.

If your system contains several network cards it may be necessary to configure the server IP address. A value of **0.0.0.0** switches the IEC 61850 driver to automatic mode. The routing is handled by Windows. This mode is required if you want to connect several networks simultaneously.

In order to route all connections over 1 network, enter the IP address of the corresponding network connection.

If no IP address is configured, the entire traffic is routed over the first network in the system.



# NOTE

The significance of these parameters corresponds to the significance of the parameters in the SICAM TOOLBOX II. No settings are required.

Click Finish to close the dialog.
 This starts the device data import.

#### **Combining Devices into Groups**

After the first of the SICAM IEC61850 Wizard, all the previously selected devices (Figure 3-31) are listed in the device list under **Single Devices**. You can now combine devices into groups and then select tags for several devices at the same time.

To combine devices into groups, use the context menu, the Drag&Drop function or the toolbar. Make sure that you only combine devices of the same type and with the same data points. Each device group must be assigned a unique name.

								SIEM	IENS SICAM S		31850 dat	a ma	nni
			Mapping [	Device settings G	lobal settings	🖌 Expe	rt view		olo/ill o	00-1200	71000 dui		ppi
~   A II		Ŧ	V Diagnos	sis									
GROUP			Log leve	el				1					
SIP_E (S	IP_7SL	87)	Log all I	ists				0					
Single devi	ces		Log all s	erver objects				0					
	P 7SL	87)	Log all o	onversions				0					
	+	Add to	o new group	CTRL+N				0					
		Add to	o					0					
	₿.	Remo	ve	Del				0					
		Damas		F2				0					
		Kenan	ne group	F2				0					
	X	Cut		CTRL+X				0					
		Paste		CTRL+V				0					
	_		Skip 61	350 send values				0					
			Skip SCO	Creceive values				0					
			Ignore 6	1850 server time				0					
			✓ Genera	I									
			Server I	^o address									
			Standby	server IP address									
			Show "A	Additional cause"				1					
			Timeout	t startup				60					
			Support	substitution				1					
			Own or	ginator address				0					
			Show or	riginator address				1					
			✓ RFC100	6				0004					
			Local tra	ansport SAP				1001					
			Log level Log level (1	=Debug, 2=Info, 4	=Warning, 8=Erro	or).							
			Values/Rang Integer [ 1 to 15	ges: ##]									

[scc_61850_12, 1, en_US]



To edit a device group:

- ♦ Select the device group.
   The data points of the devices in the group are displayed.
- In the Alarm Logging, Tag Management, and Tag Logging columns, select the tags to be imported using the SICAM IEC Wizard.

The selection applies to all devices in the group.

The devices of a group cannot be edited individually. If you remove a device from the group, it is displayed under **Single Devices** once again and can be edited separately. The device maintains the current parameter settings.



# NOTE

The table always displays the information of the first device of the group. All the devices must be configured identically:

- Information that is not provided by all devices will not be displayed.
- You cannot filter for datasets that are not available in the first device.

# Using the Originator Address for Checking the Switching Authority

For SIPROTEC 5 IEC 61850 devices you can use the originator address for a switching authority check. To do this, change the value of the **Originator addresses** to 1 in the settings of the corresponding device using the SICAM IEC 61850 Wizard.
♦ Send Direction

Define your HMI's own originator address in the **Own originator address** parameter in the **Global settings** tab.

♦ Receive Direction

To show the originator address of a command in your message list, set the **Show originator address** parameter to **1** in the **Global settings** tab.

The texts are assigned values in the **PasNorm.ini** file. A template for this INI file is available in the **misc** directory of the SICAM SCC installation. Copy this **PasNorm.ini** file into your project directory.

Before creating your project you can define up to 30 user-specific texts in the text library. Enter these texts in the **sicam_messagetext.txt** file, from TextID 1770 onwards.

The defined texts are assigned to the corresponding originator address via the **PasNorm.ini** file. You can assign several originator addresses the same TextID.

When receiving changed information with an originator address set, your defined text is shown in the **Location** message list column instead of the standard texts **NEAR**, **REMOTE** and **LOCAL**.

### 3.2.5 Connection Parameters

The steps to be performed for the configuration of the connection parameters depend on the station or device connected to SICAM SCC in the individual case.

### SICAM PAS

No connection parameters need to be defined when connecting a **SICAM PAS** station Version 8.00 or later. The connection parameters are transferred from the SICAM PAS import file.

The connection parameters for older versions of SICAM PAS are pre-assigned with default values. The connection parameters must correspond to the values defined in SICAM PAS. Check the connection parameters as described below.

### SICAM RTUs

No connection parameters need to be configured for the connection of **SICAM RTUs**. The connection parameters, and also the redundancy setting, are included in the **SXD** file. You can check the settings in your SICAM TOOLBOX II project.

### SCD/CID Files

No connection parameters need to be configured for importing SCD and CID files. All relevant parameters are included in these files.

XML Files

To import XML files, the connection parameters must be defined, see 3.2.4.3 IEC 60870-5-104 Devices.

ICD Files

To import ICD files, the connection parameters must be defined, see 3.2.4.4 IEC 61850 Devices.



### NOTE

During a data import using the SICAM Wizard, the manually changed connection parameters are overwritten with the parameters from the import file. For this reason, the connection parameters must be checked after the data import.

To check the parameters for the connection to the SICAM PAS station:

Click the desired station in the Tag Management under PAS Data Server.

3.2 Creating a New Project

III Tag Management - WinCC C	onfig	guration Studio							
<u>File E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u>	elp					1			
Tag Management			~	Find	<del>ب</del> م		Properties - Conn	lection	*
				Name	*	16	Selection		
🗈 🍄 Internal tags				1 ※			Object type	Connection	
SICAM PAS PROTOC	OL S	UITE	E	2			Object name	NewConnection_1	
PAS Data Server				3		1	General		
Substation So	uth			4			Name	NewConnection_1	
NewConnect	on 1			5			ID	8	
		New Group		6	E		Connection Parameters	127.000.000.001-10501-0-00	0.000.000.000-105C
Burger System into				7		Ľ	Assignment		
System Info		Сору		8			Communication driver	SICAM PAS PROTOCOL SUITE	
SystemInfo	19	Paste		9			Channel unit	PAS Data Server	
🖻 🗟 Structure tags			*	10		Ľ	Various	-	
alalal		Delete		11			Creator ID	0	
Tag Management		Panama		12			Last Change	25.09.2018 10:25:51	
Alarm logging		Kendirie		12					
Alarmiogging	×	Export		14		lF			
Tag Logging				15					
	161	Connection Parameters		15					
		<b>■ ₩ Ⅲ ●</b>	ት 🔛 🔹	H I H Groups	•				
Ready NUM				English (United Sta	ites)			100 % 😑	

[pascc321, 1, en_US]

Figure 3-38 Station, Properties – Connection

Click in to define the IP address of the corresponding SICAM PAS system. The PAS Connection dialog opens.

PAS Connection		<b>—</b> ×
SICAM PAS Configuration		,
Connection parameter		
Connection type	No Redundancy	
	SICAM PAS address	port
SICAM PAS 1	127 . 0 . 0 . 1	10501
SICAM PAS 2	0.0.0.0	10501
Link parameter		
Test frame period [ms]	1000 (250 - 60000	)
	OK Abbrecher	Übernehmen

[pascc322, 1, en_US]

Figure 3-39 Entering the IP Address

- ♦ Enter the IP address of the SICAM PAS system.
- ♦ Click **OK** to confirm your settings.

## 3.3 Creating a Control Diagram

### Purpose

The control diagram serves for displaying detailed information concerning the individual station sections to be controlled. For this purpose, you use the graphic objects from the graphic object library in order to represent color changes, blinking, etc.

DThe configured switching operation must be performed as follows:

• Select a switch

Click the switch icon to open the dialog for selecting the switching direction.

• Select the switching direction

To select the switching direction, click the corresponding button in the dialog in order to create the command and to display the buttons for issuing or canceling the command.

• Issue the command. Click the Acknowledge button in the dialog to issue the command.

The dialog closes if no additional operator action is performed within 30 seconds of clicking on a switch object.

Besides the two-step switching operation described above, two-step and synchronized switching is also possible (see 4.3 Using Graphic Objects).

The different states of a switch are indicated by small, colored rectangles. A specific color can be selected for the following states:

- Not current
- PAS not OK
- Bay Blocking
- Substituted
- Telecontrol blocking

The switch object **blinks spontaneously** spontaneously if the value of the assigned tag changes and if **spontaneous** was entered as the cause.

When the command is issued, the switch object starts to **blink** in the set status as soon as the target switching direction (ON or OFF) has been selected. It stops blinking when the command has been completely executed or aborted.

In the target status, the blinking frequency is half the frequency for a spontaneous cause.



### NOTE

For connections via IEC 60870-5-104 and IEC 61850, the blocking state is represented as Not topical..

### Switching device objects

Use ActiveX Controls from the SICAM graphic object library as a circuit breaker or disconnector objects. Since the above-mentioned functions are already integrated in these controls, you can create a fully functional user interface within a short time.

### Ground disconnectors and feeders

To perform the **topological coloring**, use ActiveX Controls from the SICAM graphic object library as ground disconnectors/feeders.

### **Connector and Connection Point**

To realize the topological coloring, use connectors and connection points from the SICAM graphic object library.

3.3 Creating a Control Diagram



[Detail1, 1, en_US]

Figure 3-40 Control diagram with circuit breaker and indicator

### How to proceed

To create the control diagram:

- Create a new diagram under the name **Detail_E01.PDL**.
- To do this, insert the objects from the SICAM graphic object library.

To control and show objects in the control diagram, the individual objects must be assigned tags.

### 3.3.1 Creating a New Diagram

To create a new control diagram:

In the WinCC Explorer, double-click Graphics Designer.
 Alternatively, you can open the Graphics Designer via the context menu.

🤞 WinCC Explorer - C:\Us	ers\Public\Documents\Siemens\WinC	CProjects\net	uesProjekt\neuesProjekt.MCP		
File Edit View To	ols Help				
🛯 🕒 📄 🕨 🕺	通道  日本部 🏢 省	?			
🖃 🚡 neuesProjekt		*	Name	Туре	Last
- 🖵 Computer			A CompKey_Empty.Pdl	Process picture	2/12/
Tag Manageme	ent				
Menus an	Open				
	New picture				
	Graphic OLL	E			
Tag Loggi	Select ActiveX Control	1			
SICAM PA	Show information column				
SICAM TE	Edit Favorites order				
Report De	Descention				
Global Scr	Properties				
Text Library					<b>M</b>
Text Distributor					W.
🦷 🧌 User Administr	ator				.44.
Cross-Referenc	e				/ • \
Load Online Ch	langes				
Redundancy		-	٠		E.
neuesProjekt\Graphics Des	igner\		1 object(s)	Licensed m	ode

#### [pascc331, 1, en_US]

Figure 3-41 Graphics Designer context menu

- ♦ This opens the Graphics Designer with an empty workspace.
- To save the diagram, click File > Save as.... In the file selection dialog which opens, enter Detail_E01.PDL as file name.

### Defining diagram properties

Define the properties of **Detail_E01.PDL**.

- Right-click the workspace and select **Properties** from the context menu.
   The **Object properties** dialog opens.
- ♦ In the **Properties** tab, select the **Geometry** object property.

To create a diagram with a size of 900 x 700 pixels:

- ♦ Double-click **Picture width** and enter **900** in the dialog. Click **OK** to confirm.
- ♦ Double-click **Picture height** and enter **700** in the dialog. Click OK to confirm.
- ♦ Close the **Object properties** dialog.

3.3 Creating a Control Diagram

Object Properties		
Properties Events		
Picture Object Geometry	Attribute Picture Width	Static 900
	Picture Height Grid On Grid Width Grid Height	700 Yes 10 10
Tags Output Wind	ow 🕒 SVG library 🤻 Dynamic Wizard 🕒 Library	Dbject Properties
pascc332. 1. en USI		

Figure 3-42

Defining the diagram size

## Setting the grid

To facilitate your work, you should define the grid:

- ♦ To open the **Settings** dialog, click **View > Grid...**.
- ♦ Apply all settings as shown in below.

Default Object	Settings	5	Show/Hide Layers
Grid	Options		Visible Layers
Display grid			
Snap to grid			
Width in pixels	He	aht in	pixels
⊚5 ⊚1	0 0	5	10
© 25 © 5	0 0	25	○ 50
10 10	0	1	0 📥

[pascc333, 1, en_US]

Figure 3-43 Settings of the workspace

## 3.3.2 Using SICAM Switch Controls

The Circuit breaker, Disconnector, Ground and Feeder control types are **ActiveX Controls**. When creating the picture, insert these controls and link them using lines or connectors.

The **Ground** and **Feeder** types must be positioned analogous to the switch controls. For more detailed information on how to define the necessary parameter settings, refer to *5.2.2 SICAM Electrical Device Control*.

### Positioning a Switch Control

To position a SICAM Switch Control from the SICAM graphic object library on the workspace, proceed as follows:

- ♦ To open the Library, click View > Library.
- ♦ To show a preview of the graphic objects, click **Preview** in the toolbar of the **Library**.
- ♦ Select SICAM LS under Switching devices.
- Hold down the mouse button and move the cursor over the workspace until the graphic object has reached the desired position.

3.3 Creating a Control Diagram

🖋 Graphics Designer - Test1.PDL					- • •
File Edit View Arrange Tools Windo	w SICAM Help				
i 🗅 🖻 😂 🔒 i 🕨 i 🐰 🖬 🛍 🖃 🗠 i	3 🗄 🐮 🔳 🔂 者 🛛	R : 🔍 🔍 🗔 100%	-	• •	<u>⊿</u> - <u>∧</u> - <u>A</u> -
SICAMSwitch_PAS_CB 🔹 🖫	🎢 🔗 🗛 🖣 🗛 🗄 🗎 🗃	मि में के के मि 🗄			
: C, 🔛 🔛 🥏					
NewPdl1 Test1.PDL ×				•	Standard 🛛 🔻 🗭 🗙
Library				<b>▼</b> ‡ ×	Rectangle
📸   3, 🗈 🛍 🗙   🖳 🗁 🏥 🎹   66					Rounded
🤤 Global Library	Name	Size	Last Change		Connecto
Project Library	Switch IEC CB	3542	13.04.17 08:14		🚊 📑 Smart Object
Graphic objects of previous versions>	Switch IEC DIS	3550	13.04.17 08:14		
Alarm Logging templates	switch IEC EI	3542	13.04.17 08:15		Picture W
	Switch IEC LBS	3551	13.04.17 08:14		
Control elements	Switch PAS CB	3542	13.04.17 08:24		OLE OLE objec
Wiedsured/Wetered values	Switch PAS DIS	3550	13.04.17 08:25		0.12 I/O Field
	Switch PAS EI	3542	13.04.17 08:15		Bar
±	Switch PAS LBS	3550	13.04.17 08:25		
4	ļ				( m →
Dynamic W	Vizard				🔊 s. 🔽 c 😐 s. 🔌 p.
0 1 2 3 4 5 6 7 8 9 10	11 12 13 14 15 📦 0-La	yer0			
Press F1 for Help.		Deutsch (Deutschland)	ICAMSwitch_PAS_CB	 <u>1</u> ,	t:40 Y:60

[pascc335, 1, en_US] Figure 3-44

Positioning a graphic object

### Setting the parameters of a switch control (switching device object)

To define the properties of your switch controls, open the SICAM Switch Control Properties dialog.

To do this, double-click the graphic object.
 The SICAM Switch Control Properties dialog opens.

The dialog consists of 6 tabs:

- In the **Style** tab you can define the representation style or orientation of the circuit breaker (see *Graphical representation*, *Page 108*).
- In the **Tag connection 1** and **Tag connection 2** tabs you define the protocol type and the protocol, assign tags to the circuit breaker and enter the tooltip text (see 4.4.2 Process Connection of SICAM Switch Controls).
- In the **Advanced** tab you can assign further properties for the circuit breaker (see 4.4.3 Advanced Properties of SICAM Switch Controls).
- In the **Color** tab you can assign specific colors for the switch positions and circuit breaker states (see 4.4.4 Colors of SICAM Switch Controls).
- In the **Picture** tab you assign pictures for the circuit breaker values (see 4.4.5 Picture of SICAM Switch Controls). You must only assign a picture to the switch control if you have selected the **Picture** option for **Norm** in the **Style** tab.
- ♦ Define the parameters and click **OK** to apply the properties.

### Specifying further properties

Specify further properties of the Circuit breaker and Disconnector objects in the context menu.

Right-click the graphic object and select **Properties** from the context menu.
 The **Object properties** dialog opens.

- Select the desired object property (e. g. **Geometry**) in the Properties tab.
- ♦ Double-click the attribute in order to modify the corresponding parameter.

Object Properties				<b>→</b> ‡ ×
Properties Event	s			
SICAMSwitch	Ctrl Attribute	Static	Dynamic Update	Indir
Geometry	Position X	110	Q	
- Miscellaneo	Position Y	20	Q	
Control Pro	Width	40	Q	
	Height	60	Q	
<	>			
[pascc343, 1, en_US]				

- Figure 3-45 Specifying object properties
- ♦ Close the **Object properties** dialog.

## 3.3.3 Using Connectors and Connection Points

### **Positioning Connectors and Connection Points**

After you have added and defined all ActiveX Controls, you can add the lines (connectors and connection points).

Connectors and connection points which support topological coloring are available in the **Topology** folder of the SICAM graphic object library. With these graphic objects, you can show the states of lines in different colors during runtime.

For more detailed information concerning topological coloring, refer to 5 Topological Coloring.



### NOTE

You can also use simple lines or rectangles to represent connectors and connection points, but these lines and rectangles do not support topological coloring.

To position connectors and connection points from the SICAM graphic object library on the workspace, proceed as follows:

- ♦ To open the Library, click View > Library.
- Select a **Connector/Connection Point** under **Topology**.
- Hold down the mouse button and move the cursor over the workspace until the graphic object has reached the desired position.

After you have linked the graphic objects to the connectors, you must create the event functions and scripts. Click the Enable picture for topology calculation icon:



### ♦ Click the Create topological structure icon:



The entire project, including the connection scripts, is now created. All the pictures changed are opened and generated during this process. If an error occurs when generating a picture (e.g. because a connector has not been connected correctly), the generation process is aborted and the defective, open picture is shown. You can correct the problem immediately.

Furthermore, you can view the progress of the picture generation process in the Report window. For more detailed information concerning error messages, refer to 5.3.5 *Notes on Configuration*.



# NOTE

The **FFF** Check current picture function only checks the picture. The existing topology does not change as long as the picture has not yet been saved. Scripts are also not written.

As soon as you save the picture, it is highlighted as changed and the project must be created once again.

## 3.3.4 Displaying a Measured Value

For more detailed information on the measured value object refer to 4.8 Measured/Metered Value Display.

### Purpose

The detailed control diagram serves for displaying a measured value of SICAM PAS.

### Inserting a Measured-Value Object

Change to the Graphics Designer and insert a measured value object in your control diagram:

- ♦ To open the Library, click View > Library.
- ♦ To show a preview of the graphic objects, click **Preview** in the toolbar of the **Library**.
- Select SICAM Measured Value under Measured/Metered Value.
- ✤ Hold down the mouse button and move the cursor until the graphic object has reached the desired position.

### **Connecting a Tag**

- ♦ Double-click the measured value object inserted. The SICAM Numeric Control Properties dialog opens.
- ♦ Select the Tag connection tab.
- ♦ Click ... to the right of the Tag name information entry field.
- ♦ In the tag selection dialog which opens, select the desired tag and then click **OK**.



### NOTE

Use the Filter field in the tag selection dialog in order to restrict the number of listed tags: Enter e.g. *.RTInfo if you want to show structure elements of the RTInfo type only.

		Station O	verview
HV Bay 1	HV Bay 2 H	V Bay 3 HV Ba	VA HV
	ITV Day 2	V Day O LELELE IIV Da	y 4
and a BR Lance and a second	SICAM Numeric Cont	rol Properties	X
· · · · · · · · · · · · · · · · · · ·	Style Tag connection	Advanced Limits Color For	t
· · · · · · · · · · · · · · · · · · ·			
	Protocol type:	SICAM PAS Protocol Suite	~
a a a a <b>DD</b> alla a a a <mark>a a a </mark> an	T	(* DTT={-)	
	l ag name information	n (*.R11nfo)	
· · · · · · · · · · · · · · · · · · ·	Messwert_HS_Feld1	l.RTInfo	
	- 14		
a a a a a a a a a a a a a a a <mark>la</mark> na a a	l ag name command (	(*.RTCmd)	
0,000000 A			
	Value type:	Set point hit string 32 hit	~
· · · · · · · · · · · · · · · · · · ·	value type.	Set point bit string 52 bit	•
	Tooltin text:		
· · · · · · · · · · · · · · · · · · ·			
••••••••••••••••••••••••••••••••••••••			
· · · · · · · · · · · · · · · · · · ·			
· · · · · · · · · · · · · · · · · · ·		OK Ca	ncel Apply

[pascc356, 2, en_US]

Figure 3-46 Connecting a Tag

- ♦ Define further settings (e.g. Unit, Tooltip Text).
- ♦ Close the SICAM Numeric Control Properties dialog.

### 3.3.5 Inserting an Acknowledge button

### Inserting an Acknowledge button

The circuit breaker blinks spontaneously when the state of the assigned tag changes in monitoring direction with the cause **Spontaneous**. This spontaneous blinking must be acknowledged.

To acknowledge the blinking of one or several switches, insert a button from the SICAM graphic object library into the diagram.

- ♦ To open the Library, click View > Library.
- ♦ To show a preview of the graphic objects, click **Preview** in the toolbar of the **Library**.
- ♦ Under Controls, select Button quit blinking.
- Hold down the mouse button and move the cursor until the graphic object has reached the desired position.

3.3 Creating a Control Diagram



[sc_insert_quit-button, 2, en_US] Figure 3-47 Inserting an Acknowledge button

### Defining a Tooltip Text for a Button

To define a tooltip text for a button, proceed as follows:

- ♦ Right-click the button and select **Properties** from the context menu.
- ♦ Select Others in the Properties tab.
- ♦ Double-click the **Tooltip text** attribute. The **Text input** dialog opens.
- ♦ Enter the tooltip text into the **Enter a value** entry field and click **OK** to confirm.

Object Properties		(		
Properties Events			III Text Input	<b>X</b>
Button Geometry Colors Styles Font Flashing Miscellaneous Filling Dictures	Attribute Operator-Control Enable Authorization Display Tooltip Text Configured Languages Adapt Border Shortcut	Yes <no Yes Blinko Deuts No</no 	Englisch (USA) Deutsch (Deutschland)	Quit blinking Q0 Blinken quittieren Q0
Dbject Properties	Library 🛠 Dynamic Wizard	yer0		OK Cancel

[[]pascc358, 1, en_US]

Figure 3-48 Defining a Tooltip Text for a Button

The setting of the button properties ensures that the button can be activated via mouse click or by pressing a key on your keyboard.

Instead of an acknowledge button, you can also use the integrated dialogs of the switching device objects (see 4.4.6 Runtime Dialogs of SICAM Switch Controls).

### Completing the Control Diagram

- ♦ Complete the control diagram. Add e.g. labels.
- ♦ Save the completed diagram.

3.3 Creating a Control Diagram



[pascc344, 1, en_US] Figure 3-49

49 Control Diagram

## 3.4 Creating an overview diagram

### **Overview diagram**

The diagram **hv_overview.pdl** shows an overview of your system. Fields which include several circuit breakers and disconnectors are shown with a graphic object.



[sc_overview, 1, en_US] Figure 3-50 Overview diagram

To create the overview diagram, you must

- create a new diagram hv_overview.PDL (width 900 and height 700),
- ♦ draw the diagram and insert objects and icons, e. g. bay overview objects and labels.

### Positioning a bay overview object

To position an SICAM Bay Overview Control from the SICAM graphic object library on the workspace, proceed as follows:

- ♦ To open the Library, click View > Library.
- ♦ To show a preview of the icons, click **Preview** in the toolbar of the toolbar of the **Library**.
- Select the graphic object SICAM boxed under Overview objects in the project library.
- Hold down the mouse button and move the pointer over the workspace until the icon has reached the desired position.

3.4 Creating an overview diagram

Library			
📸   3 🖻 🛍 🗙   🖦 📴 🏥 🗰 🎆			
Project Library	Name	Size	Last Change
Graphic objects of previous versior	BayOverview rect	796	27.04.20 14:28
Alarm Logging templates     Bay overview objects     Control elements     Measured/Metered values     Switching device objects     Topology	BayOverview round	796	21.04.20 09:42
< >			
📔 Object Properties 🛛 🕣 Tags 📄 Output Wi	ndow 🕒 Library 🕒 SVG library 戦 D	ynamic Wizard	

[sc_lib_bay_overview, 1, en_US]



### Defining a bay overview object

To define the properties of the bay overview, open the SICAM Bay Overview Control properties dialog.

- ♦ Double-click the bay overview icon. The **SICAM Bay Overview Control Properties** dialog opens.
- ♦ Define the tag connection (see 4.7.2 Tag Connection to Bay Overview).
- ♦ **Important**: Delete the default tag link for switchgears which do not actually exist in the bay.
- ♦ Click **OK** to close the dialog.

For more detailed information concerning the Bay overview graphic object, refer to 4.7 SICAM Bay Overview.

### Inserting a button

Insert a **Button** object into the **hv_overview.pdl** diagram. Click this button to show the **detail_E01.pdl** control diagram.

- ♦ Select the **Button** object in the object palette under **Windows objects**.
- ♦ Create the button at the desired position.

3.4 Creating an overview diagram



Figure 3-52 Inserting a button

### **Configuring a button**

The Button configuration dialog opens.

#### Working with SICAM SCC

3.4 Creating an overview diagram

Button Configuration	ı	?	×
Text:	=E01		
Font	Arial		
Color			
Operation: Authorization	<no access="" prot<="" td=""><td>ection&gt;</td><td></td></no>	ection>	
Shortcut			
Change Picture on Mo	ouse Click:		Ť
	OK	Can	cel

[sc_button_config, 1, en_US]

Figure 3-53 Configuring a button

- ♦ Define the **text**, the **font** and the **color**.
- ♦ Under Change diagram on mouse click, select the detail_E01.PDL diagram.
- ♦ Click OK.

### Defining a tooltip text for a button

To define a tooltip text for a button, proceed as follows:

- ♦ Right-click the button and select **Properties** from the context menu.
- ♦ Select Others in the Properties tab.
- ♦ Double-click the Tooltip text attribute. The Text input dialog opens.
- ♦ Enter the tooltip text into the **Enter a value** entry field and click **OK** to confirm.

itt Properties			▼ 1
perties Events	Text Input		×
utton ^ Attribute	English (United States)	Switch to detail picture	- 1
Geometry Operator-Control Enable	German (Germany)	Wechsel zu Detailbild	
Authorization	Spanish (Spain, Traditional S.		
Display			
Font Tooltip Text			-
Miscellaneo Configured Languages			- 1
Filling Adapt Border			-
Shortcut			-
- )			
Object Properties 🕒 Library 🤻 Dynamic Wizard		011	_
1 2 3 4 5 6 7 8 9 10 11 12 13 14 15	0.1	OK Cancel	_

[sc_button_tooltip, 1, en_US]

Figure 3-54 Defining a tooltip text for a button

∻ Click **OK**. The settings are applied.

## 3.5 Creating a List View

You want to define that the event list is displayed after clicking the Event list button. To do this, you must create the eventlist.PDL diagram and insert the SICAM SCC event list object. Later, the buttonbar.PDL file must be completed by the corresponding Button object.

### Creating an event list

In the eventlist.pdl diagram, insert a **SICAM SCC event list without DAF** object (for further information regarding DAF, see 7.5 *Dynamic Alarm Filter (DAF)*).

Eve	ntList.PdI	×													
∃i si	CAM SCC	Event list w	ithout DAF												
	T.st.	Date	Time	Mes	sage Group	N	lessage Text	1	Value	Unit	Cause	Status (Validity)	Additional cause	Supplementary Info.	
77	3504	14/05/2020	18.16.48,00	00 TE>	кт	т	EXT		4848	TEXT	11423	2303	21543	16319	_
78	2699	14/05/2020	18.16.49,00	00 TE>	KT	Т	EXT		15598	TEXT	28977	19333	23426	1168	
79	6209	14/05/2020	18.16.50,00	00 TE>	त	Т	EXT		22162	TEXT	26235	21903	76	5356	
30	958	14/05/2020	18.16.51,00	DO TE>	KT	Т	EXT		13190	TEXT	7454	12739	5367	6591	
31	5329	14/05/2020	18.16.52,00	DO TEX	KT	T	EXT		31252	TEXT	18669	1988	16713	6530	
2	3700	14/05/2020	18.16.53,00	00 TE>	KT	T	EXT		10806	TEXT	24995	26761	4577	13561	
3	30075	14/05/2020	18.16.54,00	00 TE>	er		EXT		22264	TEXT	12338	22777	18803	3538	
4	16546	14/05/2020	18.18.55,00	DO TEX	KT		EXT		28679	TEXT	21954	4964	28137	198	
0	084	14/05/2020	18.10.50,00	DU TEX	(T		EXT		18835	TEXT	11225	403	29/91	20390	
0	15200	14/05/2020	18.16.57,00	JU TEX	(T		EXT	-	2814	TEXT	10567	3197	7652	5198	
<u>,</u>	10338	14/05/2020	18.10.58,00		<1 /T		EXT		40070	TEXT	19910	23038	8029	31818	
<u>.</u>	4744	14/05/2020	18,10,05,01		VT		EXT		10072	TEXT	8009	20390	8849	2203	
0	27089	14/05/2020	18 17 01 00		/T	-	EVT		12077	TEVT	27599	219/7	7820	20897	
1	37451	14/05/2020	18 17 02 00		ст	T	EXT		2372	TEXT	18830	17398	25537	18358	
2	8025	14/05/2020	18 17 03 00	00 TEX	CT	т	EXT		17214	TEXT	25197	17741	16757	17075	
3	1368	14/05/2020	18 17 04 00	00 TE)	(T	T	EXT		30456	TEXT	8534	27744	7622	8	
4	15465	14/05/2020	18 17 05 00	00 TEX	CT	T	EXT		2780	TEXT	13360	22800	28998	8619	
5	17662	14/05/2020	18 17 06 00	00 TEX	CT	т	EXT		22485	TEXT	4549	23245	27984	4954	
6	23180	14/05/2020	18.17.07.00	DO TE>	KT	Т	EXT		24111	TEXT	1663	9841	1661	1400	
7	10321	14/05/2020	18.17.08.00	00 TE>	(T	Т	EXT		1746	TEXT	8156	5020	7636	8625	
8	3898	14/05/2020	18 17 09 00	10 TE>	(T	т	FXT		30638	TEXT	32037	414	1498	28792	
rary															•
1	6 6 6	l×∣≞⊡	)- HE 🕅	66											
Pro	ject Libra	iry		^	Name			Size	La	st Change					_
	< Graphic	c objects of p	previous ver	rsior	SICAM SCC Alar	n list for D	ΔF	181510	04	04.19.15:5	2				
				SICAM SCC Alar	n list with	out DAE	181212	04	04 19 15-5	-					
Bay overview objects			SICAM SCC Frank list for DAF			102026	04	04 10 15.2	1						
Control elements				CICAN SCC EVEN	UNSURATION DA		100706	04.	04.19 10:5	1					
Measured/Metered values SICAM SCC Event list for PQ Analyzer 189/36 04.04.19 15:32															
_	Switching	a device obi	ects		SICAM SCC Even	t list witho	ut DAF	182806	04.	04.19 15:4	8				
Switching device objects							sage list	181206	04.	04.19 15:5	1				
-															

[pascc375, 2, en_US]

Figure 3-55 View Showing an SICAM SCC Event List without DAF

To create the event list view, proceed as follows:

- ♦ Create the eventlist.pdl view (width 900 and height 700)
- ♦ and insert the SICAM SCC event list object, see below.

### Inserting an event list

To insert an event list, proceed as follows:

- ♦ To open the Library, click View > Library.
- ♦ To show a preview of the graphic objects, click **Preview** in the toolbar of the **Library**.
- ♦ Select the SICAM SCC event list object under Alarm Logging templates in the project library.
- Hold down the mouse button and move the cursor over the workspace until the graphic object has reached the desired position.
- ♦ Save the view under eventlist.pdl.

## 3.6 Creating a Button Bar

In the button bar, you can arrange all the buttons of the project. These buttons can be used to switch to a different view (e. g. overview diagram, list view) or to quit the runtime system.

Alarm List	Trends	Tables	HV Overview	End	SIEMENS SICAM SCC

[pascc330, 1, en_US]

Figure 3-56 Button bar with various buttons

To create the button bar, proceed as follows:

- Create a new view **buttonbar.PDL**.
- Inserting the buttons with their different functions

## 3.6.1 Inserting an Event List Button

- ♦ Create a new view named **buttonbar.PDL** (width **900** and height **100**).
- ♦ Select the **Button** object in the object palette under **Windows objects**.
- Create the button at the desired position.
   The Button configuration dialog opens.

Button Configuratio	in	?	×
Text:	Text		
Font	Arial		
Color			
Operation:	<no access="" prote<="" td=""><td>ection&gt;</td><td></td></no>	ection>	
Shortcut			
Change Picture on N	louse Click:		ħ
	OK	Can	cel



♦ Define the object properties (e. g. text, color).

- ♦ Leave the **Display changeover on mouse click** entry field empty. Afterwards, you must set the switching between different views/diagrams as C action.
- ♦ Click **OK** to close the dialog.

### Defining dynamic display properties

Via the dynamic properties of the button, specify the action for displaying the event list (eventlist.pdl).

♦ Double-click the new button. The **Object properties** dialog opens.

Object Properties			<b>▼</b> ↓ ×
Object Properties Properties Events Button Mouse Keyboard Focus Miscellaneous	<ul> <li>Execute on</li> <li>Mouse Click</li> <li>Press Left</li> <li>Release Left</li> <li>Press Right</li> </ul>	Action	- # X
Property Topics     Geometry     Geometry     Object Properties	Release Right	Wizard	

[pascc364, 1, en_US]

Figure 3-58 Defining the object properties

- ♦ Click the Events tab and then click Mouse.
- ♦ Right-click the flash icon next to Mouse action.
- Select C Action from the context menu.
   The Edit action dialog opens.

Edit Action		?	Х	
🗏 🛃   🐰 💷 🛍 🖏   🗙   🔊	🔁   🛗 🎯 🕺 관 🕞 📔			•
	<pre>#include "apdefap.h" void OnClick(char* lpszPictureName, char* lpszObjectName, char* lpszPropertyName) { SetPropChar("start.pdl","Bildfenster2", "PictureName","eventlist.pdl"); }</pre>			
	ок	Cano	:el	
Ready	Line: 5	Colum	n: 1	

[pascc384, 1, en_US]

Figure 3-59 Defining dynamic display properties

- ♦ In the Edit action dialog, enter the rows SetPropChar("start.pdl","Bildfenster2", "PictureName","eventlist.pdl"); between the curly brackets.
- ♦ Click OK. The settings are applied.
- ♦ If you are requested to recompile, confirm with Yes.
- ♦ To insert the HV Overview button, proceed in the same way as for the Event List button. This button can be used later for showing the diagram hv_overview.PDL.

## 3.6.2 Inserting a Quit Button

To add the **Quit button** to the button bar, click **Project library > Control elements**. This button serves to deactivate the runtime.

## 3.7 Creating a Start Screen

### Start Screen

Divide the start screen into two window sections (designated "picture windows"). The upper section shows the **button bar** (buttonbar.PDL). In the lower section, you can switch between the **overview diagram** (hv_overview.PDL), the **control diagram** (detail_E01.PDL) and the **list view** (eventlist.PDL) during runtime. The start screen is shown during runtime. It is 900 x 800 pixels in size.



[pascc390, 1, en_US]

Figure 3-60 Example of a Start Screen

### Overview

To create the start screen:

- ♦ Create a new display named start.PDL (width 900 and height 800).
- ♦ Create separate picture windows for buttonbar.PDL (900 x 100) and hv_overview.PDL (900 x 700).

### **Positioning Picture Windows**

To position a picture window:

♦ Select Picture window under Smart objects in the Object palette.

As soon as you move your cursor over the workspace, it changes its shape to a cross-hair with an object icon appended.

♦ At the desired position, drag the mouse cursor while holding down the mouse button until the **Picture window** object has reached the desired size.

	orement be						 	 
		PI	CTURE WINDOW					:
								•
	· · · · · · · · · · · · · · · · · · ·					 	 	 
						 	 · · ·	 
<								
bject Properties								
Properties Event	3							
Picture Window	Attribute	Static	Dynamic	Update	Indir			
Geometry	Display	Yes	Q					
- Miscellaneo	us Update Cycle	Upon change	·		_			
	Sizable	No						
	Movable	No						
	Border	No						
	Title	No						
	Can Be Maximized	No						
	Closable	No						
	Foreground	No						
	Scroll Bar	No						
	Adapt Size	No						
	Adapt Picture	No						
	Picture scaling mode	Uniform						
	Picture Name		Q					
	Picture Offset X	0	Q					
1			0					
	Picture Offset Y	0	¥					

[pascc391, 1, en_US]

Figure 3-61 Inserting a Picture Window

### Setting the Parameters of a Picture Window

To set the parameters of a picture window:

Right-click the picture window and select **Properties** from the context menu.
 The **Object properties** dialog opens.



### NOTE

In the text box, you can view the picture name (e.g. PictureWindow1 or PictureWindow2) which has been automatically assigned by SIMATIC WinCC.

#### Specifying the Picture to be Displayed on Screen

To specify which picture is shown on screen:

- Right-click the picture window and select **Properties** from the context menu.
   The **Object properties** dialog opens.
- ♦ Select **Others** in the **Properties** tab.
- Double-click the attribute to be changed, i.e. Picture name.
   A file selection window opens and shows the names of all the pictures in the project.
- ♦ Select **buttonbar.pdl** and click **OK** to confirm.

3.7 Creating a Start Screen

NewPdl1 × overviev	v.PDL					
			PICTURE WIN	DOW:		
						L.
						<u> </u>
<						
Object Properties		_	Dicture	Name		7 ×
			in recure			· ^
Properties Events						
Picture Window	Attribute	Static	Hierarchy:			
Geometry	Display	Yes				
Miscellaneous	Update Cycle	Upon change	🥐 SC	CCL35	File Name	^
	Sizable	No			*	7
	Movable	No			- r alarmlist.PDL	
	Border	No			- AlarmSimulation.P	DL
	Title	No			-	
	Can Be Maximized	No			- CompKey_Empty.P	dl
	Closable	No			- Density_Chart.pdl	~
	Foreground	No			<	>
	Scroll Bar	No			OK	Canaal Hala
	Adapt Size	No			UK	Cancel Help
	Adapt Picture	No				
	Picture scaling mode	Uniform				
	Picture Name		Ŷ			
	Picture Offset X	0	Ŷ			
	Picture Offset Y	0	Ŷ			
		•				
💷 Tags 🛛 🔚 Library 📗 🕻	Object Properties 🛛 📉 🗅	namic Wizard 📃	🛾 Output Wii	ndow 💾 SVG	library	

[pascc392, 1, en_US]

Figure 3-62 Defining the Picture to be Displayed on Screen

- ♦ In order to ensure that the picture window remains open, set the **Display** attribute to **Yes**.
- ♦ To apply all parameters, close the **Object properties** dialog.

### Second Picture Window

- ♦ Create the second picture window.
- ♦ Assign hv_overview.pdl to PictureWindow2.

### **Defining WinCC Runtime Start Screen**

To open the Computer properties dialog:

- ♦ Select the Graphics Designer level in the WinCC Explorer. The screens are shown in a list.
- ♦ Right-click the start.pdl screen.
- ♦ Select Define screen as start screen from the context menu.

#### Activating the Project

♦ To activate the project you created, select **File > Activate**.

You can now check whether the configured user interface meets your requirements.

## 3.8 Setting up User Authorizations

The **User Administrator** editor serves to specify user groups and users and to assign them user authorizations. If a registered user calls up a function, the User Administrator checks whether the user has been assigned the required user rights. If this is not the case, it prevents access to the function concerned. User authorization is a feature of SIMATIC WinCC.

### Calling up the user administrator

Open the User Administrator to set up a new user group or a new user.

♦ In the WinCC Explorer, double-click the **User Administrator** level.

### Creating a user group

When creating a new project, the **Administrator group** is automatically created with the **Administrator** user. Create a new user group and assign the required rights. The rights of the group apply for all users belonging to the corresponding group.

- ♦ Select User > Add group.
- ♦ Enter the name of the new user group (e.g. Group 1).
- Assign the group rights by double-clicking on the desired row in the Authorization column.

🍿 User Administrator - WinCC Configuratio	on Stu	udio					-		×
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp									
User Administrator «	<u>o</u>	Authorizatio Find		• ۹		🕴 Properties - User			»
🖃 📲 User Administrator		Function	Enable	^	E	Selection			
🖶 👬 Administrator-Group	1	User Administration				Object type	User		
Administrator	2	Value input				Object name	Siemen	sOp	
i siemens	3	Process controlling	<b>V</b>		E	General			
	4	Picture Editing				User name	Siemen	sOp	
SiemensOp	5	Change picture	<b>V</b>			Group name	Operat	or	
Siemensop	6	Window selection				Password			
	7	Hardcopy	<b>V</b>			Login			
	8	Confirm alarms				Logon with smart card			
	9	Lock alarms				Value of the tag logon			
	10	Free alarms	<b>V</b>			Type of automatic logoff	None		
	11	Message Editing				Period of time before automatic logoff	None		
	12	Start archive				Web			
	13	Stop archive			"	WebNavigator			
	14	Edit archive values				WebNavigator start picture			
	15	Archive Editing				Use horn on Web client			
	16	Action Editing				WebUX			
	17	Project Manager				Start Picture of WebUX			
	18	Activate remote	<b>V</b>			Reserve WebUX license			
Tag Management	19	Configure remote				WebUx Number of reserved licenses	0		
	20	Web Access - monitoring only				Web language			
Alarm logging	21								
777	22								
Iag Logging	23								
■ # # ◆ 幸 国 ▼	24 ⊮	Authorizations		<ul><li>✓</li><li>→</li><li></li></ul>					
Ready NUM		Englis	n (United States)			Table: 20 Authorizations 100 %		-Q	÷.,

[pascc380, 1, en_US]

Figure 3-63 Assigning group rights

### Setting up a user

Set up a user in the new group and assign him specific rights.

- $\diamond$  Select the new group.
- ♦ Select User > Add user. The Add a new user dialog opens.
- ♦ In the **Login** entry field, enter the user name (e. g. **User 1**).
- ♦ Enter a password and repeat it.
- Select **Copy group settings also** to assign the user all rights of the corresponding group.

3.8 Setting up User Authorizations

Change Password ×
New password:
Verify password:
Security: High (100%)
OK Cancel

[pascc381, 1, en_US]

Figure 3-64 Setting up a user

♦ Assign the user additional, individual rights (e.g. Action Editing).

lser Administrator	«	Authorizations [ User_1 ]	
📲 📲 User Administrator		Function	Enable
🗄 👬 Administrator-Group	1	Benutzerverwaltung	
🔤 🛉 Administrator	2	Werteingabe	<b>V</b>
Group1	3	Prozessbedienung	1
User_1	4	Bildbearbeitung	
-	5	Bildwechsel	<b>V</b>
	6	Fensteranwahl	<b>V</b>
	7	Hardcopy	<b>V</b>
	8	Meldungen quittieren	<b>V</b>
	9	Meldungen sperren	1
	10	Meldungen freigeben	1
	11	Meldungsbearbeitung	
	12	Archiv starten	
	13	Archiv stoppen	
	14	Archivwertbearbeitung	
	15	Archivbearbeitung	
	16	Aktionsbearbeitung	1
	17	Projektmanager	
	18	Remote aktivieren	
	19	Remote projektieren	
	20	Web Zugriff - Nur beobachten	
	21		
	22	1	



### Assigning an authorization for a circuit breaker

You can assign authorizations for various different objects, such as circuit breakers and buttons, in the Object Properties window.

Proceed as follows to assign an authorization for a circuit breaker:

- ♦ Double-click the circuit breaker in the Graphics Designer.
   The SICAM Switch Control Properties dialog opens.
- ♦ Select the Advanced tab.

♦ Click the ... Button to the right of the **Operator authorization** field and select the desired authorization.

### Assigning an authorization for a button

Proceed as follows to assign an authorization for a Button:

- $\diamond$  In the Graphics Designer, right-click the corresponding button.
- ♦ Select Properties in the context menu.
- ♦ Click the **Others** level in the **Properties** tab.
- ♦ Double-click Authorization and select an entry.

# 4 Graphic Objects

4.1	Overview	104
4.2	Design of Graphic Objects	105
4.3	Using Graphic Objects	107
4.4	SICAM Switch Controls	108
4.5	Anwendungsbeispiele für die Funktionen	142
4.6	SICAM Electrical Device Control	144
4.7	SICAM Bay Overview	145
4.8	Measured/Metered Value Display	153

## 4.1 Overview

The SICAM graphic object library includes graphic objects for the representation of typical **substation control** and protection equipment (e.g. switchgears, displays). Additionally, graphic objects are available for **topo**logical coloring. You can use these graphic objects to create station diagrams in the Graphics Designer. This section describes objects and functions that can be used with the target systems **SICAM PAS, SICAM RTUS**, and **directly connected IEC 61850/IEC 60870-5-104 devices**.

This chapter describes the SICAM graphic objects **Circuit Breaker**, **Disconnector** and **Bay Overview** SICAM SCC V8.00 or later. Older SICAM graphic objects can still be used - for a description refer to 14 Components and Functions of Earlier SICAM PAS CC/SCC Versions.

## 4.2 Design of Graphic Objects

The SICAM graphic object library provides graphic objects for the representation of the components of a power network. You require these graphic objects for creating station diagrams. The ActiveX Controls are a special kind of graphic objects.

## 4.2.1 SICAM Graphic Objects

### Structure

A SICAM graphic object serves for the graphical representation of electrical equipment using dynamic display features.

### **Graphical representation**

The graphical representation of the SICAM graphic objects (e. g. circuit breaker) is based on the ANSI/IEEE 315 1975 (R1995) and ANSI/IEEE 315A 1986 (R1995) standards.

The SICAM graphic object library provides several typical graphic objects for each element.

### Dynamic display properties

Some graphic objects already include dynamic display properties.

With the dynamization you can visualize the station status in control and monitoring direction.

The typical dynamic display properties of a graphic object are defined by default. Finally, you only have to link the dynamic properties to the process via tags.

There are 3 different ways to set the parameters for dynamic display properties:

- via the Dynamic dialog
- via a C action or
- via a VBS action (Visual Basic action)

### **Dynamic Dialog**

In the Dynamic dialog, you can specify the dynamic display properties and thus the process interfacing (referred to as "tag connection").

To do this, you insert the available dynamic display properties into a predefined frame.

### C Action

The C action offers you more flexibility in Dynamization than the Dynamic Dialog. You can use all functions provided by SIMATIC WinCC, including SICAM PAS processing functions.

### SICAM graphic object library

In the SICAM graphic object library, some dynamic display properties of graphic objects are defined via the Dynamic dialog; others are defined via the C action. You can use the corresponding graphic objects alternatively.

## 4.2.2 ActiveX Controls

The following graphic objects are implemented as ActiveX Controls:

- Circuit Breaker, Disconnector, Load Break Switch, and Earth Isolator as SICAM Switch Control
- Bay Overview as SICAM Bay Overview Control
- Measured value object as SICAM Numeric Control
- Feeder, Ground Disconnector, Transformer, and Termination as SICAM Electrical Device Control

These ActiveX Controls in the Graphics Designer are available in the SICAM graphic object library.

### Structure

An ActiveX Control is a Windows control element whose properties (e. g. graphical representation, tag connection) can be defined via a dialog.

### **Graphical representation**

An ActiveX Control (e. g. a circuit breaker) can be graphically represented in various different manners. The form, line width and orientation of the graphic object can be specified by the user. 3-D representation is possible. Dialogs can be anchored at any position on the diagram.

The colors for the representation of the value and the status are selectable. Furthermore, the graphic object can be individually designed.

### **Tag connection**

The protocol type can be selected. Depending on the protocol type, the process interfacing of the ActiveX Controls can be performed using tags.

A tooltip text can be entered.

### **Further setting options**

The Synchronized/Not Synchronized Switching and Interlocked/Non-Interlocked Switching functions can be parameterized. Spontaneous Blinking, Setpoint Blinking and SET = ACTUAL Switching can be admitted. A twostep switching operation and Blinking with Negative Command Feedback can be parameterized. The command execution timeout can be defined and the user authorization can be selected.

## 4.3 Using Graphic Objects

To use graphic objects from the SICAM graphic object library in your project, you must link the SICAM graphic object library to the project first.

Afterwards only, you can position graphic objects in station diagrams and set parameters for dynamic display properties in order to visualize the different states of the station.

### SICAM graphic object library

Use the SICAM Wizard to integrate the SICAM graphic object library into the current project.

### Displaying the SICAM graphic object library

To display the SICAM graphic object library, select **View>Library**. The SICAM graphic objects are available under **Project Library**.

### Positioning graphic objects

Using the Graphics Designer of SIMATIC WinCC, you can copy graphic objects via Drag & Drop from the library into a station diagram.

### Defining graphic objects

Link graphic objects to the related process tags using the SIMATIC WinCC Graphics Designer.

## 4.4 SICAM Switch Controls

The **C**ircuit **B**reaker, the **Dis**connector, the Load Break Switch, and the Earth Isolator are available as switching devices. They are stored in the **Switching devices** folder as **SICAM Switch Control** in the SICAM graphic object library. These ActiveX Controls already include typical functions.

### **Graphical representation**

The SICAM graphic object library provides the SICAM Switch Controls in 5 different representation styles:

View	Circuit Breaker	Disconnector	Load Break Switch	Earth Isolator
SICAM style				
based on				
DIN 42200	Ę.	1	Ź.	5
based on				
IEC 445	- F	÷.	Y	-F
based on		$\sim$		$\sim$
LSA	•	$\bigcirc$	•	$\bigcirc$
based on		$\sim$	1	$\sim$
LSA		(		( )
(alternative; LSA-2)		$\bigcirc$	$\sim$	

 Table 4-1
 Graphical representation of SICAM Switch Controls



### NOTE

You can assign your own individual image files to the objects.



### NOTE

The element **Earth Isolator** is firmly connected to earth potential on one side, thus representing a 1-pole for topology calculation. The line must be connected to the left port (marked with a small square, see chapter 4.4 SICAM Switch Controls) of the earth isolator, the earth symbol can be connected to the right. To avoid errors in topology calculation, the earth isolator must be rotated via the SICAM Switch dialog with the **Orientation** parameter, if required; not via the WinCC Object properties dialog.

### **Connecting points**

The points highlighted with a square are the left-hand/top connecting points (below called **left-hand connection points**); the points (without a square) on the opposite side are the right-hand/bottom connecting points (below called **right-hand connection points**). See also 1- and 2-pole elements, Page 183.
## NOTE

The squares always indicate the left-hand/top connecting points independently of the rotation of the object.

## 4.4.1 Representation Style of SICAM Switch Controls

Each circuit breaker, each disconnector etc. must be assigned a certain number of properties.

- ♦ Double-click the graphic object.
  - The SICAM Switch Control Properties dialog opens.
- $\diamond \quad \text{Select the Style tab.}$

SICAM Switch Control Properties		$\times$
Style     Tag connection 1     Tag co       Type     O Circuit Breaker     O Disconnector       O Load Break Switch     O Earth Isolater	Display 3-D Style on click Touch operation Line width: 2 Direction: 0° Fix dialog position Y in pixels: 100 X in pixels: 100	
	OK Cancel <u>A</u> pp	ly

[sc_style_switch_control, 1, en_US] Figure 4-1 Defining the style

### Туре

The following graphic object types can be selected: Circuit Breaker, Disconnector, Load Break Switch, or Earth Isolator.

#### Norm

The following 6 options are available for the graphical representation of the graphic object:

- SICAM
- DIN 42200
- IEC 445
- LSA
- LSA-2
- Picture

Depending on the switch position, individual pictures can be displayed for the **Picture** style. In the **Picture** tab, the individual pictures must be assigned switch positions, see 4.4.5 *Picture of SICAM Switch Controls*.

## 3-D style on click

If this checkbox is activated, circuit breakers and disconnectors are represented with a three-dimensional effect when clicking with the mouse.

#### Line width

You can select a value to define the **Line width** of the graphic objects. Level 1 corresponds to the smallest line width.

The line width can be entered in representation styles in accordance with DIN 42200, IEC 445 and LSA.

#### Direction

Orientation is possible in the 0°, 90°, 180° and 270° angles in all representation styles apart from Picture.

## Fix dialog position

The Runtime dialogs can be anchored at a fixed position in the picture.

## 4.4.2 Process Connection of SICAM Switch Controls

Each circuit breaker, each disconnector etc. must be assigned tags. The assignment options depend on the protocol type.

You can assign tags in the Tag connection 1 and Tag connection 2 tabs.

- ♦ Double-click the graphic object.
   The SICAM Switch Control Properties dialog opens.
- ♦ Select the Tag connection 1 tab.

SICAM Switch Control Properties	×
Style Tag connection 1 Tag connection 2 Advanced Color Picture	
Protocol type: SICAM PAS Protocol Suite $\checkmark$	
Tag name information (*.RTInfo)	
Station_South_10kV_Bay_1_7SJ63_cb_switch.RTInfo	
Tag name command (*.RTCmd)	
Station_South_10kV_Bay_1_7SJ63_c_cb_switch.RTCmd	
Acknowledge flashing tag:	
AckFlashing	
Tooltip text:	
Bay1 CB	
OK Cancel Apply	

[sc_switch_process1, 1, en_US]

Figure 4-2 Tag connection, Part 1

## Protocol type

Select the desired protocol type from the drop-down list box. The following protocol types are available for selection:

- SICAM PAS Protocol Suite for connection to SICAM PAS-Stationen
- SICAM IEC Communication Suite for connection to SICAM RTUs or IEC 61850/IEC 60870-5-104 devices

## Information tag

Click the button to the right of the entry field. The **Tags** dialog opens. Select the corresponding tag from the list and click **OK** to confirm.

## Command tag

If a command tag for a related information tag is specified in the SICAM PAS import data record, the command tag is determined automatically when selecting the information tag and entered in the **Command tag** entry field.

To manually select a tag, proceed as described in the paragraph Information Tag.



## NOTE

Delete the predefined scripts if you do not want to use the stored functionality in command direction.

## Acknowledge flashing tag

You can assign a tag, e.g. the **AckFlashing** tag, for several switching device objects in order to form a group. In this case, you can acknowledge spontaneous flashing for all switching device objects of the group at the same time by clicking the **All** button.

To define acknowledgement groups, you can maintain the predefined **AckFlashing** tag or create a new tag. To select another tag, click the button to the right of the entry field. The **Tags** dialog opens. Select the corresponding tag from the list and click **OK** to confirm.

## Tooltip text

Enter a text in the entry field. This text is displayed as **Tooltip** in the active project.

Select the Tag connection 2 tab.

SICAM Switch Control Properties X				
Style Tag connection 1 Tag connection 2 Advanced Color Picture				
SICAM IED protocol: PAS - IEC 61850 devices $\checkmark$				
Tag name information 'not synchronized' (*.RTInfo)				
Station_South_10kV_Bay_1_7SJ63_cb_switch_unsynch.RTInfo				
Tag name command 'not synchronized' (*.RTCmd)				
Station_South_10kV_Bay_1_7SJ63_c_cb_switch_unsynch.RTCmd				
Tag name information 'non-interlocked' (*.RTInfo)				
Station_South_10kV_Bay_1_7SJ63_cb_switch_nolock.RTInfo				
Tag name command 'non-interlocked' (*.RTCmd)				
Station_South_10kV_Bay_1_7SJ63_c_cb_switch_nolock.RTCmd				
OK Cancel Apply				

[sc_switch_process2, 1, en_US]

Figure 4-3 Tag connection, Part 2

In the **Tag connection 2** tab, you can configure tags for the advanced control of synchronization and interlocking functions during command output.

You can only assign tags in this tab if the **SICAM PAS Protocol Suite** protocol type has been selected in the **Tag connection 1** tab, i.e. if the devices are connected via SICAM PAS.

### SICAM PAS IED protocol

Select the desired IED protocol from the list. The following setting options are available:

Not specified

Select this setting if you do not require the switchover of the synchronization or interlocking function during runtime.

With this setting you cannot assign tags.

### • PAS - IEC 61850 devices

Select this setting if devices are connected to SICAM PAS via IEC 61850. With this setting you can assign tags for controlling the Synchronized/Not Synchronized and Interlocked/ Non-Interlocked switching functions.

PAS - ILSA devices

Select this setting if devices are connected to SICAM PAS via ILSA. With this setting you can assign the command tags for unsynchronized switching and for a measurement interrogation.

Table 4-2	Process tag connection de	pending on the	target system and	the device type
				21

Protocol type	IED protocol	Attribute	Meaning
SICAM IEC Communication Suite	N/A	RTInfo	<information name="" tag="">.RTInfo</information>
or			
SICAM PAS Protocol Suite	None		
		RTCmd	<command name="" tag=""/> .RTCmd

Protocol type	IED protocol	Attribute	Meaning
SICAM PAS Protocol Suite	IEC 61850 devices	RTInfo	<information name="" tag="">.RTInfo</information>
		RTCmd	<command name="" tag=""/> .RTCmd
		AddRTInfo1	<pre><information name-<br="" tag="">NotSynchronized&gt;.RTInfo</information></pre>
		AddRTCmd1	<command name-<br="" tag=""/> NotSynchronized>.RTCmd
		AddRTInfo2	<information name-nonin-<br="" tag="">terlocked&gt;.RTInfo</information>
		AddRTCmd2	<command name-nonin-<br="" tag=""/> terlocked>.RTCmd
	ILSA devices	RTInfo	<information name="" tag="">.RTInfo</information>
		RTCmd	<command name="" tag=""/> .RTCmd
		AddRTCmd1	<command name-<br="" tag=""/> NotSynchronized>.RTInfo
		AddRTCmd2	<command name-measur-<br="" tag=""/> ementInterrogation>.RTCmd

#### Information tag

Click the button to the right of the entry field. The **Tags** dialog opens. Select the corresponding tag from the list and click **OK** to confirm.

## Command tag

If a command tag is specified for an information tag in the SICAM PAS import data record, the command tag is determined automatically when selecting the information tag and entered in the **Runtime command tag** editing field.

To manually select a tag, proceed as described in the paragraph Information Tag.

## NOTE

The descriptions of SIMATIC WinCC apply to the use of tag and server prefixes and indirect addressing. SICAM-specific processing is not necessary.

For more detailed information concerning the use of the acknowledgment tag without prefix, e.g. in picture windows, refer to the configuration information in the SIMATIC WinCC Information System, Using a Tag Prefix and a Server Prefix. A preceding @NOTP, for example, disables the use of the tag prefix.

## 4.4.3 Advanced Properties of SICAM Switch Controls

In the Advanced tab, you can assign the SICAM Switch Controls additional properties.

- Double-click the graphic object.
   The SICAM Switch Control Properties dialog opens.
- ♦ Select the Advanced tab.

SICAM Switch Control Prop	erties	×
Style Tag connection 1 Visible in RT not synchronized non-interlocked Preset not synchronized non-interlocked	Tag connection 2       Advanced       Color       Picture         Image: Enable spontaneous flashing       Image: Enable setpoint flashing       Image: Enable 'SET = ACTUAL'         Image: Enable 'Select before operate'       Image: Enable 'Select before operate'         Image: Flashing on negative confirmation       Command execution timeout in seconds:         Image: Select before operate       Image: Select before operate         Image: Select before operate       Image: Select before operate	
Operator authorization: <no access="" protection=""></no>	OK Cancel <u>A</u> pply	

[sc_switch_advanced, 1, en_US]

Figure 4-4 Advanced properties

For the connection to **SICAM RTUs** or **IEC 61850/IEC 60870-5-104 devices**, the command mode (Qualifier of Command, QoC) for command output must be transmitted with the command.

## Visible in RT

Under **Visible in RT**, activate the checkboxes for the options you want to show additionally during runtime in the switching dialog and which can be modified.

#### Preset

Under **Preset**, activate all values to be transmitted as qualifiers of command (QoC). If the **Visible in RT** option is activated, you can define here the pre-assignment in the runtime dialogs. The checkboxes under **Preset** can only be activated if the **SICAM IEC Communication Suite** protocol type has been selected in the **Tag connection 1** tab.

Table 4-3Configuration with different protocol types

Protocol type	Activated fields	Attribute	Effect
SICAM PAS Protocol Suite Visible in RT		Unsynchronized	Shown in the switching dialog during runtime.
		Non-interlocked	Shown in the switching dialog during runtime.

Protocol type	Activated fields	Attribute	Effect
SICAM IEC Communication Suite	Visible in RT	Unsynchronized	Shown in the switching dialog during runtime.
		Non-interlocked	Shown in the switching dialog during runtime.
	Specification L	Unsynchronized	Pre-assignment of the value sent as QoC as part of the command (synchronized/ unsynchronized switching)
		Non-interlocked	Pre-assignment of the value sent as QoC as part of the command (synchronized/ unsynchronized switching)

#### Enable spontaneous flashing

Spontaneous flashing can be enabled or disabled.

If the value of the assigned tag has changed and if **spontaneous** has been entered as cause, the Circuit Breaker or the Disconnector flashes spontaneously.

#### Enable setpoint flashing

Setpoint flashing can be enabled or disabled.

During command output the graphic object starts **flashing** in its SET state when the SET switching direction (ON or OFF) has been selected. It stops flashing as soon as the command has been terminated or aborted, i.e. in the following cases:

- After a command output has been aborted
- On expiry of the command output monitoring time
- If Command Termination is entered as cause in the command confirmation

### Enable SET = ACTUAL

Switching over to the represented actual state can be enabled or disabled. Activate this checkbox in order to enable the switching direction independently of the switch position. This ensures e.g. that another switch-on command can be issued for a switched-on switch.

#### Enable Select before operate

A Select command is issued before the actual switching command. The switching command can only be issued after the Select command has been positively acknowledged.

#### Flashing on negative confirmation

If a switching command is not successful, i.e. if CO-, COE-, Select, Command Monitoring Time Expired is returned, the switching device object changes from slow command blinking to fast blinking in order to indicate that an abnormal event has occurred.

There is no fast blinking if this option has been deactivated. The switching device object changes to the actual position after a negative acknowledgment; command blinking is terminated.

#### **Command execution timeout**

In the **command execution timeout** field, enter the maximum delay time in seconds until successful command execution. As soon as this time has expired, the command process is terminated and a negative command termination is entered in the log.



## NOTE

For IEC connections, the **command execution timeout** only affects the switching object. The command itself only gets affected with SICAM PAS connections.

## **Operator authorization**

Select the desired **operator authorization**. For more detailed information on the setting and assignment of operator authorizations, refer to 3.8 Setting up User Authorizations.

## 4.4.4 Colors of SICAM Switch Controls

The color of the graphic object in normal state depends on its value. A specific color is set by default for each individual value. However, the color can also be freely selected from a color palette. In the **Color** tab, you can assign colors for the individual switch positions and states of the SICAM Switch

In the **Color** tab, you can assign colors for the individual switch positions and states of the SICAM Switch Control.

- Double-click the graphic object.
   The SICAM Switch Control Properties dialog opens.
- ♦ Select the Color tab.

SICAM Switch Control Properties		
Style Tag connection 1	Tag connection 2 Advanced Color Picture	
Value	State	
ON	No connection	
OFF	Bay blocked	
Disturbed 00	Not topical	
Disturbed 11	Substituted	
Background	Telecontrol blocked	
	OK Cancel Apply	

[sc_switch_color, 1, en_US]

Figure 4-5 Assigning colors

## Value

The following colors are predefined for the graphic object:

Table 4-4 Switch position

Value	Color
ON 10, value = 2	Red
OFF 01, value = 1	Green
Intermediate position 00, value = 0	Yellow
Disturbed 11, value = 3	Yellow

The form of the graphic object in representation styles in accordance with **DIN 42200**, **IEC 445**, and **LSA** depends on the value.

Table 4-5	Predefined forms	according to		42200	and I	FC 44	15
Table 4-5	Fledenned Ionns	according to	DIN '	+2200	anui	EC 44	tJ

Value	Form
ON 10, Value = 2	Switch closed
OFF 01, Value = 1	Switch open
Intermediate position 00, Value = 0	Switch on/off dashed
Disturbed 11, Value = 3	Switch on/off dashed

Table 4-6 Predefined forms according to LSA

Value	Form
ON 10, Value = 2	Filled
OFF 01, Value = 1	Not filled
Intermediate position 00, Value = 0	Half filled
Disturbed 11, Value = 3	Half filled

A red cross is indicated for values which are not indicated in the tables (e.g. Value=4).

## Background

The background color of the graphic object can be individually defined. Gray is the default color.

## State

The switch status is represented with small, colored rectangles next to the switch. A default color is predefined for each status. The color can also be freely selected from a color palette.



[dw_cb_states, 1, en_US]

Figure 4-6 Switch with switch status

The predefined colors of the rectangles depend on the status:

Table 4-7 Switch Status	Table 4-7	Switch status
-------------------------	-----------	---------------

Status	Color	Explanation
System not ok	Dark cyan (teal)	Connection between SICAM SCC and the automa- tion system/ device.
Bay blocked	Red	Messages from this bay are no longer transmitted to the automation system/device.
Not topical	Cyan (turquoise)	The device state is not topical.
Substituted	Blue	The switch position was set manually because there is no connection to the primary system.
Telecontrol blocked	Red	Messages from this bay are no longer transmitted to the telecontrol center.

## 4.4.5 Picture of SICAM Switch Controls

The values of a SICAM Switch Control (switch positions) can be assigned to individual pictures. In order to ensure that these pictures are displayed during runtime, the **Picture** option must be activated in the **Style** tab under **Norm**, see *4.4.1 Representation Style of SICAM Switch Controls*. The following picture formats are possible:

- BMP
- EMF
- JPG
- GIF



## NOTE

If, in the **Style** tab under **Norm**, the **Picture** option is active, you have to assign pictures to the values. Otherwise no switching object will be displayed.

To apply values to the pictures follow these steps:

 $\diamond$  Double-click the graphic object.

The SICAM Switch Control Properties dialog opens.

♦ Select the **Picture** tab.

SICAM S	witch Control Prop	perties				×
Style	Tag connection 1	Tag connection 2	Advanced	Color	Picture	
Prope DIST DIST DIST OFFF ORFF ONP ONP	arties: OOPicture OOPictureBlink 11Picture 11PictureBlink Picture PictureBlink rictureBlink	Preview:				
		Browse		Cle	ear	
		ОК	Ca	ancel	Apply	

[sc_switch_picture, 1, en_US]

Figure 4-7 Assigning pictures

### Properties

The values of the Circuit Breaker/Disconnector are listed under **Properties**. You can assign a picture and a **blink picture** to each value. During runtime, the following representations result for a switching object:

### • No blink picture assigned

The display switches between picture and background color.

## Blink picture assigned

The display switches between picture and blink picture.

Highlight a value and click **Browse** to assign the value a picture. Pictures are stored in the WinCC project in the **\GraCS\SicamIXPics** directory. You can assign these pictures or individual pictures.

- **DIST00Picture** Picture for the representation of Value 0 - Intermediate position
- **DIST00PictureBlink** Blink picture for the representation of Value 0 - Intermediate position
- DIST11Picture Picture for the representation of Value 3 - Disturbed
- **DIST11PictureBlink** Blink picture for the representation of Value 3 - Disturbed
- OFFPicture Picture for the representation of Value 1 - OFF
- **OFFPictureBlink** Blink picture for the representation of Value 1 - OFF
- **ONPicture** Picture for the representation of Value 2 - ON
- **ONPictureBlink** Blink picture for the representation of Value 2 - ON

## Preview

The assigned picture is shown in a preview.

## 4.4.6 Runtime Dialogs of SICAM Switch Controls

Dialogs are available for performing switching operations, for status display, to acknowledge blinking and for synchronization.

To call up these dialogs during runtime, click the graphic object.

## 2-Step Switching Operation

Click the graphic object to open the dialog for a switching operation.

SICAM Switch C	ontrol	
	^	
	$\vee$	
Schalten		
EIN	AUS	
Abbrechen		

[SCC_RT_401, 1, en_US]

Figure 4-8 Switching Dialog without Command Mode

Use the following dialog for switching operations with SICAM RTUs and IEC 61850/IEC 60870-5-104 devices. Controlling is performed via the SICAM IEC COMMUNICATION SUITE with the IEC 61850/IEC 60870-5-104 communication protocol.

7SJ63 Q0	
	^
	~
Command mode	
not synchronized	
Switching	
Unsync ON OFF	
Cancel	

[SCC_RT_402, 1, en_US]

Switching Dialog with Command Mode Figure 4-9

This dialog is extended by 2 setting options for the selection of the command mode (Qualifier of Command, QoC).

The command mode can be defined with the following object properties in the object properties of the switching devices:

Visible in RT •

> Under Visible in RT, activate the checkboxes for the options you want to show additionally during runtime in the switching dialog and which can be modified.

Preset •

Under Preset, activate the values to be transmitted.

If the Visible in RT option is activated, you can define the pre-assignment in the runtime dialogs. The checkboxes under Preset can only be activated if the SICAM IEC Communication Suite protocol type has been selected in the Tag connection 1 tab.

Table 4-8 Config	uration with Different	Protocol Types	
Protocol type	Attribute	Effe	ect if activated
SICAM PAS Protocol S	uite Not synchro	nized Sen swi	ids a marker command for unsynchronized tching to SICAM PAS.
		This this	s is indicated in the check box with return of marker command.
	Non-interlo	ked Sen swi	ids a marker command for non-interlocked tching to SICAM PAS.
		This this	s is indicated in the check box with return of marker command.
SICAM IEC Communic Suite	ation Not synchro	nized Sen con con	nds the Not synchronized Switching qualifier of nmand with the switching command in the nmand value.
	Non-interlo	ked Sen con con	nds the Non-Interlocked Switching qualifier of nmand with the switching command in the nmand value.

You can define the parameters of the Select before operate function via the properties of the control in the Graphics Designer, see 4.4.3 Advanced Properties of SICAM Switch Controls.

After clicking **ON** or **OFF**, the Select command is transmitted if the bay devices are connected via IEC 61850. The **ON** and **OFF** buttons are disabled until a confirmation has been received. If the Select command has been successful, the Confirm dialog (see *Figure 4-11*) opens directly.

SICAM Switch C	ontrol
	^
	~
Schalten	
EIN	AUS
Abbre	chen

#### [SCC_RT_403, 1, en_US]

Figure 4-10 Switching Dialog, Select Command Is Running

The select command can receive a positive or negative acknowledgment. Depending on the acknowledgment, one of the following dialogs opens.

ON	
Selecting is enabled	٨
	v
< >	
Confirm	
Cancel	

[SCC_RT_404, 1, en_US]

Figure 4-11 Switching Dialog, Selection Is Active

The check resulted in a positive acknowledgment. The actual switching command can be issued by clicking the **Confirm** button.

7SJ63 Q0	
Effect of last control attempt: command not accepted	^
	$\vee$
Switching	
ON OFF	
Cancel	

[SCC_RT_405, 1, en_US]

Figure 4-12 Switching Dialog, Selection Rejected

The actual switching command cannot be issued. The switching operation must be aborted.

## Synchronized/Not Synchronized and Interlocked/Non-Interlocked Switching

For the connection of devices to SICAM PAS via the **IEC 61850** and **SINAUT LSA ILSA** communication protocols, switching is possible by means of dialog extensions, **Command mode** dialog field. The following options can be selected by means of the dialog extensions:

- Synchronized or Not Synchronized switching
- Interlocked or Non-interlocked switching

The sequence of the advanced switching operation during runtime depends on the **IEC 61850** or **SINAUT LSA ILSA** communication protocol. For this reason, a distinction is made between the communication protocols in the paragraphs below.

Synchronized/interlocked switching is supported by further communication protocols (e.g. IEC 60870-5-101-Master). In this context, however, the dialog extensions are not used.

The dialog extensions for synchronization and interlocking are only displayed if you have activated the corresponding option in the **SICAM Switch Control Properties**, **Advanced** tab under **Visible in RT**, see 4.4.3 Advanced Properties of SICAM Switch Controls.

## IEC 61850 Communication Protocol

This section describes the sequence of an advanced switching operation for the connection of devices to SICAM PAS via the IEC 61850 communication protocol.

Click the graphic object to open the dialog window for an advanced switching operation.

7SJ63 Q0	
	^
	$\sim$
Command mode  not synchronized  non-interlocked	
Switching	_
Unsync ON OFF	
Cancel	

[SCC_RT_402, 1, en_US]

Figure 4-13 Switching Dialog with Dialog Extensions

A confirmation dialog opens if you activate the Not synchronized or Non-interlocked checkbox.

not synchronized	
	^
	$\sim$
< 2	>
Confirm	
Cancel	

[SCC_RT_406, 1, en_US]

Figure 4-14 Confirmation Dialog

Click **Confirm** to issue a single command with the value **OFF** to the **Sync not effective** or **Non-interlocked** command tag.

At the same time, all the buttons are deactivated until a command feedback is received.

7SJ63 Q0	
Command is running	^
	$\sim$
Command mode	
not synchronized	
non-interlocked	
Switching	
Unsync ON OFF	
Cancel	

[SCC_RT_407, 1, en_US]

Figure 4-15 Advanced Switching Dialog for Synchronized Switching, Buttons Deactivated

As soon as a message has arrived via the **Sync not effective** information tag, the **Sync ON** button is activated and can be clicked.

The same procedure applies to non-interlocked switching.

7SJ63 Q0	
	^
	$\sim$
Command mode	
not synchronized	
Switching	
Sync ON OFF	
Cancel	

[SCC_RT_408, 1, en_US]

 $\diamond$ 

Figure 4-16 Advanced Switching Dialog for Synchronized Switching, Sync ON Button Activated

The Sync ON button can only be used for synchronized switching. The switching command is issued as usual:

♦ Click **Sync ON**.

The control blinks in the setpoint status and the confirmation dialog opens.

Click **Confirm**.

The command is issued.

As long as the synchronized switching command is running, you can still abort the synchronization.

To abort the synchronization, click the graphic object.
 The switching dialog with the **Abort synchronization** button opens.

7SJ63 Q0	
Command is running	^
	$\sim$
Command mode	
not synchronized	
non-interlocked	
Switching	
Abort synchronization	
1	
Cancel	

[SCC_RT_413, 1, en_US]



## ♦ Click Abort synchronization.

Synchronized switching is aborted.

### SINAUT LSA ILSA Communication Protocol

This section describes the sequence of the advanced switching operation for the connection of devices to SICAM PAS using the SINAUT LSA ILSA communication protocol.

Click the graphic object to open the dialog window for an advanced switching operation.

7SJ63 Q0	
	^
	~
Command mode	
not synchror	nized
Switching	
ON	OFF
Can	cel
Start meas	Stop meas

#### [SCC_RT_409, 1, en_US]

Figure 4-18 Switching Dialog for Synchronized/Not Synchronized Switching

If the **Not synchronized** checkbox has been activated, the command tag for Not synchronized switching is used for the subsequent command output. The inscription on the button changes from **Sync ON** to **Unsync ON**.

Click the **Sync ON** button to send a Synchronized Switching command with the normal command tag (Tag connection 1). The switching command is issued as usual:

♦ Click Sync ON.

The control blinks in the setpoint status and the confirmation dialog opens.

♦ Click Confirm.
 The command is issued.

Click **Start Meas** to issue a measurement trigger to the synchronization unit. The measured values are updated without performing a switching operation.

#### Status

The status dialog can be opened by clicking with the right mouse button, provided that the status display has been activated in the Properties dialog.

An information-specific block can be defined for the information of the SICAM PAS target system in combination with SICAM PAS/PQS V8.01 or later. This means that the process value update can be blocked for individual information objects, here: Double-point indication. You can set/undo the bay blocking/telecontrol blocking in the status dialog of the switching device objects. To do this, activate the corresponding function.

7SJ63 Q0	
Value is not topical!	^
	~
No connection	
Not topical	
Bay blocked	
Telecontrol blocked	
Substituted	
Substitute	
Close	



The current status is also indicated by a tick in the corresponding checkbox in the status dialog; the switch is marked with a colored rectangle, see switching status in *Figure 4-6*.

If **Bay blocked** is activated, the switch position can be substituted by clicking **Substitute**. The dialog for substituting a switch position opens, see 4.4.7 *Substituting the Switch Position*.

## Acknowledge Blinking

Click a blinking graphic object to open the **Acknowledging blinking** dialog.

7SJ63 Q0	
State or value cha	anged!
	~
Acknowledge fla	shing
This	All
Car	icel

[SCC_RT_411, 1, en_US]

Figure 4-20 Acknowledge Blinking

Click This to acknowledge a status change or a spontaneous alarm for this switch.

Click All to use the tag entered in the properties under

Tag name acknowledgement tag for spontaneous flashing for acknowledging. All ActiveX Controls currently displayed in the diagram and connected to this tag are acknowledged at the same time.

## NOTE

To enter a new command, the flashing must be acknowledged first.

## 4.4.7 Substituting the Switch Position

Substitute
O Disturbed 00
OFF
ON
O Disturbed 11
Substitute
Cancel

[SCC_RT_412, 1, en_US]

Figure 4-21 Substituting the Switch Position

In this dialog, you specify how the switch position is to be substituted. Click **Substitute** in order to open the Confirm dialog. Click the **Confirm** button to execute the substitution.

### Substituting Switch Positions for IEC 61850 Devices

To substitute switch positions for IEC 61850 devices, the SICAM IED protocol **SICAM PAS – IEC 61850 devices** must be selected in the SICAM Switch Control Properties, **Tag connection 2** tab. Furthermore, the tag to be substituted must be selected from the drop-down list below.

SICAM Switch Control Properties X
Style Tag connection 1 Tag connection 2 Advanced Color Picture
Protocol type: SICAM IEC Communication Suite $\checkmark$
Tag name information (*.RTInfo)
SubstationNorth_SIP_7SL87_CB1_ctrl_Cmd_FB_stVal.RTInfo
Tag name command (*.RTCmd)
SubstationNorth_SIP_7SL87_c_CB1_ctrl_Cmd_FB_ctVal.RTCmd
Acknowledge flashing tag:
AckFlashing
Tooltip text:
7SL87 CB1
OK Cancel Apply

[sc_prop_switch_control_2, 1, en_US]

Figure 4-22 Defining SICAM Switch Control Properties – Tag connection 1

SICAM	Switch Control Pro	perties				×
Style	Tag connection 1	Tag connection 2	Advanced	Color	Picture	
SICA	M IED protocol:	IEC - IEC 61850 d	levices		$\sim$	
Tag n	ame information 'sub	stitute' (*.RTInfo)				
Subs	stationNorth_SIP_7S	L87_CB1_ctrl_Cmd_I	FB_SubVal.R	TInfo		
Tagin	ame command " (*.R	.TCmd)				
Tagin	name information " (*	.RTInfo)				
Tagin	ame command " (*.R	.TCmd)			1	
		ОК	Ca	ancel	Ap	ply

[sc_prop_switch_control, 2, en_US]

Figure 4-23 Defining SICAM Switch Control Properties – Tag connection 2



## NOTE

Substituting is only possible on IEC 61850 data points with Functional Constraint (FC) SV, e.g. SubVal. For IEC 61850 devices, substitution is usually performed to the XCBR or XCSWI data point.

Alternatively, you can create a new **SubVal2IED = 1** in the 61850.ini file under [GENERAL]; in this case, the .stVal can be used directly for substitution.

## 4.4.8 Defining Object Properties

The Object properties dialog consists of the **Properties** and **Events** tabs. The following section describes certain parameters from these tabs.

Proceed as follows to open the **Object properties** dialog:

- ♦ Right-click the graphic object.
- Select Properties in the context menu.
   The Object properties dialog opens.

## **Properties tab**

SICAMSwitchCtrl	Attribute	Static	Dynamic	Update	Indir
Geometry	RTInfo		Q		
Miscellaneous	RTCmd		Q		
- Control Properties	AddRTInfo1		Q		
	AddRTCmd1		Q		
	AddRTInfo2		Q		
	AddRTCmd2		Q		
	ProtocolType	SICAM PAS Protocol Si	Q		
	PASIEDProtocol	none - 0	Q		
	CmdModeVisible	none - 0	Q		
	CmdModeDefault	none - 0	Q		
	DrawWidth	2	Q		
	BackColor		Q		
	SwitchTune	Circuit Bresker - A	0		

[sc_switchcontrol_props, 1, en_US]

Figure 4-24 Object properties, Properties tab

The following table provides a list of certain important object properties of the circuit breakers/disconnectors.

Object properties	Meaning
Operator control enable	The user can define for the SICAM Switch Control whether or not the object can
	be operated during runtime.
	In order to be able to operate an object, the user must have the corresponding
	authorization.
DrawWidth	Drawing width in dots.
	The drawing width of the graphic object can be defined. Step 1 represents the smallest line width.
	The adjustment of the line width is possible for all representation styles according to DIN 42200, IEC 445 and LSA.
BackColor	Background color of the control. This color is displayed when the control blinks.
SwitchType	Type of control, circuit breaker or disconnector.
Norm	Graphical representation style of the SICAM Switch Control.
	For a list of possible styles, refer to Graphical representation, Page 108

Table 4-9	Object properties
-----------	-------------------

Object properties	Meaning
Direction	Picture rotation in degrees:
	• 0
	• 90
	• 180
	• 270
Style3D	3D representation:
	• Yes
	• No
	The 3D style illustrates the view of the selected object.
DialogPosLeft	This property defines the position of the left-hand edge of the Runtime dialog.
DialogPosTop	This property defines the position of the upper edge of the Runtime dialog.
FixDialogPosition	This property defines whether the dialog shall be opened next to the object or next to the defined position.
ToolTipText	This property defines a tooltip text in the picture.
ONPicture	If the <b>Picture</b> setting is defined in the Properties dialog, <b>Style &gt; Norm</b> tab, the picture configured under <b>ONPicture</b> ( <b>Picture</b> tab) is shown for the ON (2) status.
	⇒ The ActiveX properties dialog opens.
OFFPicture	If the <b>Picture</b> setting is defined in the Properties dialog, <b>Style &gt; Norm</b> tab, the picture configured under <b>OFFPicture</b> ( <b>Picture</b> tab) is shown for the OFF (1) status.
	⇒ The ActiveX properties dialog opens.
DISTOOPicture	If the <b>Picture</b> setting is defined in the Properties dialog, <b>Style &gt; Norm</b> tab, the picture configured under <b>DISTOOPicture</b> ( <b>Picture</b> tab) is shown for the Intermediate Position (0) state.
	⇒ The ActiveX properties dialog opens.
DIST11Picture	If the <b>Picture</b> setting is defined in the Properties dialog, <b>Style &gt; Norm</b> tab, the picture configured under <b>DIST11Picture</b> ( <b>Picture</b> tab), is shown for the fault position (3) state.
	⇒ The ActiveX properties dialog opens.
ONColor	With this property you define the color for the ON state.
OFFColor	With this property you define the color for the OFF state.
DISTOOColor	With this property you define the color for the Intermediate Position with the value 0.
DIST11Color	With this property you define the color for the fault position with the value 3.
NotTopicalColor	With this property you define the color for the <b>Not topical</b> status of the device information. The device is switched off or cannot be contacted.
PASNotOKColor	With this property you define the color for the <b>PAS not OK</b> status. There is no connection to the target system.
BayBlockedColor	With this property you define the color for the bay block defined.
SubstitutedColor	With this property you define the color for substituted values.
TeleBlockedColor	With this property you define the color for the telecontrol block defined.

Object properties	Meaning	
StateColorVisibleFlag	With this property you define the display of the following statuses:	
	• 0x0100: Bay blocking	
	• 0x0400: Not topical	
	Ox0800: Substituted value	
	Ox2000: Telecontrol blocking	
	• 0x0008: No connection to the target system	
	The default value is 0x0100   0x0400   0x0800   0x2000   0x0008 = 11528: All statuses are shown.	
CommandTimeout	The command execution is canceled by SICAM PAS if there is no feedback from the process. This value can also be modified in the <b>Advanced</b> tab.	
	The control switches to normal state or to <b>Spontaneous flashing</b> .	
EnableSpontaneous- Flashing	With this property you enable spontaneous flashing in case of spontaneous messages.	
EnableSetPointFlashing	With this property you enable spontaneous flashing when selecting the switching direction in the Command dialog.	
Enable Flashing On- Neg Confirm	With this property you enable spontaneous flashing in case of a negative command acknowledgement.	
	Flashing is only enabled for the control which has been operated. Other controls with the same tag connection or controls on a redundant system do not flash.	
EnableSETIsACTUAL	With this property you enable switching to the ACTUAL state of the switching device, e.g. sending an ON command if the device is already in ON state.	
Authorization	With this property you assign authorizations.	
	0 = without authorization check	
	The authorizations of the User administrator settings are checked.	
AckSpontanFlashing	With this property you enable the simultaneous acknowledgement of several controls in a group.	
InputValue1	Input points for topological coloring.	
InputValue2		
TOPOColorINVALID	This value defines the default color for lines in the INVALID state.	
	It is forwarded to the related connectors if the graphic object is in the INVALIFD state.	
TOPOColorOFF	Default value for defining the color in case of topological coloring.	
	This value is transferred to the corresponding connectors if the graphic object is in the OFF status.	
ConnectorAttributes	see Topological Settings for Selected Objects, Page 185	
ColorUse	see Topological Settings for Selected Objects, Page 185	

## **Events** tab

Object Properties Properties Events		
Control Properties Focus Object Events Property Topics Geometry Miscellaneous	Execute on OnLeftClick OnRightClick OnExecuteCmd OnOutput1 OnOutput2 OnProcDataChange	Action
🔲 Object Properties 🕒	ibrary   K Dynamic Wiz	ard

[sc_switchcontrol_event, 1, en_US]

Figure 4-25 Object properties, Events tab

OnLeftClick

The switching dialog is opened by default via the **OnLeftClick** event.

OnRightClick

The status dialog is opened by default via the **OnRightClick** event.

OnExecuteCmd

The command type (internal) and the command value are transferred to the **OnExecuteCmd_V800(...)** C script via the **OnExecuteCmd** event.

The switching dialog and the status dialog are opened by default in the **OnLeftClick** and **OnRightClick** events. You can adapt the scripts of these events to your specific requirements.

In the **OnExecuteCmd** event, the **PAS_CommandExecute_V800** command output script is called up. The command type and the command value are transferred to this script.

You can complement these events in order to adapt the integrated command output mechanism to your specific requirements.

The C script of the **OnExecuteCmd** event is shown in the screenshot below. Insert your script lines before calling up **PAS_CommandExecute_V800**.



[SICAMSwitch_Script, 1, -_-] Figure 4-26 OnExecuteCmd C script, SICAM Switch Control graphic object The information required for command output using the SICAM Switch Control graphic object and the processing of the SICAM SCC Runtime Data Server tags in C scripts is available in the **SCC_Def.h** file. Integrate this header file into the C script.

The values and meanings of the cmdtype and cmdvalue tags are listed in the tables below.

Command type	Enum tag	Value
Information-specific block	Command_Set_Blockstate	-3
Substitute	Command_Substitute	-2
Acknowledge flashing	Command_Acknowledge	-1
Switching	Command_Switch	1
Set point	Command_Setpoint	2
Select	Command_Select	3
Abortion	Command_Abort	4

Table 4-10 Command types and related values in the cmdtype tag

The Switch command type is also used for the output of the Not synchronized and Non-interlocked options.

 Table 4-11
 Command values in the cmdvalue tag and their meaning

Valid for command	Meaning	Constant	Value
types			
Substitute, Switch, Select	Switch position Inter-	VALUE_SWITCH_DIST00	0
and	mediate position		
Not Synchronized, Non-	Switch position OFF	VALUE_SWITCH_OFF	1
Interlocked changeover	Switch position ON	VALUE_SWITCH_ON	2
	Switch position disturbed	VALUE_SWITCH_DIST11	3
Acknowledge flashing	One object	VALUE_ACKNOWLEDGE_THIS	1
	All objects (depending on the Acknowledge tag)	VALUE_ACKNOWLEDGE_ALL	2

## 4.4.9 Operation with Self-Created Dialogs

If it is not sufficient to adapt the event scripts to normal dialog control, you can replace the default dialogs by customized dialogs. To do this, you must edit the scripts which open the switching dialog and save them under a new name.

Example of a self-created switching dialog: When clicking on the switching device objects with the left mouse button, the command tag name is written in a text tag, and the self-created switching dialog opens.

In your switching dialog you can use the **ON** or **OFF** button and the intermediately stored command tag name to call up a command output script, e.g. SCC_Command. To implement a two-stage command output, you can comment the increase of the counter tag in this script at the point described (*II* start: execute the command).

Rename the script, e.g. void SCC_Command_NoExecute(), and save it under this name. Use the SCC_CommandExecute_V500 script to send the command.

This screenshot provides an example of self-created dialogs with large touch operation buttons:

25kV\Bay01\Q0	25kV\Bay01\Q0
ON	Execute
OFF	
Cancel	Cancel

[scc439, 1, en_US]

Figure 4-27 Example, self-created dialogs

//Return-Type: long int

### Authorization Check

To also enable a check of the Authorization level with self-created dialogs, insert an authorization check in the OnLeftClick/OnRightClick events that you use.

```
#include "apdefap.h"
void OnRightClick(char* lpszPictureName, char* lpszObjectName)
// WINCC:TAGNAME SECTION START
// syntax: #define TagNameInAction "DMTagName"
// next TagID : 1
// WINCC:TAGNAME_SECTION_END
// WINCC: PICNAME SECTION START
// syntax: #define PicNameInAction "PictureName"
// next PicID : 1
// WINCC: PICNAME SECTION END
#pragma code ("useadmin.dll")
#include "PWRT_api.h"
#pragma code()
BOOL bPermission = FALSE;
long int iPermissionLevel = 0;
extern BOOL g_debug;
iPermissionLevel = GetPropWord(lpszPictureName,lpszObjectName, "Authorization");
 if (g_debug)
   { printf ("Authorization level: %d\n", iPermissionLevel);}
 bPermission = PWRTCheckPermission ( (DWORD) iPermissionLevel, FALSE); // To suppress WinCC Message
Box set: False to TRUE
 if ( !bPermission )
   if (g_debug)
      { printf ("PWRTCheckPermission: No Permission\n");}
 }
 else
 {
   if (g_debug)
      { printf ("PWRTCheckPermission: Permission OK\n");}
   // Add your script code here
   11
 }
}
```

[sc authorization check, 1, -- --]

## 4.4.10 Operation via Keyboard

The SICAM Switch Controls graphic objects can be operated via the mouse or using the keyboard.

To initiate a switching operation using the keyboard, **buttons** must be inserted into the display, and a **hotkey** must be configured for each button.

The switching operation is initiated by pressing the configured key or key combination during runtime. Additionally, a user right can be assigned for the operation of the button.

The **runtime dialogs** of switching device objects are not displayed for operation via keyboard/buttons. An ordinary PC keyboard or a special function keyboard can be used. To use a function keyboard, the PC keyboard must be removed from the computer and the function keyboard must be plugged in instead.

## **Configuring a button**

A specific button for each action must be inserted into the diagram (**Object palette > Windows object**). The **Button Configuration** dialog opens as soon as the button has been inserted.

Button Configuration	ı	?	$\times$
Text:	CB1 ON		
Font	Arial		
Color			
Operation:	<kein td="" zugriffssch<=""><td>utz&gt;</td><td></td></kein>	utz>	
Shortcut			
Change Picture on Mo	ouse Click:		
			ħ
	OK	Can	cel

[pascc440, 1, en_US]

Figure 4-28 Configuring a button

- $\diamond$  Enter the button text into the Text entry field.
- ♦ Next, click **Hotkey...** to define a hotkey for the button.
- ♦ Click **OK** to close the dialog.

For more detailed information regarding the configuration of a button, refer to the WinCC Information System.

## Defining a C script

In order to be able to initiate an action via a button for **SICAM Switch Controls**, a C script has to be defined for the button. When clicking this button, the C script executes the **SCC_Command** function. This function transfers the object name, the command type, and the command value.

In the following example an **ON** Select command shall be transmitted for a switching object.

- ♦ Open the **Object properties** of the button.
- ♦ Select the **Miscellaneous** entry in the **Properties** tab.
- ♦ For the Hotkey attribute, configure a function key to which the button shall respond.
- ♦ Select Mouse in the Event tab.

Button Mouse Keyboard Focus Miscellaneous Property Topics Geometry Colors	<ul> <li>Execute on</li> <li>Mouse Click</li> <li>Press Left</li> <li>Release Left</li> <li>Press Right</li> <li>Release Right</li> </ul>	Action C-Action VBS-Action Connection Delete	
------------------------------------------------------------------------------------------------	-------------------------------------------------------------------------------------------------------------------------------------------	----------------------------------------------------------	--

[pascc441, 1, en_US]

Figure 4-29 Opening the editor

- ♦ Right-click Mouse Action in the Action column.
- Select C Action from the context menu.
   The editor opens and the C script is displayed.

The name of the selected control can be dynamically determined in the C script using the Get_Focus function.

- ♦ Edit the C script.
- $\diamond$  Compile the C script and click **OK** to close the editor.

You can now add further buttons for **deactivating**, **confirming**, and **canceling** the switching operation and configure these buttons accordingly. In this case, the diagram looks as shown below.



[pascc443, 1, en_US]

Figure 4-30 Diagram with buttons for a switching operation

Define the **TAB order** in the Graphics Designer in order to be able to select the controls using the keyboard. Afterwards, you can select the controls using the Tab key on the keyboard during runtime.

## Switching operation during runtime

During runtime, a switching operation (OFF > ON) would be executed as follows:

- The switch is in **OFF** state. You press the **CB1 ON** hotkey on the keyboard.
- The switching device object starts blinking in setpoint state.
- You press the **CB1 Confirm** hotkey on the keyboard. The switching command is executed.
- The switching device object switches to the **ON** state. The switching operation is completed.

Feedback messages regarding the switching operation are shown in the event list.

# 4.4.11 Interfaces for Project-Specific Dialogs

The **SICAMSwitch.dll** has been extended by several interfaces which enable the communication of selfcreated dialogs with the SICAM Switch Control in the same way as for the integrated dialogs.

## 4.4.11.1 SetControlCommand Function

This functions allows the user to transmit all operations of the intergrated dialog from the outside to the SICAM Switch Control.

## Command

SetControlCommand (LONG CmdType, LONG ButtonID, LONG ButtonStates)

### Parameter

CmdType transfers the command type.

Information-specific block	Command_Set_Blockstate	-3
Substitute	Command_Substitute	-2
Acknowledge flashing	Command_Acknowledge	-1
Switching	Command_Switch	1
Set point	Command_Setpoint	2
Select	Command_Select	3
Abortion	Command_Abort	4

ButtonID transfers the ID of the actuated button.

ButtonStates defines the button mask, i.e. the IDs of the buttons actuated are linked via an OR operation and transferred.

enum	ButtonID {		
	sccds_Btn_Diff	= 0x0001,	
	sccds_Btn_Off	= 0x0002,	
	sccds_Btn_On	= 0x0004,	
	sccds_Btn_Stoer	= 0x0008,	
	sccds_Btn_WithLock	= 0x0010,	
	sccds_Btn_NoLock	= 0x0020,	
	sccds_Btn_WithSynch	= 0x0040,	/* with PSG */
	sccds_Btn_NoSynch	= 0x0080,	/* without PSG */
	sccds_Btn_CancelSynch	= 0x0100,	/* cancel PSG */
	sccds_Btn_Select	= 0x0200,	
	sccds_Btn_Execute	= 0x0400,	
	sccds_Btn_Cancel	= 0x0800,	
	sccds_Btn_ACK_THIS	= 0x1000,	
	sccds Btn ACK ALL	= 0x2000	

[sc_fct_1, 1, --_--]

## 4.4.11.2 GetControlState Function

This function is used to read out the current status of the SICAM Switch Control. The **enum** value is transferred upon the call; afterwards the return value is indicated here.t.

#### Command

GetControlState ( VARIANT* pVal)

enum GetControlState {	
gcs_Version = 1,	// 01
gcs_get_Value,	// 02
gcs_get_Cause,	// 03
gcs_get_AddCause,	// 04
gcs_get_QualityCode,	// 05
gcs_get_VarType,	// 06
T-D-t-T-lil	(/ 07
gcs_ISDatavalid,	// 0/
gcs_lsHeld,	// 08
gcs_IsOverflowed,	// 09
gcs_IsBayBlocked,	// 10
gcs_IsRemoteBlocked,	// 11
gcs_IsSubstituted,	// 12
gcs_IsDataServerNotOK,	// 13
gcs_IsNoVar,	// 14
gcs_IsDemoMode,	// 15
gcs_IsDemoModeExpired,	// 16
gcs_IsNotTopical,	// 17
gcs_IsSubstitutionEnabled,	// 18
gcs_IsSpontaneousFlashing,	// 19
gcs_IsSwitchEnabled,	// 20
gcs_getControlCommandState,	// 21
gcs_get_Cmd_Value,	// 22
gcs_get_Cmd_Cause,	// 23
gcs_get_Cmd_AddCause,	// 24
gcs_Cmd_IsDataValid,	// 25
gcs_get_Cmd_ValueType,	// 26
gcs_set_Cmd_ValueType,	// 27
gcs_get_LimitStates	// 28

## };

[sc_fct_2, 2, --_--]

gcs_get_LimitStates return values:

- Bit 0: Command Timer Timeout
- Bit 1: Setpoint Flashing
- Bit 2: Spontaneous Flashing

## 4.4.11.3 Event OnProcDataChange

```
The event is triggered by SICAMSwitch if the object status changes.
void OnProcDataChange(char* lpszPictureName, char* lpszObjectName , long opdcEvent, long value)
{...}
opdcEvent:
enum OnProcDataChange {
     opdc Select
                           = eSelect,
                                                 // 16
                                                // 17
     opdc SelectConfPos = eSelectConfPos,
                                                 // 18
     opdc SelectConfNeg = eSelectConfNeg,
                                                 // 19
     opdc Command
                          = eCommand,
                                                // 20
     opdc CommandConfPos = eCommandConfPos,
     opdc CommandConfNeg = eCommandConfNeg,
                                                // 21
                                                 // # 25
     opdc Abort
                          = eAbort,
                                               // 26
     opdc AbortConfPos = eAbortConfPos,
     opdc_AbortConfNeg = eAbortConfNeg,
                                                // 27
     opdc CommandTermPos = eCommandTermPos,
                                                // # 35
                                                // 36
     opdc CommandTermNeg = eCommandTermNeg,
                                                // 37
     opdc AbortTermPos = eAbortTermPos,
     opdc AbortTermNeg = eAbortTermNeg,
                                                // 38
                                                 // 39
     opdc SelectTermPos = eSelectTermPos,
     opdc SelectTermNeg = eSelectTermNeg,
                                                 // 40
     opdc newValue = 100,
                                                 // # 100
                                                 // 101
     opdc TimeOutSelect,
                                                 // 102
     opdc TimeOutSelected,
                                                 // 103
     opdc TimeOutExecute
     opdc new lValue = 110,
                                                 // # 110, long
                                                 // 111, unsigned long
     opdc new ulValue,
```

```
// 112, float
```

#### [sc_fct_3, 2, --_--]

};

opdc new fValue

The **value** parameter indicates the value, e.g. the switching direction in case of commands or the new status in case of a process value change.

# 4.5 Anwendungsbeispiele für die Funktionen

## 4.5.1 Script for Event OnProcDataChange

This script sets the **QuitBlinking** variable at event **OnProcDataChange** of the SICAM Switch Control in the same way as the Switch Control object for SICAM SCC V7 or earlier versions:

- Checking the switch for spontaneous flashing
- Setting iSwitchState for the call to gcs_IsSpontaneousFlashing
- The return value in iSwitchState is a Boolean value (Yes/No)
- bReturn is only required for VBS, does not include information

Sub OnProcDataChange(ByVal Item, ByVal opdcEvent, ByVal Value)

' ----- event identifier of SICAMSwitch on process data changes ------

```
' OnProcDataChange Event On Process Data Change
```

Const	con opdc Select	= 16
Const	con opdc SelectConfPos	= 17
Const	con opdc SelectConfNeg	= 18
Const	con_opdc_Command	= 19
Const	con_opdc_CommandConfPos	= 20
Const	con_opdc_CommandConfNeg	= 21
Const	con_opdc_Abort	= 25
Const	con opdc AbortConfPos	= 26
Const	con_opdc_AbortConfNeg	= 27
Const	con_opdc_CommandTermPos	= 35
Const	con_opdc_CommandTermNeg	= 36
Const	con_opdc_AbortTermPos	= 37
Const	con_opdc_AbortTermNeg	= 38
Const	con_opdc_SelectTermPos	= 39
Const	con_opdc_SelectTermNeg	= 40
Const	con_opdc_newValue	= 100
Const	con_opdc_TimeOutSelect	= 101
Const	con_opdc_TimeOutSelected	= 102
Const	con_opdc_TimeOutExecute	= 103

#### ' ------ call parameter identifier for reading switch state -------

#### ' GetControlState GCS

Const	con_gcs_Version	= 01
Const	con_gcs_Value	= 02
Const	con_gcs_Cause	= 03
Const	con_gcs_AddCause	= 04
Const	con_gcs_QualityCode	= 05
Const	con_gcs_VarType	= 06
Const	con_gcs_IsDataValid	= 07
Const	con_gcs_IsHeld	= 08
Const	con_gcs_IsOverflowed	= 09
Const	con_gcs_IsBayBlocked	= 10
Const	con_gcs_IsBayBlocked	= 11
Const	con_gcs_IsSubstituted	= 12
Const	con_gcs_IsDataServerNotOK	= 13
Const	con_gcs_IsNoVar	= 14
Const	con_gcs_IsDemoMode	= 15
Const	con_gcs_IsDemoModeExpired	= 16
Const	con_gcs_IsNotTopical	= 17
Const	con_gcs_IsSubstitutionEnabled	= 18

[sc_func_ex_1p1, 1, --_--]

```
Const
             con gcs IsSpontaneousFlashing
                                               = 19
             con gcs IsSwitchEnabled
                                               = 20
Const
Const
            con gcs GetControlCommand
                                               = 21
Const
                                               = 19
            con gcs IsSpontaneousFlashing
            con_gcs_IsSwitchEnabled
Const
                                               = 20
             con gcs GetControlCommand
                                              = 21
Const
            con_gcs_GetCommandValue
Const
                                               = 22
Const
            con gcs GetCommandCause
                                               = 23
            con_gcs_GetCommandAddCause
Const
                                               = 24
             con_gcs_CmdIsDataValid
Const
                                               = 25
Const
             con gcs GetCommandValueType
                                               = 26
             con gcs SetCommandValueType
                                              = 27
Const
Const
             con gcs get LimitStates
                                               = 28
' gcs get LimitStates returns:
 - Bit 0: Command Timer Timeout
' - Bit 1: Set point Flashing
' - Bit 2: Spontaneous Flashing
'Variable declaration
Dim iSwitchState
Dim bReturn
'Script code
HMIRuntime.Trace "OnProcDatachange - Event: " & opdcEvent & vbNewline
If con_opdc_newValue = opdcEvent Then
    iSwitchState = con_gcs_IsSpontaneousFlashing
       bReturn = Item.GetControlState(iSwitchState)
       HMIRuntime.Trace "GetControlState(con_gcs_IsSpontaneousFlashing) = "
                        & iSwitchState & vbNewline
       If 1 = iSwitchState Then
             HMIRuntime.Tags("QuitBlinking").Write 1
       End If
End If
HMIRuntime.Trace "PictureName: " & HMIRuntime.ActiveScreen.ObjectName & vbNewline
HMIRuntime.Tags("LastAlarmPicName").Write HMIRuntime.ActiveScreen.ObjectName
```

#### End Sub

[sc_func_ex_1p2, 1, --_--]

# 4.6 SICAM Electrical Device Control

The following SICAM Electrical Device Control types are available: Feeder, Ground, Transformer (additionally: Auto transformer 1-phase and Auto transformer 3-phase) and Termination. These control types are included in the **Topology** folder of the SICAM graphic object library. See *5.2 Topological Elements*.
# 4.7 SICAM Bay Overview

The **Overview** folder in the SICAM graphic object library includes the SICAM Bay Overview user object. It is implemented as an ActiveX Control and already contains typical functions.

You can use a bay overview to show the status of an entire bay by means of a single graphic object.

# Graphical representation

4 bay overview variants are available in the SICAM graphic object library:

Bay overview	View	Graphic
LSA rounded	LSA representation with circular symbol	$\bigcirc$
LSA boxed	LSA representation with rectangular symbol	
SICAM rounded	SICAM representation with circular symbol	
SICAM boxed	SICAM representation with rectangular symbol	

T     4 4 0	~ · · ·		C . I	
Table 4-12	Graphical	representation	of the	bay overview

## Maximum bay extension

A bay overview diagram can show one single bay with the following maximum extension:



[sc_topo max bay overview, 1, en_US]

Figure 4-31 Maximum bay extension shown in a bay overview

The SICAM bay overview is processed with only 1 busbar by the topology component.



# NOTE

If switches configured in the bay overview are configured as single switches in another picture, you have to take care of the orientation of the connection points.

If multiple busbars should be considered, there are 2 ways for the configuration:

• The busbar disconnectors are configured outside of the project: The bay overview then is electrically connected between the busbar disconnectors and the circuit breakers.



[sc_topo busbar ext, 1, en_US]

Figure 4-32 Bay overview with busbar disconnector outside of object

• The busbar disconnectors are configured inside of the project: The connector to the busbar above is not considered by the topological coloring. You can color this connector at will.



```
[sc_topo busbar int, 1, en_US]
```

Figure 4-33 Bay overview with busbar disconnector within object

The picture displayed in the bay overview must be configured in another (detail) picture to ensure that a consistent topological model can be generated.

# 4.7.1 Representation Style of Bay Overview

Each bay overview must be assigned several properties.

♦ Double-click the graphic object.

The SICAM Bay-Overview Control Properties dialog opens.

The properties are listed in the Style tab.

## Туре

The following 5 options are available for the representation of the graphic object:

- SICAM boxed
- SICAM rounded
- LSA boxed
- LSA rounded
- Picture

With the **Picture** style, individual pictures can be displayed depending on the switch position. The individual pictures must be assigned switch positions in the **Picture** tab, see 4.7.4 *Picture of Bay Overview*.

## Grounded only with CB closed

With this option you define whether the grounding shall only be represented with the circuit breaker closed.

• The **Grounded only with CB closed** option is activated:

The bay overview is only shown as grounded if the grounding disconnector and the circuit breaker are closed.

• The **Grounded only with CB closed** option is not activated: The bay overview is shown as grounded if the grounding disconnector is closed.



[sc_grounding_without_cb, 1, --_--]

Figure 4-34 Grounding without circuit breaker

## 3-D style

If this checkbox is activated, the bay overview is represented with a three-dimensional effect as soon as the user clicks with the mouse.

## Line width

The line width of the graphic objects (LSA only) can be selected. Step 1 represents the smallest line width.

## **Tooltip text**

Enter a text in the entry field. This text is displayed as a **Tooltip** in the active project.

# 4.7.2 Tag Connection to Bay Overview

The bay overview must be assigned tags.

- ♦ Double-click the graphic object.
   The SICAM Bay Overview Control Properties dialog opens.
- ♦ Open the Tag connection tab.

SICAM E	Bay-Overview Cor	ntrol Pro	operties				×
Style	Tag connection	Color	Picture				
Tag n	ame busbar discon	nector 1	(*.RTInfo	o):			
Bust	Bas_Disconnector 1						
Tag n	name busbar discon	nector2	(*.RTInfo	o):			 
Bust	Bas_Disconnector2						
Tag n	name busbar discon	nector3	(*.RTInfo	o):			
Bust	Bas_Disconnector3						
Tag n	ame circuit breaker	· (*.RTIr	nfo):				
Circ	uitBreaker						
Tag n	ame line disconnec	tor (*.R	TInfo):				
Line	_Disconnector						
Tag n	name ground discon	nector (	*.RTInfo)	):			
Eart	h_Disconnector						
			(	ОК	Car	ncel	Apply

[scc324, 1, en_US]

Figure 4-35 Defining the bay overview

## Tag assignment

Proceed as follows to assign the graphic object a tag:

- Click the ... button next to the entry field.
   The Tags dialog opens.
- Select the corresponding tag from the list and click **OK** to confirm.



# NOTE

Delete the default tag link for switching devices which do not exist in the bay.

- Double-click the tag to be deleted. The tag is selected.
- Delete the selected tag.

This ensures that the elements in question are no longer considered for the determination of the bay state, i.e. the value and the status of the **bay overview** are independent of the deleted elements. However, at least the circuit breaker must be configured for the bay overview.

# 4.7.3 Colors of Bay Overview

## Value

In normal state, the color and the form of the graphic object depend on its value. A specific color is defined by default for each individual state. It is also possible to select the color from a color palette. In the **SICAM** representation style, only the color and not the form is changed depending on the corresponding value.

Table 4-13	Colors define	ed according	to SICAM
		J	

Value	Color	Meaning
ON	Red	The circuit breaker, the line disconnector and at least one busbar disconnector are switched on.
OFF	Green	The circuit breaker, the line disconnector or all busbar disconnectors are switched off.
Disturbed	Yellow	At least one of the connected devices in the bay is faulted.
Grounded	Pink	The bay is grounded.

#### Table 4-14 Colors defined according to LSA

Value	Form	Meaning
ON	Filled	The circuit breaker, the line disconnector and at least one busbar disconnector are switched on.
OFF	Not filled	The circuit breaker, the line disconnector or all busbar disconnectors are switched off.
Disturbed	Half filled	At least one of the connected devices in the bay is faulted.
Grounded	Filled/ not filled	The bay is grounded.
Geerdet		

### Background

The default background color is gray. It can also be freely selected.

### Status

The switch state is indicated by small, colored rectangles next to the graphic object. A specific color is set by default for each individual state. The color can also be freely selected from a color palette. The following colors of the rectangles are set by default for the representation of the individual states:

Status	Color	Explanation
System not ok	Dark cyan (teal)	Connection between SICAM SCC and the automa- tion system/ device.
Bay blocked	Red	Messages from this bay are no longer transmitted to the automation system/device.
Not topical	Cyan (turquoise)	The device state is not topical.
Substituted	Blue	The switch position was set manually because there is no connection to the primary system.
Telecontrol blocked	Red	Messages from this bay are no longer transmitted to the telecontrol center.

### Priority of the object colors

The bay overview states are represented as a sum of all the switching devices in the bay from high priority to low priority:

Fault position - Grounded - On - Off

The representation of the bay overview states is implemented as the sum of all the switching devices in the bay and shows the states of the individual switches according to their priority. If, for example, a switch is in fault position, the bay overview object is shown in fault position. This means that other switch positions are no longer relevant. If the grounding disconnectors and outgoing feeder disconnectors are switched on in such a case, the bay overview object is represented as grounded.

# 4.7.4 Picture of Bay Overview

You can assign the values of Bay Overview individual pictures. To ensure that these pictures are shown during runtime, the **Picture** checkbox must be activated under **Type** in the **Style** tab, see 4.7.1 *Representation Style of Bay Overview*.

The following picture formats are possible:

- BMP
- EMF
- JPG
- GIF

## Properties

The values of Bay Overview are listed under **Properties**. Assign each value a picture.

Highlight a value and click the **Browse** button to assign the value a picture. Pictures are stored in the **\GraCS \SicamIXPics** directory in the WinCC project. You can assign these pictures or individual pictures.

#### Preview

The assigned picture is shown in a preview.

# 4.8 Measured/Metered Value Display

The **Measured/Metered values** folder in the SICAM graphic object library includes the **Numeric display** object. Typical functions are already provided in this ActiveX Control. With this graphic object you can:

- display measured and metered values
- substitute measured and metered values
- issue setpoint commands for measured and metered values
- define upper and lower limits

Figures consisting of up to 7 digits can be displayed with the measured value object. The WinCC data type used does not allow any further digits.

# 4.8.1 Style of the Numeric Display

A SICAM Numeric Control consists of a value field and a unit field.

0.00000e+000	kWh -
0,0000000.000	
· · · · · · · · · · · · · · · · · · ·	

[sc_numeric_control_1, 1, --_--]

You can adjust its appearance as follows.

♦ Double-click the graphic object.

The SICAM Numeric Control Properties dialog opens.

 $\diamond \quad \text{Select the } \textbf{Style tab}.$ 

SICAM Numeric Control Properties		×
Style       Tag connection       Advanced         Display       Digits behind comma:       2         Divider:       1.000000       0         Unit:       kWh#20       0	Limits       Color       Font         Touch operation       3-D Style on click         Fix dialog position       Y in pixels:       X in pixels:         100       100	
C	OK Cancel Apply	

[[]SICAM_Numeric_05, 2, en_US] Figure 4-36 Specifying the style

4.8 Measured/Metered Value Display

## Digits behind comma

Enter the desired number of decimal places.

## Divider

The value of the SICAM Numeric Control is divided by this number before being displayed.

## Unit

Enter the text to be displayed in the unit field.

Additionally, you can determine the ratio of the size between the value field and the unit field – or if the unit field is displayed at all.

• If you want to display a unit in default size, just enter it, for example "kWh". Without further information, the default size (width) of the unit field represents 30 % of the width of the complete control.



• If you want to change the size of the unit field, enter the corresponding percentage value, separated by "#", next to the text of the unit.

In order to set the size to, for example, 20 % of the complete control, enter "kWh#20".



• If you want to display an empty unit filed with, for example, 15 % size, enter "#15".



• If you leave the text for the unit empty, the unit field is hidden.





## NOTE

The unit field is limited to 10 characters.

## **Touch operation**

If this option is activated, the runtime dialogs are displayed with optimized settings for touch operation (e.g. bigger buttons, different style).

## 3-D style on click

If this option is activated, the value output triggered by a mouse click is represented with a three-dimensional effect.

Fix dialog position

You can place the dialogs in a fixed position on the screen.

# 4.8.2 Tag Connection of the Numeric Display

Each value output must be assigned to a tag.

- ♦ Double-click the graphic object.
   The SICAM Numeric Control Properties dialog opens.
- ♦ Select the Tag connection tab.

SICAM Numeric Cont	rol Properties	×
Style Tag connection	Advanced Limits Color Font	
Protocol type:	SICAM PAS Protocol Suite $\sim$	
Tag name information	n (*.RTInfo)	
Tag name command (	*.RTCmd)	
Value type:	Set point bit string 32 bit $\qquad \lor$	
Tooltip text:		
SICAM Numeric Con	trol	
	OK Cancel Apply	

[SICAM_Numeric_01, 2, en_US] Figure 4-37 Tag connection

## Protocol type

Select the desired protocol type from the drop-down list box. The following protocol types are available for selection:

- SICAM PAS Protocol Suite for connection to SICAM PAS-Stationen
- SICAM IEC Communication Suite for connection to SICAM RTUs or IEC 61850/IEC 60870-5-104 devices

## Information tag

Click the button to the right of the entry field. The **Tags** dialog opens. Select the corresponding tag from the list and click **OK** to confirm.

## Tag name command

If a related command tag is indicated for an information tag in the SICAM PAS import data record, the command tag is determined automatically when selecting the information tag and entered in the **Tag name command** entry field. In order to select a tag yourself, proceed as described under **Tag name information**.

# Value type

This setpoint type is used for the command tag in order to describe the data type of the command.

## **Tooltip text**

Enter a text in the entry field. This text is shown as a **Tooltip** in the active project.

# 4.8.3 Advanced Properties of the Numeric Display

In the Advanced tab you can assign further value output properties.

- ♦ Double-click the graphic object.
   The SICAM Numeric Control Properties dialog opens.
- ♦ Select the Advanced tab.

SICAM	SICAM Numeric Control Properties				
Style	Tag connection	Advanced Limits Color Font			
Visi	ble in RT not synchronized non-interlocked set	Enable 'Select before operate'			
	not synchronized	Command execution timeout in seconds:			
Oper <no< td=""><td>ator authorization: access protection</td><td>&gt;</td><td></td></no<>	ator authorization: access protection	>			
		OK Cancel Apply			

[SICAM_Numeric_02, 2, en_US]

Figure 4-38 Advanced properties

# Visible in RT

Under **Visible in RT**, activate the checkboxes for the options you want to show additionally during runtime in the switching dialog and which can be modified.

## Preset

Under **Preset**, activate all values to be transmitted as qualifiers of command (QoC). If the **Visible in RT** option is activated, you can define here the pre-assignment in the runtime dialogs. The checkboxes under **Visible in RT** and **Preset** can only be activated if the **SICAM IEC Communication Suite** protocol type has been selected.

Table 4-16	Configuration w	ith different	attributes
	configuration w	itii uniciciit	attributes

Protocol type	Activated fields	Attribute	Effect
SICAM IEC Communication Suite	Visible in RT	Unsynchronized	Shown in the switching dialog during runtime.
		Non-interlocked	Shown in the switching dialog during runtime.
	Preset	Unsynchronized	Pre-assignment of the value sent as QoC as part of the command (synchronized/ unsynchronized switching)
		Non-interlocked	Pre-assignment of the value sent as QoC as part of the command (synchronized/ unsynchronized switching)

#### Enable 'Select before operate'

A select command is issued before the actual command. The setpoint can only be issued after the select command has been answered with a positive acknowledgment.

#### Command execution timeout in seconds

Enter the **Command execution timeout in seconds**. This corresponds to the maximum timeout until the successful command execution. As soon as this timeout has elapsed, the command process is terminated and a negative command termination is logged.



# NOTE

For IEC connections, the **command execution timeout** only affects the switching object. The command itself only gets affected with SICAM PAS connections.

### **Operator authorization**

Select the desired **Operator authorization**. For more detailed information on the definition and granting of operator authorizations refer to 3.8 Setting up User Authorizations.

# 4.8.4 Limit Values of the Numeric Display

Enter limit values for the information and the setpoint in the Limits tab.

- ♦ Double-click the graphic object.
  - The SICAM Numeric Control Properties dialog opens.
- ♦ Select the Limits tab.

#### Graphic Objects

4.8 Measured/Metered Value Display

SICAM	Numeric Control	Properties				×
Style	Tag connection	Advanced	Limits	Color	Font	
Info	ormation					
	Lower limit font co	or:		Upper l	imit font color: 00000	
	Lower limit blinking	:		Upper l	imit blinking:	
	10.000000			120.00	00000	
Set	point					
	Lower limit:			Upper l	imit:	
	0.000000			120.00	00000	
		[	OK		Cancel	Apply

[SICAM_Numeric_03, 2, en_US]

Figure 4-39 Defining limit values

### Information

You can define 2 upper and lower limits for the value. The font color changes if the value is above or below the 1st upper/lower limit. The display starts flashing if the value is above or below the 2nd upper/lower limit.

#### Set point

You can define a setpoint with upper and lower limits for the value. The display starts flashing if the value is above/below the upper/lower limit of the setpoint.

# 4.8.5 Color of the Numeric Display

#### Value

In the **Color** tab you can assign further colors for the value ranges and states.

- ♦ Double-click the graphic object.
  - The SICAM Numeric Control Properties dialog opens.
- ♦ Select the Color tab.

SICAM Numeric Control Properties		$\times$			
Style Tag connection Advanced	Limits Color Font				
Value	State				
Normal state	No connection				
Overflow	Bay blocked				
Upper limit	Not topical				
Lower limit	Substituted				
Background	Telecontrol blocked				
	Unit				
	Font color				
Background					
	OK Cancel Apply				

```
[SICAM_Numeric_04, 2, en_US]
Figure 4-40 Assigning colors
```

The following colors are predefined for the graphic object:

Table 4-17	Value
------------	-------

Value	Color	Meaning
Normal state	Black	The value is in the normal range.
Overflow	Magenta	The value is above/below the setpoint range.
Upper limit	Black	The value has exceeded the upper limit defined.
Lower limit	Black	The value is below the lower limit defined.

## Background

You can individually define the background color of the graphic object. White is the default color.

## State of the value

The state of the measured value object is represented with small, colored rectangle icons on the measured value object. A color is defined by default for each state, but the color can also be freely defined from a color palette. The size of the colored rectangles is automatically adapted to the measured value object.



#### [le_status, 1, --_--] Figure 4-41

Measured value object with state

The default colors of the rectangles depend on the individual state:

	State	Color	Meaning
1	No connection	Dark cyan (teal)	No connection between SICAM SCC and the auto- mation system/device.
2	Bay blocked	Red	Messages in this field are no longer transmitted to the automation system/device.
3	Not topical	Cyan (turquoise)	The device state is not topical.
4	Substituted	Blue	The value was set manually because no connection was available, e.g. to a protection device.
5	Telecontrol blocked	Red	Messages in this field are no longer transmitted to the telecontrol center.

## Table 4-18 Value state

## Unit

The unit color can be defined individually. Black is the default font color, and white is the default background color.

# 4.8.6 Font of the Numeric Display

Define the font in the **Font** tab.

- ♦ Double-click the graphic object.
- The SICAM Numeric Control Properties dialog opens.
- ♦ Select the **Font** tab.

SICAM	Numeric Control	Properties	Х
Style	Tag connection	Advanced Limits Color Font	
Prope Font	rties:	Font:     Size:       Arial     11.25 ~       Effects     Bold       Italic     Strikeout	
		Sample Text: Arial	
		OK Cancel App	у

[SICAM_Numeric_06, 2, en_US] Figure 4-42 Defining the font

# Font

Select the desired font from the drop-down list box.

## Size

Select the desired font size from the drop-down list box.

## Effects

You can select the Bold, Italic, Underline and Strikeout boxes.

# 4.8.7 Runtime Dialogs of the Numeric Display

## Issuing the setpoint

Dialogs are available in order to transmit the setpoint to the process. To call up these dialogs during runtime, click the related graphic object.

float	
	*
	-
Operating	
Set point	
1,760000	
Apply	
Cancel	

[SCC_RT_420, 1, en_US]

Figure 4-43 Applying the setpoint value

- Enter the setpoint value in the entry field.
   You can enter a dot or a comma as a decimal separator.
- Click Apply.
   The Apply dialog opens.

4.8 Measured/Metered Value Display

Apply	1
	*
	*
1.760000	
Confirm	
Cancel	

[SCC_RT_421, 1, en_US]

Figure 4-44 Issuing the setpoint

♦ Click **Confirm** in order to send the setpoint command to the destination system.

## Status

The status dialog can be opened by clicking with the right mouse button, provided that the status display has been activated in the Properties dialog.

An information-specific block can be defined for the information of the SICAM PAS target system in combination with SICAM PAS/PQS V8.01 or later. This means that the process value update can be blocked for individual information objects.

You can set/undo the bay blocking/telecontrol blocking in the status dialog of the Numeric Display. To do this, activate the corresponding function.

SICAM Numeric Control			
	1		
	-		
No connection			
☐ Not topical			
Bay blocked			
Telecontrol blocked			
☐ Substituted			
Substitute			
Close			

[SCC_RT_422, 1, en_US] Figure 4-45 Status dialog

The current status is also indicated by a tick in the corresponding checkbox in the status dialog; the Numeric Display is marked with a colored rectangle, see status information in *Figure 4-41*.

If **Bay blocked** is activated, the value of the Numeric Display can be substituted by clicking the **Substitute** button.

## Substituting the value



# NOTE

This function is only available with connection to SICAM PAS.

In this dialog you can define the desired substitute value (setpoint) for the corresponding value. Click **Substitute** in order to open the Apply dialog. The substitution is carried out after clicking **Confirm**.

# 4.8.8 Representing Measured Values for the Invalid State

For the **SICAM Measured value display** object you can define the information to be displayed for the Invalid state. Depending on the individual configuration the last valid value or a question mark is displayed. Perform the configuration via the **StateColorVisibleFlag** attribute in the **Object properties** dialog. To configure the display for the **Invalid** state:

- ♦ Right-click SICAM Measured value display and select Properties from the context menu.
- ♦ Select SICAMNumericCtrl > Control properties in the Properties tab.

Object Properties	Oł	oje	ct P	rop	ber	ties	5
-------------------	----	-----	------	-----	-----	------	---

SICAMNumerio	Cti Attribute	Static	Dynam
Geometry	PASNotOKColor		Q I
Miscellaneo	us BayBlockedColor		0
Control Pro	per SubstitutedColor		ý
	TeleBlockedColor		Q
	StateColorVisibleFlag	11528	Q
	CommandTimeout	5	Q
	LimitSetPointMax	120.00000	Q
	A last sector a state	0.000000 000	<u> </u>

[state_unvalid, 1, en_US]

Figure 4-46 Defining the StateColorVisibleFlag attribute



# NOTE

The information shown for an invalid value is defined via Bit 0x10000 in the **StateColorVisibleFlag** attribute.

- Enter the desired value for the StateColorVisibleFlag attribute:
  - To show the last valid value, enter 11528.
  - To show a question mark, enter 77064 (11528 + 0x10000).

# 4.8.9 Support of Controllable Analogue Process Value (CDC = APC)

The SICAM SCC IEC channel supports the IEC 61850 Common Data Class (IEC) **APC** (Controllable Analogue Process Value) in receive direction and command direction. The currently set analog set point (attribute name **mxVal.f**) of an APC data object is received via reporting and displayed in Tag Management and Alarm Logging. The analog set point (attribute name **ctlVal.f**) can be sent to the remote location via **SICAM Numeric Control** in the following types of sequence of commands:

- ctlModel=1 (direct control with normal security)
- ctlModel=3 (direct control with enhanced security)
- ctlModel=4 (sbo control with enhanced security)

The locking conditions (synchocheck/interlocking) specified via the **SICAM Numeric Control** are encoded and transmitted accordingly in the sequence-of-commands telegram. For **SBO** (select before operate), the command can be canceled after **Select** with **Cancel**. The transmission causes **Activation** (COT=6), **Confirmation** (COT=7), and **Termination** (COT=10) are set on the command tag depending on the state of the command flow.

# 5 Topological Coloring

5.1	Introduction	166
5.2	Topological Elements	168
5.3	Parameterization	181
5.4	Cross-Picture References	190
5.5	Using Topological Coloring	192
5.6	Using Picture Windows	197
5.7	Debugging	199
5.8	Application Examples	201

# 5.1 Introduction

The term topology describes the structure of a network, which results from the switching and operating states of the equipment (switchgear, transformers, etc.). A network has a limited, but very large number of possible connections, i.e. a so-called potential topology. However, the major part consists of switchable connections in the bays of the switchgear. The connections switched on at a certain time determine the current topology of the network.

The operational network conditions are represented in network diagrams.

Based on the object parameterization, the compiler creates the topology model using the SICAM add-in **Create Topological Structure**.



# NOTE

The new topological coloring (SICAM SCC V9.0 or later) is not supported for SICAM SAS components.



# NOTE

You require a separate license for topological coloring.



# NOTE

The configuration of the topological coloring only works for pictures in the root directory of the Graphics Designer: **<project directory>\GraCS**.

Images from subdirectories are excluded.

## Overview

Using **topological coloring**, the states of a power network can be represented by means of different colors in SICAM SCC. All adjacent graphic objects of a feeder are assigned the same color. The uniform color assignment is interrupted if a control element is open.

In terms of topological coloring, a **power system** consists of lines (connectors), transformers, switches and further objects. To be able to forward information, the graphic objects must be interconnected via their connecting points. Each connecting point consists of 1 input and 1 output.





Incoming information is forwarded through the entire network and issued on the connecting points connected. This mechanism works in any direction.

The following graphic objects support topological coloring:

- Circuit breaker, disconnector, load break switch, earth isolator
- Bay overview
- Feeder, ground, transformers, termination
- Connectors and connection point Connectors in the SICAM graphic object library support the same functions as connectors in the SIMATIC WinCC object palette.

The graphic objects Feeder, Ground Disconnector, Connector and Node are available in the **Topology** folder of the SICAM graphic object library.

### **Dynamic Network Coloring**

The Dynamic network coloring function enable you to represent the electrical connection between various network sections using specific colors. On the SICAM SCC operator console, you can thus obtain a quick overview of the switching status of the station.

The Dynamic network coloring function detects the **Secure supply** status as well as the **Connection of several feeders**. These operating states can be highlighted specifically via the line width used to represent the tie lines, or also via dashed lines.

The switching status can be represented by means of specific colors in all graphical network diagrams, including substation diagrams and the worldmap. The interlinkage with the dynamic network coloring algorithms is performed via the process references (variables) of the equipment represented in the pictures, such as disconnectors, circuit breakers, transformers.

#### Restrictions

The restrictions concerning topological coloring specified in SICAM SCC V9.06 must be observed:

- The topological coloring does not support umlauts for tag names.
- Multi-clients with pictures including active objects from several servers are not supported.
- Mixed configurations of pictures are not possible.
- Topological coloring across several WinCC servers is not possible.
- Indirect addressing for active objects cannot be used.
- If you deactivate a picture and a different option was selected for Coloring of switch controls, you have to select the option Use topological color in the Topological settings for selected objects under Coloring of switch controls; thus, all elements are displayed with default color again. See also 5.3.3 Settings.

# 5.2 Topological Elements

# 5.2.1 General

The following objects are available in SICAM SCC:

- SICAM Topology (SICAM Electrical Device Control)
  - Feeder
  - Ground
  - Transformer
  - Auto transformer 1-phase and 3-phase
  - Termination
- SICAM Switch Control
  - Circuit breaker
  - Disconnector
  - Load breaking switch
  - Earth isolator
- SICAM Bay Overview
- Connector
- Connection point

The following paragraphs describe the individual types with their specific parameterization options.

Library			
📸   X 🖻 🛍 🗙 ! 🖳 🗁 🏥 🛲   🚱			
🤤 Global Library	Name	Size	Last Change
🖶 🚈 Displays	Busbar with 3 nodes	1670	27.01.17 16:27
😥 📄 Operation	Busbar with 6 nodes	3500	27.01.17 16:27
PlantElements	Connector	547	27.01.17 16:28
🕀 😁 Siemens HMI Symbol Library 1.4.1	Note: The second	2636	27.01.17 16:25
Eroject Library	Seeder with measurement	2634	27.01.17 16:25
Graphic objects for SICAM SAS>	Seeder with process tag	2582	27.01.17 16:25
Graphic objects of previous versions>	Field with bay overview	3391	27.01.17 16:26
Alarm Logging templates	Field with BBDC, CB	10839	27.01.17 16:26
	Field with BBDC, CB, LNDC	13732	27.01.17 16:26
🕀 📄 Control elements	Field with BBDC1, BBDC2, CB, EDC,	18805	27.01.17 16:26
🗄 💼 Measured/Metered values	Ground left with EDC	4538	27.01.17 16:25
Switching device objects	Ground right with EDC	4542	27.01.17 16:25
	List tag prefixes	735	27.01.17 16:27
	Node circle	441	27.01.17 16:26
	Node rectangle	439	27.01.17 16:27
	Termination	2367	27.01.17 16:27
	Transformer	2604	27.01.17 16:27
	Transformer auto 1phase	2644	27.01.17 16:28
	Transformer auto 3phase	2644	27.01.17 16:28
< >			
📳 Object Properties 🕒 Library 🤻 Dynamic W	/izard		

[sc_library_topology, 1, en_US] Figure 5-2 SICAM SCC Library

# 5.2.2 SICAM Electrical Device Control

## 5.2.2.1 Description of Functions

The following **SICAM Electrical Device Control** types are available: Feeder, Ground, Transformer (additionally: Auto transformer 1-phase and Auto transformer 3-phase) and Termination. These are described below.

## Feeder

The Feeder object represents the start of a topological network.

The feeder is an active component which initiates the coloring in the WinCC picture. It transfers its value to the graphic objects connected to it.

Each power network in which topological coloring is to be realized must have a feeder. Preferably use just 1 feeder, e.g. for a busbar. If several feeders are available on a busbar, you must define the preferred feeder. A topological status (i.e. supply type with color) must be defined for each feeder (see *5.3.3 Settings*).

A feeder has different statuses. The representation style is determined by the switching status of the process tag linked, as well as by its status:

- Feeder switched on Color defined on the feeder as the Supply type color for the Topological color (see *Color, Page 173*)
- Feeder switched off
   Color for de-energized. This color is defined for the entire project (see *Topological Project Settings*, *Page 186*).

- Status of the DIST feeder Color for **Undefined**. This color is defined for the entire project (see *Topological Project Settings*, *Page 186*).
- Status of the DIFF feeder Color for **Undefined**
- Disturbed status Color for **Undefined**
- Initial status Color for **Initial**. This color is defined for the entire project (see *Topological Project Settings, Page 186*).

# Ground

**Ground** is a special type of feeder. It always transfers the color for grounding to the graphic objects connected to it.

Ground elements serve for the grounding of station sections which have been switched off. Since the element is fixedly connected to ground potential on one side, it is considered as a 1-pole within the scope of topology calculation.

If the element is in the **ON** status, i.e. the breaker is closed, the connected network section is represented in the color defined for **grounded**.

# Transformer

The transformer performs an electrical isolation.

A transformer can operate in the same way as the **Feeder** element.

If the transformer is supplied from one side, the other side becomes a feeder, provided that a topological status has been assigned from the project settings.

If reverse energization is possible, an individual supply type must be defined for each side (usually a nonsecure supply type is used). If reverse energization is not possible, do not assign a color to the corresponding side.



# NOTE

A structure tag must be created and assigned for the transformer (5.2.2.5 Creating Structure Tags).

In addition to the ordinary transformer, the Auto transformer 1-phase and Auto transformer 3-phase types are available.

The Grounded status cannot be spread beyond a transformer.

## Termination

This element is only used if a single feeder must be logically connected, e.g. if a branch to a consumer has to be represented. This is e.g. **not** the case for sections from an overview picture.

# 5.2.2.2 Graphical representation

The following SICAM Electrical Device Controls are available in the **Topology** folder in the SICAM graphic object library:

Table 5-1	Graphical representation style of the SICAM Electrical Device Controls
-----------	------------------------------------------------------------------------

Graphic object	Туре	Graphic
Feeder	1-pole	$\bigcirc$
Ground	1-pole	-

Graphic object	Туре	Graphic
Transformer	2-pole	(0)
Auto transformer 1-phase	2-pole	0
Auto transformer 3-phase	2-pole	$\mathbb{Q}$
Termination	1-pole	

# 5.2.2.3 Properties of SICAM Electrical Device Controls

Each SICAM Electrical Device Control must be assigned a certain number of properties.

♦ Double-click the graphic object.
 The SICAM Electrical Device Control Properties dialog opens.

## Style

SICA	M E	lectrical Device C	ontrol P	ropertie	5	$\times$
Sty	le	Tag connection	Color	Picture		
Г	Disp	lay			Measurement	
	Typ Fe	ee: eder		~	Level ON/OFF 10.00000	
	Dire 0°	ection:		~	Hysteresis 2.000000	
	Line 2	e width:			Pictures	
				(	DK Cancel <u>Apply</u>	

[sc_edc_style, 1, en_US]

Figure 5-3 Properties of SICAM Electrical Device Controls, Style

## Туре

The following types are available:

- Feeder
- Ground
- Transformer
- Auto transformer, 1-phase
- Auto transformer, 3-phase
- Termination

Each type has a pre-defined style (5.2.2.2 *Graphical representation*). You can adapt the style to your needs and requirements.

## Orientation

For all representation styles apart from pictures, the orientation angles 0°, 90°, 180°, and 270° can be defined.

## Line width

You can define a line width for graphic objects; line width 1 is the smallest line width.

## Measured value

In these input boxes you can define values for Level ON/OFF and Hysteresis.

To do this, the **Measurement** tag type must have been selected in the **Tag connection** tab (see **Tag Connection**, **Page 172**).

### Pictures

If you activate the **Pictures** checkbox, the image files selected in the **Picture** tab are used for displaying the status of the object.

## **Tag Connection**

SICAM Electrical Device Control Properties	×
Style Tag connection Color Picture	
Tag type Internal information	
Tag name information (*.RTInfo)	
Tag name topological information (*.RTInfo)	
Tooltip text:	
SICAM Electrical Device	
OK Cancel	<u>A</u> pply

[sc_edc_process, 1, en_US]

Figure 5-4 Properties of SICAM Electrical Device Controls, Tag connection tab

## Tag Type

The following types are available:

### • Internal information

Used, for example, in order to integrate statuses determined from a script (on the **Tag name topological information** output). See also 5.2.2.5 Creating Structure Tags.

## • Process information

A single- or double-point indication is connected here which directly includes the **ON**, **OFF**, and **Disturbed** states and forwards these states.

## Measured value

Used for connecting a measured value as an input value which controls the output via the configuration of the ON/OFF level and the hysteresis (connection: **Tag name topological information**).

The tag type is not available for **Ground** and **Termination**. See also 5.2.2.4 Tag Connection of the Feeder.

### Tag name information (*.RTInfo)

Here you can assign the tag types **Process information** and **Measured value** a process tag with the file extension **RTInfo**.

## Tag name topological information (*.RTInfo)

Here you assign the tag types **Internal information** and **Measured value** an internal tag with the file extension **RTInfo**.

## **Tooltip text**

Enter a text in this entry field. This text is displayed as a **Tooltip** for the object in the active project.

#### Color

SI	CAM E	lectrical Device C	ontrol P	ropertie	5	Х
	Style	Tag connection	Color	Picture		
	Cor	ntrol style			Topological style	
	For	eground			Supply type	
					Green (fail-safe) - 400V 🗸 🗸	
	Bac	kground			Secondary/output side	
				(	OK Cancel Apply	

[sc_edc_color, 1, en_US]

Figure 5-5 Properties of SICAM Electrical Device Controls, Color

### Foreground

The foreground color of the graphic object can be individually set. Red is the default setting.

### Background

The background color of the graphic object can be individually defined. Gray is the default setting.

# **Topological style**

Here you select the colors for the topological representation style of the object.

- For the **Feeder** you define the **Supply type** color.
- For the **Transformers** you define the colors for the **Primary side (reverse energization)** and the **Secondary/output side**.

Define the colors and their priority via the **Settings for the project** dialog (see *Topological Project Settings, Page 186*)

## Picture

SICAM Electrical Dev	vice Control Properties	×
Style Tag conne	ction Color Picture	
Properties: INVALIDPicture OFFPicture ONPicture	Preview:	
	Browse OK	Clear Cancel <u>A</u> pply

[sc_edc_picture, 1, en_US]

Figure 5-6 Properties of SICAM Electrical Device Controls, Picture

## **Assigning Pictures**

Select a value under Properties and click Browse to assign an image file.

INVALIDPicture

Picture for representing the INVALID status.

- **OFFPicture** Picture for representing the OFF status.
- ONPicture

Picture for representing the ON status.

### Preview

The assigned picture is shown in a preview.



# NOTE

For the changes made to the SICAM Electrical Device Control properties to take effect (e.g. change of the supply type color), proceed as follows:

- Save the changed picture in the Graphics Designer,
- re-generate the entire topological structure for the project,
- start or stop and re-start the runtime.
   This has to be done using the WinCC Explorer. Activating the picture via the Graphics Designer only is not sufficient.

# 5.2.2.4 Tag Connection of the Feeder

The tag connection of the feeder must be defined depending on the supply type.

## Supply of Internal Information

If the feeder is supplied by an item of internal information, the internal tag must be created with the **PAS_InformationInternal** structure type (see 5.2.2.5 Creating Structure Tags) and is directly defined as topological information.

For controlling the topological coloring, the tag has the values OFF = 1 or ON = 2.

Tag type		
Internal information	ı <b>•</b>	
Tag name informatio	on (*.RTInfo)	
Tag name topologica	al information (*.RTInfo)	
Tooltip text:		
Tooltip text: SICAM Electrical De	evice	

[sc_edc_process, 1, en_US]

Figure 5-7 Supply of Internal Information

### Supply of a (Process) Measurement

If the feeder is supplied by a (process) measurement, an internal tag must be additionally created as a **PAS_InformationInternal** structure type (see 5.2.2.5 Creating Structure Tags) and assigned. For controlling the topological coloring, the tag has the values **OFF = 1** or **ON = 2**. 5.2 Topological Elements

yle	Tag connection	Color	Picture			
Тар	g type					
Me	asured value		•			
Tag	g name information	(*.RTIr	ifo)			
Fe	eder_Tag.RTInfo				 	
Тар	g name topological	informat	ion (*.RT	Info)		
Fe	eder 1.RTInfo					
Too	oltip text:					
SI	CAM Electrical Dev	ice				

[sc_topo_feeder_measured_value, 1, en_US]

Figure 5-8 Supply of a (Process) Measurement

The switching point when the feeder switches from OFF to ON is defined in the Style tab.

ityle	Tag connection	Color	Picture	
Disp	blay			Measurement
Ту	pe:			Level ON/OFF
Fe	eder		•	10.000000
Dir	ection:			Hysteresis
0°			<b>_</b> ]	2.000000
Lin	e width:			
2				Pictures

[sc_topo_feeder_measured_value_level, 1, en_US]

Figure 5-9 Defining the Switching Point

In order to prevent continuous switching the color ON and OFF in the case of slightly fluctuations around the switching point, a **hysteresis** can be defined.



[[]dw_topo value hysteresis, 1, en_US] Figure 5-10 Hysteresis around the Switching Point



# NOTE

When controlling the feeder with a measured value, the feeding object must be active in the picture displayed at runtime in order to ensure that the changes are applied in the Runtime. The measured value is the input value which controls the topological tag with ON/OFF within the scope of configuration on the object (switching threshold and hysteresis).

The topological tag is not used if the object is not active. Alternatively,

- you can evaluate the measured value via a global script and define the tag.
- you can place the feeding object invisibly at any position in other pictures (no connection required).

# **Supply of Process Information**

If the feeder is supplied by an item of process information, the value of the information is directly used as an input for controlling the topological coloring with the value OFF = 1 or ON = 2. An additional topological control tag is not required for this configuration. 5.2 Topological Elements

le Tag connection Colo	r Picture	
Tag type		
Process information		
Tag name information (*.R	TInfo)	
<process_information>.R</process_information>	TInfo	[]
Tag name topological inform	nation (*.RTInfo)	
Tooltip text:		
STCAM Electrical Davies		
SICAM Electrical Device		

[sc_topo_feeder_processint	fo, 1, en_US]
Figure 5-11	Supply of Process Information

## 5.2.2.5 Creating Structure Tags

To be able to use **Internal Information** as **Tag type** for the Tag connection, you first have to create structure tags.



# NOTE

Do not use special characters and umlauts in tag names.

### **Changes in Tag Management**

Create new tags in Structure tags > PAS_InformationInternal, e.g. TopoTestLoad and TopoTest-Feeder.

	Staaro						l	
<u>File E</u> dit <u>V</u> iew <u>H</u> elp								
Tag Management	~		Structure tags [ PAS_Info	rmationInt Find	<del>،</del> م	][	🤪 Properties - Structure tag	
			Name	Data type	Leng 🔺	1	Selection	
🗄 🍄 Internal tags		1	TopoTestFeeder	PAS_InformationInternal	0	11	Object type	Structure
- I SICAM PAS Protocol Suite		2	TopoTestLoad	PAS_InformationInternal	0		Object name	TopoTes
PAS Data Server		3	*				General	
DAS		4					Name	TopoTes
		5					ID	2099
Structure tags		6					Data type	PAS_Info
PAS_Command		7					Length	0
PAS_CommandFloat							Format adaptation	
🗄 🏤 PAS_CommandSInt		0					AS Length	
PAS_Information		9					Address	
PAS InformationFloat		10				1	Assignment	
PAS InformationInternal		11					Communication driver	
		12					Channel unit	

[[]sc_tagmanagement, 1, en_US]

Figure 5-12 Tag management

# **Defining SICAM Electrical Device Controls**

- $\diamond \quad \text{Insert a SICAM Electrical Device Control.}$
- ♦ In the Style tab, select Feeder as Type.

- In the Tag connection tab, select Internal information as Tag type.
- Enter the name of the desired internal tag in the Tag name topological information column, here e.g.
   TopoTestFeeder.RTInfo.

	SICAM Electrical Device Control Properties
	Style Tag connection Color Picture
-	Tag type
)	Internal information
<b>-</b>	Tag name information (*.RTInfo)
:::	
	Tag name topological information (*.RTInfo)
	Feeder 1.RTInfo
· · · · · · ·	Tooltip text:
	SICAM Electrical Device
	OK Abbrechen Übernehmer

[sc_edc_topo, 1, en_US]

Figure 5-13 Defining SICAM Electrical Device Controls

# 5.2.3 SICAM Switch Controls

A closed control (switching device object) functions like a connector. An incoming value is transferred to the output of the other connecting point. An open control does not transfer the value.

If the switching object is in the OFF state, the color value defined for de-energized is issued.

The **ON** and **Grounded** colors are not prioritized by the controls, but processed with the same priority. If a control is in the **Intermediate position/Fault position**, the line color is transferred depending on the priority of the line color on one of the inputs: Only if the line color unequal **OFF** is pending on one of the inputs will the line color **Undefined** be transferred.

# NOTE

The element **Earth Isolator** is firmly connected to earth potential on one side, thus representing a 1-pole for topology calculation. The line must be connected to the left port (marked with a small square, see chapter 4.4 SICAM Switch Controls) of the earth isolator, the earth symbol can be connected to the right. To avoid errors in topology calculation, the earth isolator must be rotated via the SICAM Switch dialog with the **Orientation** parameter, if required; not via the WinCC Object properties dialog.

# 5.2.4 SICAM Bay Overview

You can use a bay overview to show the status of an entire bay by means of a single graphic object.



# NOTE

If the breakers configured in the bay overview are configured as individual breakers in another picture, make sure that the connecting points are correctly oriented.

In the topological model of the bay overview, the earth isolator is connected to the circuit breaker connector pointing away from the busbar, if the corresponding tags have been programmed (see *Figure 4-34*).

# 5.2.5 Connector

**Connectors** are used to link graphic objects. Usually it is used to represent, e.g., cable trains and bsubars. Lines must not be used for this purpose.

A connector can be linked to a graphic object on both ends. A connection is performed automatically if one end of a connector is positioned next to a graphic object. As soon as the connection has been successfully defined, the color changes from green to red.

For more detailed information regarding connectors, refer to the online help of the Graphics Designer.

## **Connecting points**

If a graphic object is moved, the linked end of the connector moves as well. The connector itself cannot be moved when linked to a graphic object. A connector must always be linked to a graphic object on both ends.

# 5.2.6 Node

With the **Connection point** graphic object, 2 connectors are linked or a feeder is created. A node can be represented as a circle or as a rectangle.

Up to 4 connectors can be linked to the same connection point.



[dw_topo col node, 1, en_US] Figure 5-14 Connection Point



# NOTE

Do not draw the connection point too small in order to ensure that the link to the connector can be conveniently defined.
# 5.3 Parameterization

# 5.3.1 Data Analysis

Various definitions for the representation of the network equipment and for the evaluation of the network status must be performed in order to be able to use the Dynamic network coloring function.

- In which pictures do you want to represent the current network status?
  - Substation diagrams
  - Worldmap with definition of the zoom levels (visibility)
- Which colors and symbols are used in order to represent the various equipment items?
  - Color of the voltage levels and feeders
  - Symbols used in the network diagrams
  - Coloring of the switch symbols from the topology
- What colors are used in order to represent the individual network statuses?
  - De-energized, grounded, undefined
  - Priorities of the topological status values
- Which of the following functions do you want to use additionally?
  - Consistent coloring across multiple pictures
  - Coupled and secure operating mode

The connectors are represented in the color defined for the individual network status. This line color can also be applied to the switching objects.

# 5.3.2 Data Model

# **Topological Elements**

All the objects whose indications are used to determine the current switching status of the network are referred to as "topological elements".

These include:

- Switching elements, e.g. disconnectors and circuit breakers
- Feeders
- Transformers
- Termination

In order to design networks which enable dynamic network coloring, all equipment items must be available as dynamic SICAM structure tags (RTInfo).

When designing pictures, it must be ensured that the lines end in the objects. This is a major prerequisite in order to be able to create an electrically connected network in which the topology can be calculated.

#### Coloring – Basic Principles

For dynamic network coloring the topological view of the network is represented via connectors and other topological elements. This function requires at least the following topological elements connected to each other via connectors:

- Source (Feeder)
- Termination

		6			1000	• • •	
1.1		C	y		:		-0
11			: :			:	
135	•	• •		11	•3	:0	
		1		8			$\sim$
			-	<u>.</u>	2		(2)
				÷.	•	•	$\smile$
2.2		11	: :		•	:	
133					2		
• •			•		•	•	
					1	1	
101						:	U

# [le_basic_structure, 1, --_--]

Figure 5-15 Basic structure

- (1) Feeder
- (2) Connector
- (3) Termination

In addition, the switching elements are inserted in this basic model, e.g. a circuit breaker.



[le_basic_structure_w_breaker, 1, --_--]

Figure 5-16 Basic structure with circuit breaker

(1) Feeder	ſ
------------	---

- (2) Connector
- (3) Termination
- (4) Circuit breaker

Via the supply type assigned, the topological element **Feeder** determines the color used for representing the lines. All other elements, e.g. the circuit breaker, transfer the color to other elements or restrict the coloring.

#### 1- and 2-pole elements



# NOTE

The left-hand connection point of the 1- and 2-pole-elements is highlighted with a small square in the Graphic Editor.

For more information regarding the connectors see Connecting points, Page 108

The topological graphic objects are subdivided into 1-pole elements, 1-pole elements with special function and 2-pole elements:

• 1-pole: Feeder, ground, terminator

A 1-pole element only has a connection on the left-hand side. Since all the objects have 4 connecting points, only 1 side may be used in any case.

1-pole with special function: Grounding disconnector (Earth isolator)

This 1-pole element must always be connected to the topology via its left-hand connection. The righthand side can be used additionally for a connection to a ground symbol graphic object.

• **2-pole**: Circuit breaker, disconnector, load break switch, transformer, bay overview To ensure unambiguous identification, the 2 connections of these 2-pole elements are referred to as the "left-hand connection" and "right-hand connection". 2-pole elements must always be connected to 2 connectors. The left-hand connection is marked with a small square in the Graphic Editor. See also *Connecting points, Page 108*.

Bay overview objects are not marked with a square; the left-hand connection is 'Always at the top' or on the 'Left'.



# NOTE

The left-hand connection of the 1- and 2-pole elements is marked with a small square in the Graphic Editor.

#### Line Node

Connections connected by means of connectors (lines) form a line node.

An element with 2 connections is connected to 2 line nodes, e.g. a circuit breaker (2-pole element). An element with 1 connection is connected to 1 line node, e.g. a grounding switch (1-pole element). Each line node must be represented completely with all its elements in at least 1 picture. For more detailed information, refer to *5.4 Cross-Picture References* 

All other functions, such as coloring or , are derived from the topological calculations performed for this line node. For this reason, the topological parameters of the node elements must be identical in all pictures. This means that a switch represented in various pictures must always have the same neighbor (breaker). However, these do not necessarily need to be drawn, e.g. for bay representations as a section from an overview picture.

As soon as the parameterization and project generation have been completed, the node structure of your network as well as any errors are shown in the tree view of the topology.



[sc_treeview, 1, en_US]

Figure 5-17 Representation of the topological node structure in the editor, example

When selecting a topological element, the corresponding picture is shown. The selected element is high-lighted.



[sc_node_and_graphic, 1, en_US]

Figure 5-18 Representation of the Topological Node Structure in the Editor with Picture Section, Example

# 5.3.3 Settings

You can access the two setting dialogs described below from the **Topological coloring** submenu of the **SICAM menu** (see 6.2 SICAM Menu).

# **Topological Settings for Selected Objects**

In the **Topological Settings for Selected Objects** dialog you can set the parameters of the **Topological coloring** function of the selected line and switching objects.

First, select the objects to edit. When the dialog is opened, their parameters are read in. If the selected objects are parameterized differently, the relevant parameter fields are displayed empty, check boxes are marked in the mixed state. If you do not edit these parameters, they will not be changed when you save them. The following applies to **Line mode**:

With **Use topological project settings** you apply to the selected objects the properties which have been defined as default in the *Topological Project Settings, Page 186* dialog.

To make different settings for the selected objects, remove the check mark next to **Use topological project settings** and set the line mode, the line thickness, and, if necessary, a different color for de-energized lines. The following applies to the **Line mode**:

- With **Single-colored** the color of the supplying source is displayed with highest priority.
- With **Two-colored** the 2 source colors with highest priority are displayed with dashed lines when supplied by different sources, otherwise they are displayed with single color.
- With **Fail-safe**, i.e. if the network section is supplied on both sides, the color of the source with highest priority is displayed. If the section is not fail-safe, i.e. if it is supplied only on 1 side, dashed lines are displayed with the colors of the source with highest priority and **Not energized**.

Set the **Line weight** independent from each other **For insecured supply** and **For secured supply**. For **de-energized lines** you can use a color different from supply type **Not energized**. The following applies to the **coloring of switch controls**:

- Choose whether you want to use the topological color for the selected switch controls.
- Since 2 different line colors can meet for switching state **OFF**, you still need to specify how the switching object should be colored:
  - Do not use topological color
  - Use color of top left connector
  - Use color of bottom right connector

# NOTE

Use deviating color for de-energized lines is ignored in this case – the setting in **Topological project** settings will be used.

# Topological Coloring

5.3 Parameterization

Topological settings for selected objects	×
Line representation Use topological project settings Line mode Single-colored	Coloring of switch controls Use topological color When switch control is OFF O Do not use topological color
<ul> <li>Two-colored</li> <li>Fail-safe</li> </ul>	<ul> <li>Use color of top/left connector</li> <li>Use color of bottom/right connector</li> </ul>
Line weight       For insecured supply       3       For secured supply       6	
De-energized lines ✓ Use deviating color	
	OK Cancel

[sc_settings_for_selected_objects, 2, en_US]

Figure 5-19 Dialog Topological Settings for Selected Objects

#### **Topological Project Settings**

In the **Topological Project Settings** dialog you define the project-wide default settings. In the *Topological Settings for Selected Objects, Page 185* dialog you can define differing values for single objects.

Use the **Supply type** tab to define **Line color** and **Secured state** as project default value for each available **Topological state**.

In addition, you can use Add topological state in order to define further topological states.

The states highlighted in gray are predefined. In contrast to self-defined states (highlighted in white), only the line color can be changed for these states; however, they cannot be renamed.

For the SICAM Topology objects (SICAM Electrical Device Controls), the color settings for the topological states are available as a selection list for the **Supply type** (see *Color, Page* 173).

Topological project settings		
ropological project settings		
Supply type Line representation		
Topological state	Line color	Secured
Initial		
Undefined		
Not energized		
Grounded		
Red (secured) - 480 kV		
Yellow (secured) - 110 kV		
Green (secured) - 400V		
Blue - 480 kV		
Orange - 110 kV		
Darkred - 230 V		
Add topological state		
ОК	Cancel	Apply

[sc_settings_for_project, 2, en_US]

Figure 5-20 Dialog Topological Project Settings – Supply Type

Use the **Line representation** tab to define the project-wide default values for **Line mode** and **Line weight**. For further information regarding possible settings for **Line mode** and **Line weight**, see *Topological Settings for Selected Objects*, *Page 185*.

Topological project settings		_		×
Supply type Line representation				
Line mode				
<ul> <li>Single-colored</li> </ul>				
◯ Two-colored				
◯ Fail-safe				
Line weight				
For insecured supply	2 ~			
For secured supply	4 ~			
[	ОК	Cancel	Ap	ply

[sc_line_representation, 1, en_US]

Figure 5-21 Dialog Topological Project Settings – Line Representation



# NOTE

For changes to take effect, the runtime has to be restarted



# NOTE

Do not use the **WinCC Classic** design with large line widths because 2-color connections cannot be displayed correctly in this case.

Use WinCC Classic with Line weight 1 only.

# Priority of the Topological Status Values (Colors)

The priorities of the topological status values are as follows: Grounded > Energized > Undefined > Initial state > Not energized

Topological state	Line color	Secured
Initial	<b>7</b> (1)	
Undefined		
Not energized		
Grounded		
Red (fail-safe) - 480 kV Low priority		$\checkmark$
Yellow (fail-safe) - 110 kV		
Green (fail-safe) - 400V		$\checkmark$
Blue - 480 k∨		
Orange - 110 kV		
Darkred - 230 V		
New topological state 1 High priority	/	
	-509)	

[sc_settings_for_project_priority, 1, en_US]

Figure 5-22 Priority in the Topological Project Settings

# 5.3.4 Parameterizing Elements and Symbols

For more detailed information on how to set the parameters of the elements, refer to 4 Graphic Objects.

# 5.3.5 Notes on Configuration

Before you create the topological structure, the connections are first checked. The Report window shows the result of this check, **warnings** or **error messages**.

An error message is displayed if the topological coloring could not be performed correctly during runtime. A warning is shown if the topological coloring could be performed although a discrepancy exists. A new topological calculation is performed if a warning is issued, but not in the case of an error. The following table provides a list of faulty connections.

Faulty connections	Result of the check	Correct connections	Remark
	Error The connector has not been completely linked.	••	Open connections can delay the build-up of a diagram. The open side of a connection tends to automatically link to another object.
•	Error 2 connectors are linked without a connection point.		An additional connector or an addi- tional connection point must be inserted.
	Error Circular connection	Disconnect the circular connection. Avoid a loop in a network.	The term 'circular connection' desig- nates that an active object (switch, bay overview, feeder and ground disconnector) is connected to itself. A loop consisting e.g. of 2 switches is not considered as a circular connec- tion.
Ø	Warning Connection to a graphic object which does not support topological coloring.		No topological coloring of this graphic object takes place during runtime.
•	Warning The graphic object has more than 1 connection on one of its inputs/ outputs.	•	For graphic objects, only 1 single connection can be defined per input/ output.

Table 5-2List of Faulty Connections

# 5.4 Cross-Picture References

If network sections are represented in different pictures, e.g. in the overview picture and in the branch picture, cross-picture node references must be created. This ensures that dynamic network coloring is possible across the limits of the individual picture.

# Reference via Double Representation of Topological Elements

If the topological elements of a node are represented in various pictures, the topology algorithm detects that the same elements have been created in the node copy.

As a prerequisite, the node must be **completely** described with all its elements in one of the pictures. In this case, fewer elements can be created on the node in the other pictures. Regarding the topology, the same parameter values must have been set as for the original node. However, **no additional elements** may be connected to the node copy.

In the example illustrated below, the **Original** of branch **HV Bay 1** is located in the overview picture and the **Copy** is located in the branch picture.



[sc_node_original, 2, en_US]

Figure 5-23 Original Node Definition (Overview Picture)



 [sc_node_copy, 2, en_US]

 Figure 5-24
 Reference Node Definition, Copy (Branch Picture)

# 5.5 Using Topological Coloring

The following requirements must be fulfilled in order to use the topological coloring function:

- The graphic objects Feeder and Ground must be used in your station diagrams.
- Connectors and connection points must be added instead of simple lines and circles.
- Feeders must be configured.
- Topological structure has to be created.

This subchapter provides an example for the creation of a picture using topological coloring. A measured value is used as source for the topological coloring.

The following section describes how to draw and configure a branch. Alternatively, you can use default branches from the library.

# **Positioning Graphic Objects**

Proceed as follows to position graphic objects on your workspace:

- ♦ To open the Library window, click View > Library.
- ♦ Select a **feeder** under **Topology**.

🧃 Global Library	Name	Size	Last Change
Project Library	🚅 Busbar with 3 nodes	1634	30.11.16 15:52
Graphic objects for SICAM SAS>	Busbar with 6 nodes	3440	30.11.16 15:52
Graphic objects of previous versions>	Connector	549	30.11.16 15:52
Alarm Logging templates	Feeder with internal tag	2581	30.11.16 15:53
	Feeder with measurement	2572	30.11.16 15:53
Measured/Metered values	Feeder with process tag	2537	30.11.16 15:53
Switching device objects	Field with bay overview	3319	30.11.16 15:53
	Field with BBDC, CB	10520	30.11.16 15:54
	Field with BBDC, CB, LNDC	13269	30.11.16 15:54
	Field with BBDC1, BBDC2, CB, EDC,	18047	30.11.16 15:54
( ) ) ·	Ground left with EDC	4375	30.11.16 15:55

[sc_topo_insert_object, 1, en_US]

Figure 5-25 Inserting graphic objects

- Hold down the mouse button and move the cursor over the workspace until the graphic object has reached the desired position.
- ♦ Insert the controls (switching device objects) from the library.
- Insert a grounding (consisting of earth isolator and ground disconnector).
   The grounding is available in the library under Topology.



[sc_topo_swob1, 2, --_--]

Figure 5-26 Picture with a feeder, controls (switching device objects) and a grounding.

# **Inserting Connection Points and Connectors**

- ♦ Insert the connection point into the picture.
   The connection points and connectors are available in the library under **Topology**.
- $\diamond$  Insert the connectors.

When inserting the connectors, make sure that the connection to the graphic object is properly defined. A successful connection is represented by a red dot.







# NOTE

After renaming an active graphic object (e.g. a feeder, switch, or connection point), all connections to this graphic object must be redefined. To do this, separate the connection in the picture and redefine it afterwards. This ensures that the new name is entered in the properties of the connector.

# **Configuring a Feeder**

Proceed as follows to configure a feeder:

 $\diamond$  Double-click the feeder.

The SICAM Electrical Device Control Properties dialog opens.

SICAM E	lectrical Device C	ontrol Pr	opertie	5	Х
Style	Tag connection	Color	Picture		
Disp	blay			Measurement	
Ty; Fe	pe: eder		$\sim$	Level ON/OFF 10.000000	
Dir 0°	ection:		~	Hysteresis 2.000000	
Lin 2	e width:			Pictures	
			(	OK Cancel <u>A</u> pply	

[sc_edc_style, 1, en_US]

Figure 5-28 Configuring a feeder

- In order to use a measured value as source for topological coloring, on the Tag connection tab, select
   Measurement as Tag type.
- ♦ In the Style tab under Measurement, you can now define the values for Level ON/OFF and Hysteresis.

# Linking feeders to tags

Each feeder must be linked to a tag.

To link the feeder to a tag, proceed as follows:

- ♦ In the SICAM Electrical Device Control Properties dialog, select the Tag connection tab.
- ♦ Select a Tag type:

**Process information**: The value of the information includes ON/OFF/DISTURBED or RAISED/CLEARED and is directly transferred to the topology calculation

**Internal information**: internal data structure, e.g. filled by a script; ON/OFF/DISTURBED values are transferred to the topology calculation

**Measured value**: Input data originate from a measured value; the switching point and the hysteresis determine ON/OFF and set the additionally linked internal message to this value which is then transferred for topology calculation. For further information see hint after *Figure 5-10*.

# Topological Coloring

5.5 Using Topological Coloring

SICAM Electrical Device Control Properties	×
Style Tag connection Color Picture	
Tag type Measured value	
Tag name information (*.RTInfo) Feeder_MW-Tag.RTInfo	
Tag name topological information (*.RTInfo)	
Feeder 1.RTInfo	
Tooltip text:	
SICAM Electrical Device	
OK Cancel	Apply

[sc_topo_tagconnection, 1, en_US]

Figure 5-29 Feeders, connecting tags

- ♦ Select the corresponding **Tag names** (*.RTInfo).
- ♦ Click **OK** to close the dialog.

#### **Creating the Topological Structure**

After inserting all graphic objects required and linking them to the appropriate connectors, the topological structure must be created.

♦ Activate the picture (e.g. by clicking the corresponding icon in the SICAM toolbar):



♦ Check the picture:



♦ Click the Create Topological Structure icon:



After checking the topology, the model and the event scripts on the objects are generated. You can view the progress in the Report window. Also errors are displayed here, see 5.7.1 General Information. For more detailed information concerning error messages, refer to 5.3.5 Notes on Configuration.

# 5.6 Using Picture Windows

You can use pictures as picture windows in superordinate pictures. If the picture window in the superordinate picture uses variable prefixes, you have to apply them for the picture which you want to display in the picture window. Therefore, during configuration you define a list with prefixes. These are taken to generate all possible combinations to be used for the topological coloring.

If you click a picture window in the superordinate picture during runtime, the corresponding values are displayed.

How to use the prefix list:

♦ Drag and drop the List tag prefixes element from the Topology section of the Library into your picture.

Library			
📸   X 🗈 🖎 🗡 ! º₂ 🖫 🏢   601			
Graphic objects for SICAM SAS>	Name	Size	Last Change
Graphic objects of previous versior	ៅ List tag prefixes	730	30.11.16 16:55
Alarm Logging templates	Mode circle	436	30.11.16 16:56
Bay overview objects	🗾 🚅 Node rectangle	441	30.11.16 16:56
Control elements	Termination	2362	30.11.16 16:57
Switching device objects	Transformer	2580	30.11.16 16:57
	🛛 🚅 Transformer auto 1phase	2620	30.11.16 16:56
	Transformer auto 3phase	2620	30.11.16 16:57
Dbject Properties 🕒 Library 🦿 Dynamic	Wizard		

[sc_bildfenster_prefix de, 2, en_US]

The element is inserted.

1000	12.22 30	1.00		- 20		10		10			12	1.0		12	112			100	12	10		et.	10		 100		•	1.0		•	•	
	-				•	•			•					•				•														
	K	١.						•							÷.																	
		<b>,</b> .	÷.,		•		8.		•		۰.		•		2.		••		٠.		•••	•	٠.									
	$\sim$						÷.				÷.								12	1			1.1		 					•		
	· · •					•										•		•														
				•				•							÷.																	
							۰.				2.				÷.				2.				٠.									
	🚦					e.	. e.			e.	÷.				12			a.			•				e.			1.0				
															-			100							900				-			
•			•					•							1	??	?	??	??	1										•		
			۰.				84				۶.				1	22	0	20	00	2												
								•			a.	•				• •	1	11	1	4									ł.	•		
					•					•						??	?	?7	??	3									ł.			
	I Т		•				÷.					•			11														1	•		
	and the second se				•		۰.		•		٠.				8L-	-		-	1	-		-	1	-	 -	1	1		4			
	I				•		12			a.	а.				. e. 1	• •			÷.			e.			 			1.20				
•			•	•	•								•	•											•							
	🗄			•		•						•		•	÷.	•		•												•		
		-					۰.				٠.				٠.		•	•	٠.		•				•							
	1.	10					÷.				1				at .			et e				et e			 							
		<b>_</b> .						•				•				•			1	•				•			•			•		

[sc_bildfenster_prefix_obj, 1, --_--]

Right-click the List tag prefixes object and open its Properties.
 Under Geometry you can set the Number of Rows as desired.

ist box	Attribute	Static	Dynamic	Update Ind
Geometry	Position X	240	Q	
Colors Styles Font Miscellaneous Effects	Position Y	110	Q	
	Width	160	Q	
	Height	60	Q	
	Number of Rows	3	Q	

[sc_bildfenster_rows de, 1, en_US]

♦ Under Miscellaneous you can change the texts.
 Therefore, use Selected box to select the entry and change it in Selected text.

List box Geometry Colors Styles	Attribute	Static	Dynamic	Update	Indir
	Tooltip Text		Q		
	Configured languages	Deutsch (Deutschland)			
	Operator message	No	Q		
Font	Operator Activities Report	No	Q		
Miscellaneous	Selected box	1	Q		
Effects	Selected text	?????1	Q		

[sc_bildfenster_text de, 1, en_US]

 $\diamond$  To hide the List tag prefixes object during runtime, set the Display attribute to No.

Properties Events					
Picture Object	Attribute	Static	Dynamic	Update	Indir.
Geometry	Operator-Control Enable	Yes	Q		
Colors Styles	Authorization	<no access="" protection<="" td=""><td>Q</td><td></td><td></td></no>	Q		
	Display	No	Q		
Miscellaneous	Update Cycle	2 s			
Background Picture	Date of Last Change	19.01.2017			
Ellects	Cursor Mode	Tab Order			
	Extended Zooming	Yes	Q		

[sc_bildfenster_unsichtbar de, 1, en_US]

# 5.7 Debugging

# 5.7.1 General Information

Any warnings or error messages which may pop up from the pictures during creation of the topological structure are displayed in the Report window.

<i>≣</i> Report	_		$\times$
🛨 Export 🛭 🗳 Print preview 😽 Delete 🖏 Delete all			
SICAM SCC Graphics Designer Add-in SICAM PAS Wizard SICAM IEC Wizard SICAM SCC IEC Importer 5	SICAM SCC Importe	r SICAM SO	• •
Messages	Date	Time	^
Tree view	4/4/2017	1:41:41 PM	
Begin: Process picture 'asdasdasd.odl'.	4/4/2017	1:41:41 PM	
	4/4/2017	1:41:41 PM	
Picture 'asdasdasd.pdl' opened	4/4/2017	1:41:42 PM	
Checking objects	4/4/2017	1:41:42 PM	
No tag information for topological object (e.g. switch) was parameterized.     SICAMSwitch PAS LBS	4/4/2017	1:41:42 PM	
(i) Close picture	4/4/2017	1:41:42 PM	
Processing is aborted.	4/4/2017	1:41:43 PM	
First, correct picture: 'asdasdasd.pdl'.	4/4/2017	1:41:43 PM	
End: Process picture 'asdasdasd.pdl'.	4/4/2017	1:41:43 PM	
End: Topological coloring - Generate project- 3 fault(s), 0 warning(s)	4/4/2017	1:41:43 PM	
٠		_	× *

[[]sc_error_generation, 1, en_US]

Figure 5-30 Error during generation, example

In addition, the error messages are also displayed in the tree view, see Figure 5-17.

# i

# NOTE

Click the link indicated in the error message in order to jump directly to the element concerned.

# 5.7.2 Error Messages

• An element occurs several times on the same node

An element must not occur several times on the same node. Otherwise, the representation can become inconsistent.

Element short circuited

The left- and right-hand connection of an element are connected. The subsequent error **Not connected** can also occur.

• Connected too often

A 1-pole element has more than 1 connection, but may only occur in an original node. A 2-pole element has more than 2 connections, but may only occur in 2 original nodes.

- Line without connection Check the line connection.
- Node without connection
   Check the configuration of the topological segment.

# Not connected

At least 1 feeder or transformer and at least 1 terminator must exist and be connected in the topology description. All other elements must be connected to a line and a neighboring element. Connectors without connection cause an error message.

# • Inconsistent representation

The most common cause is an erroneous double use of a process tag on a switching device objects. Elements can be duplicated for cross-picture representations. In this case a node copy is created, e.g. in a detailed picture. This node copy may include fewer elements than the original node, but no additional elements. No valid original node can be determined in such cases.

Complete the original node by the missing elements.

Connect the correct neighboring elements.

# • Incorrect transformer side

The transformer with its tag allocation has been used several times and has been installed at least once in the opposite direction, i.e. the Side 1 and Side 2 connections have been confused.

# • Type mismatch

Switching device or bay overview objects with the same tag assignment were defined with different topological types.

# • Supply type not clear

A different supply type was used for a SICAM Electrical Device Object in the original node and in the node copy.

# • Mounting direction (left/right reference) not consistent

The mounting direction of an element in the original node is opposite to the mounting direction in the node copy.

Rotate the element using the **Orientation** parameter in the **Properties** dialog.

# 5.8 Application Examples

# 5.8.1 Switchgear trucks

If switchgear trucks are shown in pictures, disconnectors supplied by the same process tag are represented on both sides of the circuit breaker. Since this scenario cannot be represented in the topology, only one of the disconnectors may be configured with the process tag.

The second disconnector must be connected to a newly created internal structure tag (type: **PAS_Informatio-nInternal**). The names can be freely selected or adapted to the name of the external process tag.

The disconnector with the internal tag connection cannot be controlled. For this reason, you can remove the **OnLeftClick** and **OnRightClick** scripts in the **Event** tab.



[sc_appex_carriage_event, 1, en_US] Figure 5-31 Scripts

If the process values of the disconnector with the process tag change, the data of the process tag is transferred to the internal tag via copying. The C script

SCC_CopyTagValueRT(char* p_cSourceTagName, char* p_cDestinationIntTagName, BOOL p_bDigitalValue) can be used for this purpose. You can configure the function to the **OnProcData-Change** event of the disconnector with tag connection. 5.8 Application Examples

```
#include "apdefap.h"
void OnProcDataChange(char* lpszPictureName, char* lpszObjectName , long opdcEvent, long Value)
{
//WINCC:TAGNAME SECTION START
// syntax: #define TagNameInAction "DMTagName"
// next TagID : 1
//WINCC:TAGNAME SECTION END
// WINCC: PICNAME_SECTION_START
// syntax: #define PicNameInAction "PictureName"
// next PicID : 1
// WINCC: PICNAME_SECTION_END
        char * cRTInfoName;
        char* cRTInfoNameINT;
        BOOL bOkValue = 0;
                       linkinfoRTInfo;
        LINKINFO
        int ch='';
        int iCharPosition;
        int iNameLength;
        cRTInfoName = malloc(256);
        memset (cRTInfoName, 0, 256);
        cRTInfoNameINT = malloc(256);
        memset (cRTInfoNameINT, 0, 256);
        // Get link of RTInfo property
        bOkValue = GetLink(lpszPictureName, lpszObjectName, "RTInfo", &linkinfoRTInfo);
        // get name of linked tag
        strcpy(cRTInfoName, linkinfoRTInfo.szLinkName);
        // cut off ".RTInfo" from variable name to get the structure name
        iNameLength = strlen(cRTInfoName);
        for (iCharPosition = 0; iCharPosition < iNameLength; iCharPosition++ )
        {
                 if (cRTInfoName[iCharPosition ] == ch) break;
        }
        // Build internal tag name and copy runtime data to variable
        strncpy (cRTInfoNameINT, cRTInfoName, iCharPosition );
        cRTInfoNameINT = strcat(cRTInfoNameINT, "_INT");
        SCC_CopyTagValueRT(cRTInfoName, cRTInfoNameINT, 1); //Return-Type: long int
        free (cRTInfoName);
        free (cRTInfoNameINT);
}
[sc_appex_carriage_script, 1, --_--]
Figure 5-32
                Example of the script
```

A .var file is required in order to ensure that the tag can be processed by the SICAMRTDataServer. The files for the SICAMRTDataServer are stored in the GWData subfolder of the WinCC project. The name must end with .var e.g. SICAMRTDS_TopoINT.var.

The file structure is as follows (identical with SICAMRTDS_TopoPlugIn.var):

# 2017-01-01 01:01:01.010101; SICAM_Pas803_T103M_T103IF_7SJ63_q1_einaus_INT.RTInfo; <Generic type>;

Each tag created manually for a (truck) disconnector must be entered here.

# 6 SICAM Add-In

6.1	Overview	204
6.2	SICAM Menu	205
6.3	SICAM Toolbar	207
6.4	Performing Settings	208
6.5	Predefined Tasks	211
6.6	Creating User-Defined Tasks	214
6.7	Replacing a Graphic Object in the Library	230

# 6.1 Overview

The SICAM add-in is an extension to the Graphics Designer.

It enables the parameterization of any graphic object in a diagram (picture) based on defined **tasks**. To do this, you use predefined tasks, but you can also create user-defined tasks.

The tasks allow the simultaneous parameterization of **several graphic objects**. You can define parameters for **static values**, **tag dynamizations** and also **events**.

Based on a specific task, you can e.g. assign a bay's switching device objects and measured-value objects tags from a different tag group.

As a rule, the **SICAM add-in** is enabled. To disable/enable it, click **Tools > Addin Manager** in the **Graphics Designer**.

The Graphic Library Explorer allows you to edit graphic objects in the SICAM graphic object library.



# NOTE

The **SICAM add-in** for the logged on Windows user is registered during installation. If another user works with SIMATIC WinCC, the SICAM add-in is not displayed in the SIMATIC WinCC Graphics Designer.

To activate the SICAM add-in for a newly logged on Windows user, the SICAM add-in must be registered while the new user is logged on. A **SICAMAddIn.reg** registration file which includes this registration is available in the <InstallationDirectory>\bin.

# 6.2 SICAM Menu

The **SICAM** menu provides the following functions:

- Topological Coloring
  - Topological settings for selected objects
     Opens the Topological settings for selected objects dialog.
  - Topological project settings

Opens the **Topological project settings** dialog, which allows you to define topology states and assign the project-wide default settings to lines and active objects.

#### Verify current picture

Verifies the object parameterization of the current picture and shows the result as well as any errors in the Report window.

This function enables the user to verify the picture without the need to change the existing project. The topological structure only must be generated once again after the picture has been saved.

#### - Enable/disable picture for topological coloring

Enables/disables the current picture and indicates the status with a checkmark.

#### - Create topological structure

Starts the project generation for the topology and shows the result and any errors in the Report window.

Tree view

Represents the topological node structure.

#### Tasks

Shows the dialog for executing predefined or user-defined tasks.

# • Define working area

Defines the working area in the picture by dragging a rectangle with the mouse. This working area applies to subsequent functions.

# • Select identical objects

Selects all graphic objects in the working area which correspond to the type of the selected graphic object. It is also possible to select several object types simultaneously.

This function allows you to simultaneously change e.g. the color settings for all selected graphic objects in the WinCC Properties dialog.

# Invert selection

Inverts the current selection. Selected graphic objects are deselected; deselected graphic objects are selected.

This function applies to the graphic objects in the whole picture.

# • Show Graphic Library Explorer

Opens the Graphic Library Explorer.

# Settings...

This submenu items allows you to perform general settings and create user-defined tasks, see *6.4 Performing Settings*.

# SICAM Help Topological coloring Topological project settings Tasks Topological settings for selected objects Define working area Verify current picture Select identical objects Enable/disable picture for topological coloring Invert selection Create topological structure Show graphic library explorer Tree view

[sc_sicam_menu, 2, en_US]

Figure 6-1 Graphics Designer, SICAM menu

Based on these tasks, you can edit:

- Controls (switching device objects) circuit breakers and disconnectors
- Feeders, Ground
- Measured-value objects
- All other graphic objects, e.g. standard objects

#### Define working area

The **Define working area** function influences the next two functions in the list. You can use it in order to define to which picture section the selection functions shall apply. If no working area or an empty working area has been defined, the selection functions apply to the entire picture.

To simultaneously modify the object properties of several identical graphic objects (e.g. breakers), you can use the selection function.

Proceed as follows to execute a selection function:

- ♦ Click to select the working area in your picture.
- Click the **Define working area** function.
   The graphic objects in the working area are recorded internally.
- Click on a free space on the picture.
   All visible markers are removed.
- ♦ Select the reference object.
- ♦ Next, click Select identical objects.

All identical graphic objects are selected in the working area.

The working area remains active until a new area is defined.

- $\diamond$  Right-click one of the selected graphic objects.
- ♦ Open the **Object properties** dialog.

You can now e.g. modify the **ColorON** attribute simultaneously for all selected graphic objects.

# 6.3 SICAM Toolbar

Die SICAM Toolbar wird angezeigt, wenn das SICAM Add-In über das Menü Extras > Addin Manager aktiviert wurde.

# Functions

lcon	Meaning
сц.	Define working area
<b></b>	Select identical objects
	Invert selection
0	Show task dialog
14 / 11	Activate/deactivate current picture for Topological Coloring
👬 / 👬	Check current picture; if an error occurs, the red symbol is displayed
📅 / 🖬	Create topological structure; if an error occurs, the red symbol is displayed
1	Show tree view

Table 6-1Functions of the SICAM Toolbar

You can also call up the functions of the SICAM Toolbar via the SICAM menu, see 6.2 SICAM Menu.

# 6.4 Performing Settings

To open the **Settings** dialog, click **SICAM > Settings...**. This dialog allows you to perform general settings and create user-defined tasks.

The following entries are displayed on the uppermost level of the **tree structure** in the left-hand pane of the dialog.

General

This entry is required for working with the **Graphic Library Explorer**.

Tasks

All **user-defined tasks** are arranged under this entry. User-defined tasks can only be displayed after they have been created by the user.

The settings are displayed and can be edited in the right-hand pane of the display. The display always shows the settings which belong to the entry selected in the tree structure. The settings are described in the following paragraphs.

New Dille level Fred	
New - Delete Import Export	ShowLibObjList False
	ShowLibObjList Indicates whether the library object list is shown to rename the new object when a new object is insert into the library.
	OK Cancel

# 6.4.1 General Information

[sc_sicam_settings, 1, en_US]

Figure 6-2 Settings dialog, General

The following setting is possible under General:

ShowLibObjList

This setting defines how a modified graphic object is inserted in the **Graphic Library Explorer**. **False** adds the modified graphic object under a new name.

**True** opens the **Select graphic object** dialog. In this dialog, you can modify the name of the graphic object and define whether it is replaced.

To replace the existing graphic object, right-click the graphic object and click **OK**. The existing graphic object is replaced by the modified graphic object; the name is retained.

The name of the replaced graphic object remains unchanged in each available language.

# 6.4.2 Tasks

Settings				?	×
New - Delete Import Export	Ξ	Parameterization of grap	hic objects		
		StaticProperties	(none)		
General		DynamicProperties	RGBValue		
⊟ Tasks		Events	(none)		
Upgrade V6 Ground object		Name	Upgrade V6 Grou	und obje	ect
		Description	The task connect	ts the "	Activ
	NT	lame he name to indicate a task.			
			01	_	
			ОК	Cano	iel

[sc_sicam_tasks, 1, en_US]

Figure 6-3 Settings dialog, Tasks

User-defined tasks can be created and defined below the User-defined tasks entry, see 6.6 Creating User-Defined Tasks.

You can call up these user-defined tasks in the **Graphics Designer** (SICAM > Show or hide task dialog) or via the SICAM Toolbar. They influence the graphic objects of a diagram.

#### Deleting a user-defined task

To delete a user-defined task:

- ♦ In the tree structure in the **Settings** dialog, select the task to be deleted.
- ♦ Click Delete.

#### Exporting a user-defined task

You can export the current task configuration into a ***.satsk** file. Afterwards, the task can be imported into another project.

To export a user-defined task:

- ♦ In the tree structure in the Settings dialog, select the task to be exported. In the tree structure, select the tasks in order to simultaneously export all user-defined tasks.
- ♦ Click Export.

#### Importing a user-defined task

You can import a task from a ***.satsk** file into the Settings dialog. The imported task is displayed in the tree structure in the left-hand pane of the display.

To import a user-defined task:

- ♦ In the **Settings** in the tree structure, select the **Tasks** entry.
- ♦ Click Import.

# 6.5 Predefined Tasks

The **SICAM Add-In** provides several **predefined tasks**. You can select a predefined task in the **Execute task** dialog.

To open this dialog, select SICAM > Show task dialog from the menu or click the icon in the 📿 toolbar.

Execute task					×
Pre-defined	tasks	User-defined tasks			
Switches, Ground: U Feeder: U Switches: Bay overvi Measured Measured Switches	bay ove pgrade o ograde o Upgrade ew: Upg value up value up bay ove	view: Change of tag c objects from SCC V7 to bjects from SCC V7 to e objects from SCC V7 to rade objects from SCC to V8.01: Upgrade to to V8.01: Upgrade to oview: Change of tag c	onnection (SCC V V9 V9 to V8, V9 S V7 to V8, V9 SICAM Numeric C SICAM Numeric C	(8, V9) Control (V8.02) (; Control (V8.02) (; 7)	~
Description					
					^
					~
- Selection -					
Use sele	cted ob	jects in picture.		Collect	
0 object	s) colle	cted		Show	
			Execute	Close	•

[sc_tasks_given, 1, en_US] Figure 6-4 Execute task dialog, Predefined tasks tab



# NOTE

If objects were replaced by a task: Check after the replacement whether configured scripts which have been applied must be adapted or removed.

# **Predefined Tasks**

The following predefined tasks are available:

- Switches, bay overview: Change of tag connection (SCC V8, V9) With this task you can change the tag connection of switch, bay overview, feeder, and ground objects in a switch bay.
- **Ground: Upgrade objects from SCC V7 to V9** With this task you can replace ground objects of SICAM SCC V7 with the ones of V9.

- Feeder: Upgrade objects from SCC V7 to V9 With this task you can replace feeder objects of SICAM SCC V7 with the ones of V9.
- Switches: Upgrade objects from SCC V7 to V8, V9 With this task you can replace switch objects of SICAM SCC V7 with the ones of V8 and accordingly V9.
- Bay overview: Upgrade objects from SCC V7 to V8, V9
   With this task you can replace bay overview objects of SICAM SCC V7 with the ones of V8 and accordingly V9.
- Measured value up to V8.01: Upgrade to SICAM Numeric Control (V8.02) (step 1) With this task you can replace measured value objects of former SICAM SCC versions with numeric objects of V9. For a successful upgrade you have to execute step1 and then step 2.
- Measured value up to V8.01: Upgrade to SICAM Numeric Control (V8.02) (step 2) With this task you execute the second step to upgrade measured value objects. The configured process tags *.Counter are replaced by *.RTInfo.
- Switches, bay overview: Change of tag connection (SCC V7) With this task you can change the tag connection of switch, bay overview, feeder, and ground objects in a switch bay.
- Switches: Update PAS CC V5.10 objects with "Activate" tag With this task you can update the switching device objects of PAS CC V5.10; the ActivateControls tag gets connected. The ActivateControls tag is connected.
- Measured value: Upgrade PAS CC V5.10 objects to V6 (up to V8.01)
   With this task you can replace measured value objects of SICAM SCC V5.1 with newer measured value objects (V6 to V8.01).
- Measured value: Upgrade PAS CC V5.0x objects to V6 (up to V8.01) (step 1) With this task you can replace measured value objects of PAS CC V5.0 with newer measured value objects (V6 to V8.01). For a successful upgrade you have to execute step1 and then step 2.
- Measured value: Upgrade PAS CC V5.0x objects to V6 (up to V8.01) (step 2) With this task you execute the second step to upgrade PAS CC V5.0 measured value objects. The configured process tags *.Counter are replaced by *.RTInfo.
- Show dynamics This task shows all the 'Dynamic' parameterization of the selected objects.
- Edit items of a Check Box or Option Group object The task adds, removes, or modifies the items of the selected Check Box or Option Group.
- Edit Items of a Listbox or Combobox The task adds, removes, or modifies the items of the selected Listbox or Combobox.

# NOTE

You can continue to operate existing SICAM SCC projects of version 7.xx with the current **IndustrialX Controls** without using the SICAM SCC Runtime Data Server.

In order to continue to use current IndustrialX Controls (switching device objects) the IX State Sync can also be continue to be used.

The optionally installable **IX State Sync** redundancy component is entirely replaced by the SICAM SCC Runtime Data Server and no longer is required when using the ActiveX Controls of V8.0 or higher.



# NOTE

Be aware that **pictures** and settings configured under the Bitmap option are not applied for Send **QoC in command value**.

Scripts or actions configured for properties or events of the switching device objects are not applied during conversion. They cannot be applied because the property types and events are not fully compatible. The scripts and actions must be created again after the conversion.

The new object which is used for replacement can be updated in advance with the corresponding pictures. All further object settings are applied during conversion.

#### **Executing a task**

Due to the large number of different application options, the execution of the various tasks cannot be described in detail. However, a brief description of each predefined task is provided in the **Execute task** dialog.

Three different types of tasks are possible, see 6.6 Creating User-Defined Tasks.

Proceed as follows to execute the Switches: Update PAS CC V5.10 objects with "Activate" variable predefined task:

- In the Graphics Designer, open the diagram (picture) to be edited.
- ♦ In the Graphics Designer, click SICAM > Show task dialog to open the Execute task dialog.
- ♦ Select the Predefined tasks tab.
- Select Switches: Update PAS CC V5.10 objects with "Activate" tag.
- $\diamond$  In the display, select the V5.10 controls for which you want to perform an upgrade.
- ♦ Click Execute.

The Switches: Update PAS CC V5.10 objects with Activate variable dialog opens. The ActivateControls value is entered in the New value column.

To confirm, click OK in the dialog which opens.
 The switching device objects are upgraded and the new value is applied.
 The result is output as a report.

# 6.6 Creating User-Defined Tasks

You can create your own, **user-defined tasks** in addition to the predefined tasks. The following 3 types of tasks are possible:

• **Parameterizing graphic objects** This task defines the properties and events of a group of graphic objects.

# • Replacing graphic objects

This task replaces the graphic objects in a diagram (picture) with new graphic objects. The values of the properties and events are copied in accordance with the definition.

# • Editing elements of a graphic object

In your diagram, you can edit the elements of a **check box**, **radio box**, **list box** or **combo box** in order to customize them according to your requirements. In the past, this task was performed in the **Object Properties**, attribute **Index** dialog. In the meantime, it could be further simplified with the new function.

The following paragraphs describe how to **create user-defined tasks**. A specific task is created for each possible task type.

The examples illustrate the creation of predefined tasks. To create customized tasks, proceed as illustrated below.

# 6.6.1 Upgrade V5.1 Measured Value Objects

This paragraph describes the creation and subsequent execution of the **Upgrade V5.1 measured value objects** task.

The following steps must be performed:

- Creating a task
- Configuring a task
- Executing a task

# Creating a task

To create a task:

In the Graphics Designer, select SICAM > Settings.
 The Settings dialog opens.

Settings		?		×
New - Delete Import Export	General         ShowLibObjList         True    ShowLibObjList          Indicates whether the library object list new object when a new object is insert in the library object list insert insert in the library object list insert ins	s shown to ren nto the library.	ame the	e
		DK (	Cancel	

[add-in501, 1, en_US]

Figure 6-5 Settings dialog, creating a task

- ♦ Select Tasks in the tree structure.
- Click New and then select the Replacement of graphic objects task type.
   The task is created and displayed in the tree structure.

#### Configuring a task

You can now configure the task, i.e. define the actions performed by the task.

- Under StaticProperties and DynamicProperties, keep the (all) entry.
   All values of the static and dynamic properties with the same property name are transferred during the upgrade of the V5.1 graphic objects to the new graphic objects and will be retained.
- In the Events row, click (all) and then click the button with the dots.
   The Events dialog opens.

Events		?	×
Action Event:	Initial value:		
(all)	Reference		$\sim$
	(this)		~
			~
	ОК	Cance	el

[add-in502, 1, en_US] Figure 6-6 Events dialog

- Under Action event, right-click (all) and select Delete.
   This removes the (all) entry. During the upgrade, the scripts of the V5.1 graphic objects will be replaced by new scripts.
- ♦ Right-click the empty field under Action event and select Apply. The delete process is executed.
- $\ \ \, \diamond \quad \ \ \, \text{Click } \mathbf{OK} \text{ to close the dialog.}$
- ♦ Under Name, enter Upgrade V5.1 measured value objects for the task.
- ♦ Under Description, enter a brief explanation of the task with notes on the workflow.
| Settings                                                                                                                                                                                                                                | ?   | ×   |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----|-----|
| New - Delete Import Export       Replacement of graphic objects         General       StaticProperties       (all)         Upgrade V6 Ground object       Events       (rone)         Name       Upgrade         Description       Text |     |     |
| The description of the task.                                                                                                                                                                                                            |     |     |
| ОК                                                                                                                                                                                                                                      | Can | cel |

[add-in503, 1, en_US]

Figure 6-7 Settings dialog, newly created task

♦ Click **OK** to close the dialog.

The task has been created and is displayed in Graphics Designer, **Execute task** dialog, **User-defined tasks** tab.

#### **Executing a task**

Proceed as follows to execute a task:

- ♦ In the Graphics Designer, open the diagram (picture) to be edited.
- ♦ Insert a measured value object of the new version into the diagram.
- ♦ In the Graphics Designer, click SICAM > Show task dialog to open the Execute task dialog.
- ♦ Select the User-defined tasks tab.
- ♦ Select the Upgrade V5.1 measured value objects task.

SICAM Add-In

6.6 Creating User-Defined Tasks

Execute task			×
Pre-defined tasks	User-defined tasks		
Upgrade V6 Grour Upgrade	nd object		
Description			
Text			^
			~
Selection			
Use selected of	jects in picture.		Collect
0 object(s) colle	ected		Show
		Execute	Close

[add-in504, 1, en_US]

Figure 6-8 Graphics Designer, executing the task

♦ In the display, select the measured value objects for which you want to perform an upgrade.

#### ♦ Click Collect.

The highlighted measured value objects are now available for selection.

- ♦ Select the measured value object of the new version.
- ♦ Click Execute.

The measured value objects are upgraded. The result is output as a report.

### 6.6.2 Upgrade of V5.10 Controls

This paragraph describes the creation and subsequent execution of the Upgrade V5.10 Controls task. The following steps must be performed:

- Creating a task
- Configuring a task
- Executing a task

#### Creating a task

To create a task:

In the Graphics Designer, select SICAM Settings.
 The Settings dialog opens.

Settings		?	×
New - Delete Import Export	□ General         ShowLibObjList         True         ShowLibObjList         Indicates whether the library object list is shown to new object when a new object is insert into the library	rename t ary.	he
	ОК	Cance	<b>اد</b> ۱۱.

#### [add-in505, 1, en_US]

Figure 6-9 Settings dialog, creating a task

- ♦ Select Tasks in the tree structure.
- Click New and then select the Parameterization of graphic objects task type.
   The task is created and displayed in the tree structure.

#### Configuring a task

You can now configure the task. i.e. define the actions performed by the task.

Click DynamicProperties and then click the button with the dots.
 The DynamicProperties dialog opens.



[add-in506, 1, en_US]

Figure 6-10 DynamicProperties dialog

- ♦ Right-click the empty field under Dynamic property and select Add. The Add dialog opens.
- ♦ From the list in this dialog, select the name of the property you want to edit (here: Activate) and then click OK to close the dialog.

If the desired property is not included in the list, you can enter the name.

- ♦ Under Initial value, select the Tag entry.
- ♦ Enter the ActivateControls initial value.

DynamicProperties		?	×
Dynamic Property:	Initial value:		
Activate	Tag		$\sim$
	ActivateControls		~
			$\sim$
	OK	Cano	el

[add-in507, 1, en_US]

Figure 6-11 DynamicProperties dialog

- Right-click the field under Dynamic property and select Apply.
   The initial value is applied.
- ♦ Click **OK** to close the dialog.
- ♦ Under Name, enter Upgrade V5.10 controls for the task.
- ♦ Under **Description**, enter a meaningful text.

Settings			?	×
New - Delete Import Export  General  Tasks Upgrade V6 Ground object Upgrade Upgrade Switching Devices	Parameterization of graph     StaticProperties     DynamicProperties     Events     Name     Description      Description      The description of the task.	ic objects (none) Activate (none) Upgrade Switching Text	g Devic	es
		ОК	Cance	

[add-in508, 1, en_US]

Figure 6-12 Settings dialog, newly created task

♦ Click **OK** to close the dialog.

The task has been created and is displayed in Graphics Designer, **Execute task** dialog, **User-defined tasks** tab.

#### **Executing a task**

Proceed as follows to execute a task:

- ♦ In the **Graphics Designer**, open the diagram (picture) to be edited.
- ♦ In the Graphics Designer, click SICAM > Show task dialog to open the Execute task dialog.
- ♦ Select the User-defined tasks tab.
- ♦ Select the Upgrade V5.1 controls task.
- ♦ In the display, select the switching device objects for which you want to perform an upgrade.

Execute task			×
Pre-defined tasks	User-defined tasks		
Upgrade V6 Grour Upgrade	nd object		
Upgrade Switchin	g Devices		
Description			
Text			^
			~
Selection			
Use selected of	ojects in picture.		Collect
0 object(s) colle	ected		Show
		Execute	Close

#### [add-in509, 1, en_US]

Figure 6-13 Graphics Designer, executing the task

#### ♦ Click Execute.

The **Upgrade V5.10 controls** dialog opens. The **ActivateControls** value is entered in the **New value** column.

Filter by the differe	ent criteria						
Object type (r	none)	<ul> <li>Item type (none)</li> </ul>	<ul> <li>Actual value type</li> </ul>	(none)	▼ Value (none)		-
Search in New	value	<ul> <li>Find what</li> </ul>	•			Reset	filte
Object	Name	Actual value		New value			
SCC V5.10 LS1	Activate	Empty		ActivateControls			
SCC V5.10 LS2	Activate	Empty		ActivateControls			
SCC V5.10 LS3	Activate	Empty		ActivateControls			
In the 'New valu	ue' column, Find what	at	Replace by			Re	plac
					OK	Cance	el

#### [add-in510, 1, en_US]

Figure 6-14 Upgrade V5.10 switching device objects (controls)

#### ♦ Click **OK** to close the dialog.

The upgrade of the switching device objects (controls) is performed. The result is output as a report.

## 6.6.3 Edit Items of a Listbox or Combobox

This paragraph describes the creation and subsequent execution of the **Edit items of a Listbox or Combobox** task.

The following steps must be performed:

- Creating a task
- Configuring a task
- Executing a task

#### Creating a task

To create a task:

 ♦ In the Graphics Designer, select SICAM Settings. The Settings dialog opens.

Settings		?	Х
New - Delete Import Export	□ General         ShowLibObjList         True         ShowLibObjList         Indicates whether the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object is insert into the library object list is shown to new object when a new object list is shown to new object when a new object list is shown to new object when a new object list is shown to new object when a new object when a new object list is shown to new object when a	o rename t	the
	ОК	Canc	el .

[add-in511, 1, en_US]

Figure 6-15 Settings dialog, creating a task

- ♦ Select Tasks in the tree structure.
- Click New and then select the Edit items of a Listbox or Combobox task type.
   The task is created and displayed in the tree structure.

#### Configuring a task

You can now configure the task. i.e. define the actions performed by the task.

♦ Click PropertynameCount and then on the button with the dots.
 The PropertynameCount dialog opens.

#### SICAM Add-In 6.6 Creating User-Defined Tasks

PropertynameCount	×
Check Box1	$\sim$
Border Background Color Border Color Flashing Line Color Off Flashing Line Color On Line Style Line Weight Base Alignment	^
Number of Boxes Configured Languages Draw border inside Fill Pattem Color Dynamic Filling Fill direction Fill Level Fill Pattem	~
BoxCount	
OK Cance	<b>اا</b> :

[add-in512, 1, en_US]

Figure 6-16 PropertynameCount dialog

♦ Select CheckBox1.

The attributes of a check box are listed in the window in the center.

- Select the name of the property (e.g. **Number of boxes**) in order to assign the property (e.g. **BoxCount**).
- ♦ Click **OK** to close the dialog.
- ♦ Leave the entries under **PropertynameIndex** and **PropertynameText** unchanged.
- ♦ Under Name, enter Edit items of check box for the task.
- ♦ Under Description, enter a meaningful text.

Settings				?	×
New - Delete Import Export General Topological coloring Tasks Upgrade V5.1 measured value objekts Upgrade V5.10 switching device objects Edit items of check-box		Editing of graphic object PropertynameCount PropertynameIndex PropertynameText Name Description	ctitu i i	ems BoxCount Index Text Edit items of check-box Text	
	D	escription he description of the task.			
				UK Cancel	ل :::

[add-in513, 1, en_US]

Figure 6-17 Settings dialog, newly created task

Click OK to close the dialog.
 The task has been created and is displayed in Graphics Designer, Execute task dialog, User-defined tasks tab.

#### **Executing a task**

Proceed as follows to execute a task:

- ♦ In the **Graphics Designer**, open the diagram (picture) to be edited.
- ♦ In the Graphics Designer, click SICAM > Show task dialog to open the Execute task dialog.
- ♦ Select the User-defined tasks tab.
- Select the Edit items of a Listbox or Combobox task.
- $\diamond$  In the display, select the check box which you want to edit.

SICAM Add-In 6.6 Creating User-Defined Tasks

Execute task			×
Pre-defined tasks	User-defined tasks		
Upgrade V6 Ground Upgrade Upgrade Switching Edit Items of check	l object Devices -box		
Description			
Text			^
			~
Selection			
Use selected obje	ects in picture.		Collect
0 object(s) collect	ted		Show
		Execute	Close

[add-in514, 1, en_US]

Figure 6-18 Graphics Designer, executing the task

♦ Click Execute.

The CheckBox1 dialog opens.

Check Box1			?	×
Current language	German (G	ermany)		
Option 1 ??????2 ??????3				
		ОК	C	ancel

[add-in515, 1, en_US] Figure 6-19 CheckBox1 dialog

- $\diamond$  Modify the texts of the existing options.
- ♦ To add an option, right-click the box and click Add.
- ♦ Click OK to close the dialog.
   The check box with the new texts and the additional option is displayed.

## 6.7 Replacing a Graphic Object in the Library

The replacement of existing objects by objects of a new version or by corrected objects can be performed automatically. When replacing the objects, the existing tag connection will be applied, which significantly reduces the configuration and testing expenditure.

To replace a graphic object:

- In the Graphics Designer, select SICAM > Settings.
   The Settings dialog opens.
- ♦ Select General in the tree structure.
- ♦ Set ShowLibObList to True.

The **ShowLibObjList** setting enables you to define how a modified graphic object is inserted in the **Graphic Library Explorer**, see chapter 6.4.1 *General Information*.

- ♦ Click **OK** to close the dialog.
- Insert the graphic object to be modified, e.g. a feeder, into a diagram.
- ♦ Modify the object properties, e.g. the feeder width.
- Drag the modified graphic object from the diagram into the graphic object library.
   The graphic object is inserted temporarily, e.g. as Object2, and the Graphic Library Explorer opens.

orary			
🎽   X 🗈 🛍 🗙   º= 🖫 🏭 🐻 -			
📄 Global Library	Name	Size	Last Change
Project Library	🚅 Field with BBDC, CB	10839	27.01.17 16:26
■ <graphic for="" objects="" sas="" sicam=""></graphic>	Field with BBDC, CB, LNDC	13732	27.01.17 16:26
Straphic objects of previous versions>	Field with BBDC1, BBDC2, CB, EDC,	18805	27.01.17 16:26
Alarm Logging templates	Cround left with EDC	4538	27.01.17 16:25
	Ground right with EDC	4542	27.01.17 16:25
Masured/Metered values	🛁 List tag prefixes	735	27.01.17 16:27
Switching device objects	🕍 Node circle	441	27.01.17 16:26
	📈 Node rectangle	439	27.01.17 16:27
	n Termination	2367	27.01.17 16:27
	🛁 Transformer	2604	27.01.17 16:27
	📝 Transformer auto 1phase	2644	27.01.17 16:28
	📫 Transformer auto 3phase	2644	27.01.17 16:28
	ៅ Object1	2642	05.04.17 14:29
>	]		

[sc_lib_replace1, 1, en_US]

Figure 6-20 Modified graphic object, temporarily inserted

Select graphic library object		?	×	
Name ↑ Object1 ↑ Feeder with internal tag ↑ Feeder with measurement ↑ Feeder with process tag ↑ Ground left with EDC ↑ Ground left with EDC ↑ Field with BBDC, CB ↑ Field with BBDC, CB, LNDC ↑ Field with BBDC1, BBDC2, CB, EDC, LNDC ↑ Field with BBDC1, BBDC2, CB, EDC, LNDC ↑ Field with bay overview ↑ Node circle ↑ Node circle ↑ List tag prefixes ↑ Busbar with 5 podes	1031:Einspeisung mit Prozes 1033:Feeder with process ta	ssmeldur 1g	פו	^
가 Busbar with 6 nodes 가 Termination 가 Transformer 가 Transformer auto 1phase				~
	UK	Cance	8	

#### [sc_lib_replace2, 1, en_US]

Figure 6-21 Graphic Library Explorer with the list of graphic objects

The **Graphic Library Explorer** displays a list of all graphic objects which are stored in the current directory and can be replaced.

- ♦ Select the graphic object which you want to replace.
- ♦ Click **OK** to confirm.
- ♦ In the dialog which opens, click Yes.

The existing graphic object is replaced by the modified graphic object in the SICAM graphic object library.

6.7 Replacing a Graphic Object in the Library

Library			
📸   X 🗈 🛍 🗙   🖦 🐎 🏥 🏢   60			
□ Global Library       Name         □ Project Library       □ Busbar with 3 nodes         □ - □ < Graphic objects for SICAM SAS>       □ Busbar with 6 nodes         □ - □ < Graphic objects of previous versions>       □ Connector         □ - □ Alarm Logging templates       □ Feeder with internal tag	Size 1670 3500 547 2636	Last Change 27.01.17 16:27 27.01.17 16:27 27.01.17 16:28 27.01.17 16:25	
Bay overview objects Control elements Measured/Metered values Switching device objects Topology	Feeder with measurement Feeder with process tag Field with bay overview Field with BBDC, CB	2636 2582 3391 10839 13732	05.04.17 14:33 27.01.17 16:25 27.01.17 16:26 27.01.17 16:26 27.01.17 16:26
Chiert Properties	Field with BBDC1, BBDC2, CB, EDC, Ground left with EDC Ground right with EDC List tag prefixes	18805 4538 4542 735 441	27.01.17 16:26 27.01.17 16:25 27.01.17 16:25 27.01.17 16:27 27.01.17 16:27 27.01 17 16:26
E object ropentes			

[sc_lib_replace3, 1, en_US]

Figure 6-22 Graphic object replaced



#### NOTE

This procedure does not change graphic objects in existing diagrams. Newly inserted graphic objects have the new properties.

# 7 Components and Functions

7.1	System Overview	234
7.2	Data Import	250
7.3	SICAM Communication Connection - Tag Management	280
7.4	Alarm Logging	286
7.5	Dynamic Alarm Filter (DAF)	296
7.6	SICAM Functions	308
7.7	System Control	325
7.8	SICAM SCC Runtime Data Server	338
7.9	Language Settings	339
7.10	Communication with SICAM DISTO	343
7.11	SNMP – SICAM Network Manager (NWM)	345

## 7.1 System Overview

This section provides you with detailed information on the connections to the supported target systems:

- SICAM PAS/PQS, see chapter 7.1.1 Connection to SICAM PAS/PQS
- SICAM RTUs, IEC 61850 and IEC 60870-5-104 devices, see chapter 7.1.2 Connection to SICAM RTUs or IEC 61850/IEC 60870-5-104

## 7.1.1 Connection to SICAM PAS/PQS



[System_SCC_1, 1, en_US]

Figure 7-1 SICAM SCC with SICAM PAS/PQS server and bay devices

SICAM SCC is connected to SICAM PAS/PQS using a **SICAM SCC Proxy driver** integrated in SICAM PAS/PQS. This driver communicates with the SICAM PAS/PQS channel and enables the setup and connection of redundant SICAM PAS/PQS or SICAM SCC systems.

The internal control is performed via **administrative tags** created in the corresponding channel connection in a **SICAM_Admin** tag group in the WinCC Tag Management.

The process tags are created in the Tag Management according to their names in SICAM PAS/PQS. These tags are created as data structures (structured tags) in order to enable the transmission of the value together with additional information such as the status or cause.

The process data can be mapped into both the Tag Management and the Alarm Logging systems. When using the Tag Management, the maximum number of licensed tags for SIMATIC WinCC must be taken into account. For SICAM SCC, one item of SICAM information, i.e. one structured tag, is counted as a WinCC tag. This restriction does notapply to the information for the Alarm Logging system.

If several stations are imported into a SIMATIC WinCC project, the project ID of the imported stations must be unique because this ID becomes part of the message numbers and enables the distinction of the individual stations, see the note in chapter *Table 7-15* following table 6-7.

Process data can also be mapped into the Tag Logging system. The maximum number of licensed data points must also be observed for the Tag Logging system. A special license is available for this.

#### Message buffer

The **SICAM SCC Proxy driver** integrated in SICAM PAS/PQS includes a **message buffer** for the storage of messages which occur in case of a communication fault ora short-time shutdown of SICAM SCC. As soon as the communication between SICAM SCC and SICAM PAS/PQS has been restored, these buffered messages are forwarded to the WinCC Alarm Logging system in order to prevent gaps in the message archives.

The messages are buffered from the start of the SICAM SCC driver in the SICAM PAS/PQS system. All status changes which occur after the start of the SICAM PAS/PQS system and which are mapped to SICAM SCC are logged in the SICAM SCC message list.

The message buffer size can be defined in **SICAM PAS/PQS UI - Configuration**. If the message buffer is set to 0, it is deactivated. A message buffer overflow is indicated by means of a system message in SICAM PAS/PQS. This system message can also be mapped to SICAM SCC and logged in the message lists.



### NOTE

If a redundant SICAM PAS/PQS system is connected to SICAM SCC and a SICAM PAS/PQS system cannot be contacted, the entry of messages in the message lists can be delayed after an interruption of the connection or after the start of the SICAM SCC system.

#### Resetting the message archive

To reset the message archive:

• In the Alarm Logging window, right-click Messages and select Archive Configuration > Reset from the context menu.

The message archive and the message lists are emptied.

Alarm Logging			~		Message types [ S	
🖃 🖂 Messages			^		Name	
🗄 🖓 Error	New message class			1	Alarm	
🕀 🖓 Analo				2	Warning	
🗄 - 🖼 SICAI 🖼	Сору			3	Failure	
🗈 - 🔛 SICAI 🛍	Paste			4	Analog Warning	
🗄 🖓 SICAI 🚬	Emered	t S		5	Analog Error	
🗄 🖓 SICAI	Ехроп	t D		6	Alarm_161	
SICAL 👔 Archive Configuration 🔸			F	Reset	N	
<b>`</b>	Selection •		1	Link archive		
Tag Management Disconnect from arc		nnect from archive				
Alarm Logging	Alarm Logging Reload after power fai		d after power failure			
Tag Logging		Properties		rties		

[sc_archiv-reset, 1, en_US]

Figure 7-2 Resetting the message archive

#### Saving the current status

To ensure the consistency of the message lists - thus to prevent missing messages or double entries even after a restart of SICAM SCC - the last messages are saved persistently in a file. In order to enable a comparison of the messages arriving from the message buffer with the current status of SICAM SCC, this data is read in upon a restart of SICAM SCC. The **PersistantStorage.psf** file is stored in the corresponding station directory (...\Project directory\GWData\<Station name>).

Delete message lists: To ensure that all messages are displayed as usual in the message list upon the restart of SICAM SCC Runtime even after a reset of the message archive, the corresponding files of the stations included in the project must be deleted as well.

#### Adaptation of the configuration required

To prevent double entries in the message list, the message lists in the diagrams of existing projects (up to version 7.01) must be replaced by new ones from the SICAM graphic object library because the filter settings have been adapted to the message buffer.

## 7.1.2 Connection to SICAM RTUs or IEC 61850/IEC 60870-5-104



Figure 7-3 SICAM SCC with SICAM RTUs and bay devices

SICAM SCC is connected to SICAM RTUs or bay devices via IEC 61850/IEC 60870-5-104 using the **SICAM IEC COMMUNICATION SUITE**. This also enables the setup and connection of redundant systems.

The internal control is performed via **administrative tags** created in the corresponding channel connection in a **SICAM_Admin** tag group in the WinCC Tag Management.

The process tags are created in the Tag Management with their names from the SICAM TOOLBOX II configuration or a SCD/CID/XML file. These tags are created as data structures (structured tags) in order to enable the transmission of the value together with additional information such as the status or cause.

The process data can be mapped into both the Tag Management and the Alarm Logging system. When using the tags in the Tag Management system, the maximum licensed number of tags for SIMATIC WinCC must be taken into account. For SICAM SCC, one item of SICAM information, i.e. one structured tag, is counted as a WinCC variable. This restriction does not apply to the information for the Alarm Logging system.

A project ID is assigned when creating a station with the SICAM IEC Wizard (import in the Wizard). The numbering of the different stations starts with 10. It remains unchanged in case of a further import using the Wizard.

Make sure that you use unique project IDs in the case of mixed projects with SICAM PAS connections.

#### Resetting the message archive

To reset the message archive:

In the Alarm Logging window, right-click Messages and select Archive Configuration > Reset from the context menu.

Alarm Logging 🖼 Message types [ S << ~ Name Messages 1 Alarm 🗄 🖓 🔛 Error New message class 2 Warning Analo Copy 3 Failure 🚽 SICAI Paste 4 Analog Warning SICAI 5 Analog Error SICA t SI Export 6 Alarm_161 🗄 - 🔛 SICAI D 🗄 🖂 SICAI 🛅 Archive Configuration Reset ۲ < Selection Link archive ١ Tag Management Disconnect from archive Alarm Logging Reload after power failure Tag Logging Properties

The message archive and the message lists are emptied.

[sc_archiv-reset, 1, en_US]

Figure 7-4 Resetting the message archive

#### Saving the current state for IEC 61850 devices

In order to also ensure consistency of the message lists without missing messages or double entries after a restart of SICAM SCC, the last messages are persistently saved in a file.

This data is read in upon a restart of SICAM SCC in order to ensure that the messages arriving from the message buffer can be compared to the current status of SICAM SCC.

The **BufReportData.bin** file is stored in the corresponding station directory (...\Project directory\GWData \<Station name>\ComConfig61850).

#### Adaptation of the configuration required

In order to prevent double entries in the message list, the message lists in the diagrams of existing projects (Version 7.01 or earlier) must be replaced by new ones from the SICAM graphic object library because the filter settings were adapted to the message buffer.

#### Initialization of the IEC Tags upon the Start of the Runtime

For IEC 61850 and IEC 60870-5-104 drivers, any changed values and any changed status information of the tags during the runtime are stored in a status file (IEC 61850: DATA61850.BIN, IEC 60870-5-104: STATUS.BIN), provided that this has been defined for the corresponding tag ("Save value", "Save status").

When starting the Runtime, the values and status information are read out of these files and used to initialize the tags as specified in the **Status mask** parameter. Afterwards, these tags are transmitted to the SCC. This ensures that the process image in the Tag Management corresponds to the process image in the driver and the GI is initiated with the correct data.

Via the **IniTimeout** parameter, the Invalid identifier of the receive data points can be retained from the time of starting the Runtime until the connection has been set up successfully. Alarm and event list entries can thus be avoided. Once this timer has expired, the non-received data points are transmitted to the SCC via an Invalid replica.

## 7.1.3 Configuration for Improved Message Display in the Case of Redundancy

On redundant SICAM SCC systems, IEC 61850, IEC 104 and SNMP communication channels can result in duplicate entries in the message lists. This behavior occurs especially after disconnections or restarts of the WinCC runtime on one of the 2 redundant systems.

In order to identify and assign reporting instances to each other, SICAM SCC projects with IEC or SNMP channels use the timestamps provided by the transmitter. For identical timestamps, 1 instance can then be discarded. This does not work with the SNMP port, because the messages are sent without a timestamp and are only time-stamped in the SNMP channel of SICAM SCC itself. For all 3 ports, system messages are also sent without a timestamp and must then be time-stamped by the channel driver, and in IEC 104 even General Interrogation messages.

In order to avoid duplicate messages in these cases, you can link a **DAF_Marker** tag to the messages in the Dynamic Alarm Filter (DAF), which then logs only the messages of the leading system. The DAF_Marker tag is controlled by a global action. This requires an OPC connection between the 2 redundant WinCC computers, which transmits the tag **@RedundantServerState** of both systems to the other side.

#### Setting Up OPC Connection on Both Machines

- ♦ To set up an OPC connection, start the Runtime on both WinCC servers.
- ♦ Open the Tag Management and select Add new driver > OPC from the context menu.

<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp	
Tag Management	« 📦 Tags [ All ]
I Tag Management	Nama
🗄 🍄 In 🖡 Add new driver 🔸	SIMATIC S7 Protocol Suite
Struc 🕞 Copy	SIMATIC S7-1200, S7-1500 Channel
Paste	SIMATIC S5 Serial 3964R
▶ Export	SIMATIC S5 Programmers Port AS511
	SIMATIC S5 Profibus FDL
	SIMATIC S5 Ethernet Layer 4
	SIMATIC TI Serial
	SIMATIC TI Ethernet Layer 4
	SIMATIC 505 TCPIP
	Allen Bradley - Ethernet IP
	Mitsubishi Ethernet
	Modbus TCPIP
	OPC
	OPC UA WinCC Channel
	Profibus DP
	Simotion
	System Info
	SICAM IEC Communication Suite
	SICAM PAS Protocol Suite V5
	SICAM PAS Protocol Suite V6
	SICAM PAS Protocol Suite
	SICAM SNMP Suite
I	

III Tag Management - WinCC Configuration Studio

[sc_opc_neuer_treiber, 1, en_US]

♦ In the Tag Management, right-click OPC Groups and select System parameters from the context menu.

7.1 System Overview



[sc_opc_systemparameter, 1, en_US]

#### ♦ Click **Computer...** and enter the **Computer Name** of the redundant server.

📌 OPC Item Manager	– 🗆 X
File View Options Help	
Microsoft Terminal Services Microsoft Windows Network Web Client Network WORKGROUP V <local> Unlisted Computer × Computer Name: SCCCL88 OK Cancel</local>	Computer OPC Web server Browse Server Exit
Finished!	

[sc_opc_rechnername, 1, en_US]

- ♦ Click OK.
- Click the plus sign in front of the displayed computer name. If the OPC pairing is configured correctly and all access rights are available (same user on both machines), the question mark disappears from the computer icon.

PC Item Manager File View Options Help	_		×
VMware Shared Folders Microsoft Terminal Services Microsoft Windows Network WORKGROUP WORKGROUP V4LOCAL > V4LOCAL > V5CCCL67 CCOPC.XMLWrapper.1 COPCServer.WinCC.1	Co OPC	web serv	er
	Bro	wse Serve	r
		Exit	
Attempts are made to connect the desired OPC server.			

[sc_opc_expand, 1, en_US]

- Select **OPCServer.WinCC.1** and click **Browse Server** (Runtime must be running).
- ♦ In the following Filter Criteria dialog, do not enter anything and click Next ->.

#### The OPCServer.WinCC.1 dialog opens.

Under @LOCALMACHINE:: > Internal Tags select the @RedundantServerState tag. This tag contains the redundancy status of the "other" WinCC machine at the runtime.

OPCServer.WinCC.1 - (SCCCL88)				×
OPCServer.WinCC.1  CLOCALMACHINE:: CLOCALMACH	Items @Con @Curr @Data @Delt @Cloca @Red @Serv	InectedRTClients rentUser rentUserName asourceNameRT taLoaded alMachineName dundantServerState verName verVersion	Data Type	
<- Back	Display Data Types	Add	Items Item Prope	erties

[sc_opc_internal_var, 1, en_US]

♦ Click Add Items.

To create a new logical connection, answer the following dialog with Yes.

♦ In the New Connection dialog, the proposed name of the connection is displayed automatically. Change the name if desired.

New Connection	×
Please enter a name for the new connection:	
OPCServer_WinCC_1	
OK Cancel	

[sc_opc_new-conn, 1, en_US]

- ♦ Click OK.
- ♦ To use the tag in the global action, in the Add Tags dialog, enter "RedunPartner" as the tag's Prefix.

Add Tags	×
Tags to be added:	
Tag names should be completed as follows:       Prefix     Name     Suffix       RedunPartner     ExampleTag	
Example: RedunPartnerExampleTag	
Add here:	
<- Back Finish	

[sc_opc_add_var, 1, en_US]

- ♦ Click Finish.
- ♦ Go back to the Tag Management. Right-click OPCServer_WinCC_1 and select Connection Parameters from the context menu.

III Tag Management - WinCC	Configu	ration Studio			
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u>	<u>H</u> elp				
Tag Management		~		Tags	[OPCServer_WinCC_1]
🖃 🛄 Tag Management				Name	
🕀 🍄 Internal tags			1	Redun	Partner@RedundantServerState
📄 🚽 📙 OPC			2	罴	
🖶 👖 OPC Groups (Of	PCHN Ur	it #1)	3		
OPCServer_V	NE-CC 1		4		
🗄 🚭 Structure tags	S Ne	w Group			
	Co	ру			
	🖺 Pa	ste			
	De	lete			
	Re	name			
	▶ Ex	port			
	👂 Co	onnection Paramet	ers		
	Cr	eate Enable/Disabl	le Tag	s	

[sc_opc_conn-para, 1, en_US]

♦ Check the parameters for the OPC connection.

Under **Run the server on another computer** the name of the redundant server must be entered. Via **Test Server** you can check if the OPC connection to the other WinCC computer is currently available. 7.1 System Overview

	×
OPC Connection	
Server type: OPC DA	
OPC Server Name	
OPCServer.WinCC.1	
Run the server on another computer:	Test Server
SCCCL88	
Read data from:     O Device	
Specify here the OPC server and computer you wish to acc	cess.
OK Abbrechen	Hilfe

[sc_opc_connection, 1, en_US]

♦ Click**OK** to close the dialog.

#### **Providing Global Actions**

- ♦ Copy the global action SicamSCC_DAF_RedunCheck.pas.
   You can find it in the SCC installation path: C:\Program files (x86)\Siemens Energy\SICAM\SCC\pas
- ♦ Paste the copied file into the **PAS** subfolder of your project folder. Example:

📙   🛃 🤿 🖛   PAS		- C	x c
File Home Share View			~ 🕐
$\leftarrow$ $\rightarrow$ $\checkmark$ $\uparrow$ $\blacksquare$ « Siemens » WinCCProjects » Buff	fRep_RedSCCCL67-68 → PAS	✓ Ö Search	PAS 🔎
	Name	Date modified	Туре
> 📌 Quick access	Sicam1703_RedundancyMaster.pas	5/11/2020 2:36 PM	PAS File
🗸 💻 This PC	SicamPAS_AlarmListFilter.pas	7/3/2010 5:32 AM	PAS File
> 🧊 3D Objects	SicamSCC_DAF_RedunCheck.pas	5/14/2020 3:51 PM	PAS File
> 🔜 Desktop	SicamSCC_PQA_SetTimeRange_MsgList	11/22/2016 3:15 PM	PAS File
> 🗄 Documents			
> 🕂 Downloads			
> 🎝 Music			
> 📰 Pictures			
> 📑 Videos			
> 🏪 Local Disk (C:)			
>  Network  Isc global paste, 1, en USI			

♦ You can find your copied action in the WinCC Explorer under Actions > Global Actions.

\land WinCC Explorer - C:\Users\Public\Documents\Siemen:	\WinCCProjects\BuffRep_RedSCCCL67-68\BuffRep_Re
File Edit View Tools Help	
🗈 🕞   🔳 🕨   🗶 🗎 🌆   🖽 🖂 🐼 🚺	i 🕯 ?
BuffRep_RedSCCCL67-68	Name
	Sicam1703_RedundancyMaster.pas
	SicamPAS_AlarmListFilter.pas
	SicamSCC_DAF_RedunCheck.pas
Menus and toolbars	SicamSCC_PQA_SetTimeRange_MsgList.pas
Text and graphics lists	
ICAM Dynamic Alarm Filter	
Tag Logging	
SICAM Network Manager	
SICAM IEC Wizard	
SICAM PAS Wizard	
SICAM Import/Export Wizard	
🚍 📲 Global Script	
⊡ <u>a</u> C-Editor	
Actions	
Global actions	
for clocal explorer 1 en US	

♦ Generate and save the action:



7.1 System Overview

Global Script C - BuffRep_RedSCCCL67-68.mcp : SicamSCC_DAF_RedunCheck.pas						
File Edit View Window Options	Help					
i 🗋 🖺 🖺 🕑 🌽 🐰 🗈 🙇 🕫	🛯 🗃 🏹 🦃 🎥 🗄 🔀 🖬 Germ	ian (Germany)				
Global Script C 🛛 🔻 🗭 🗙	BuffRep_RedSCCCL67-68. Compi	le (Umschalt+F8)				
oject functions	<pre>#include "apdefap.h"</pre>					
andard functions						
ternal functions	int gscAction( void )					
tions	- E					
Actions : SCCCL67	//***	**********				
Global actions	11					
Sicam1703 RedundancyMaster.pas	// Project:	SICAM				
CircamDAS Alarmi istEilter pas	<pre>// Department:</pre>	SI DG				
Gut ci coco DAE Data cha d	// Module:	SicamS				
SicamSCC_DAF_RedunCheck.pas	// Date:	2019-0				
SicamSCC_PQA_SetTimeRange_Msgl	11					
	11					
	//*********************	**********				

[sc_global_generate, 1, en_US]

To prevent the channel from transmitting messages at the start of the runtime before this action can control the DAF_Marker, the tag group SICAM_Admin_xxxx contains a **StartupDelayTime_xxxx** tag in the IEC and SNMP channels that allows you to set a delay time (start value in milliseconds) before starting data transfer after connecting to the remote sites. This delay time depends on the communication protocol, the number of devices connected, and the number of information points. Therefore, this variable must be set to a project-specific basis. By default, you can assume a value of 10 seconds (value of the variable: 10,000). In order to avoid delays for stand-alone systems without redundancy, the value is not pre-set.



[sc_startup_delay, 1, en_US]

#### Configuring the DAF

The DAF (Dynamic Alarm Filter) must do the filtering of the remaining duplicate messages (i.e. those that were not detected and removed due to the double timestamp). An internal **DAF_Marker_1** tag is used for this purpose.

For the DAF to prevent duplicate entries, filters must be created for all list entries, both binary and numeric. The following is an example of duplicate messages.



#### NOTE

For each of the 4 states of a double message, the **DAF_Marker_1** must be queried to the value **1**. This variable is set to 1 by the aforementioned global action if this computer is the redundancy leader. This means that on the leading computer it is 1, on the standby computer it is 0. This only logs the messages of the leading computer.

#### Components and Functions 7.1 System Overview

						SICAM SCC - dynar	nic alarm filter config	uration SIEM
alarm filter list	Configured filter criteria							
🙀 🖬 🛓	Value	Status	Time status	Event list	Alarm list	Notes		
hary	••••••01			✓		DAF_Marker_1=1		
Binary filter template	10			<b>√</b>		DAF_Marker_1=1		
Filter_for_DPs_DAF_Marker_1	00			~		DAF_Marker_1=1		
neric Numeric filter template	11			1		DAF_Marker_1=1		
ith alarm when ON								
larm when ON filter template								
ith alarm when OFF								
Jarm when OFF filter template								
		]						
		]						
	<ul> <li>♥ Ba X</li> <li>✓ Filter criterion settings</li> </ul>	]						
	+ D, X < N V 2 • Filter criterion settings Value						Notes	
	Image: Second section settings       Value       33     24       23     24		16	15		* 7	Notes	
	+     +     +     +     >       •     Filter criterion setting:       Value     24     23       •     •     •     •		16	15	] • • •	· · · · · · · · • • • • • • • • • • • •	Notes Comment:	DAF_Marker_1=1
	C N V      O     Filter criterion settings     Value     J1     Value     Status	• • • •	16 • • •	15 • • •		• • • • • • • • • • • • • • • • • • •	Notes Comment: Cause of transmission	DAF_Marker_1=1
	P Filter criterion settings     Value     31     24     23     status     imail     e	• • • •	16 •••	15 • • • igin • Initiator	· · ·	· • • • • • • • • • • • • • • • • • • •	Notes Comment: Cause of transmission Cause of transmission:	DAF_Marker_1=1
	Filter criterion setting:     Value     Status     Imaid     Status     Bay blocked     C		16 • • •	15 • • • igin igin Initiator Dely IEC conr	category:	· • • • • • • • • • • • • • • • • • • •	Notes Comment: Cause of transmission Cause of transmission: Additional cause:	DAF_Marker_1=1
	Filter criterion settings      Value     Status     Invalid     Status     Bay blocked     C	• • • •	16 • • •	15 • • • igin Initiator Only IEC conr	category:	* * * * * * * * 0 Ť	Notes Comment: Cause of transmission Cause of transmission: Additional cause:	DAF_Marker_1=1
	Image: Second	• • • •		15 • • • • igin Initiator Only IEC conr Origina	••••••••••••••••••••••••••••••••••••••	* * * * * * * 0 1 • • *	Notes Comment: Cause of transmission Additional cause: Internal user defined tage	DAF_Marker_1=1
	Filter criterion settings     Value     Status     Imaild     Explosed     Time status     Time status	• • • •		15 • • • • igin Initiator Only IEC conr Origina	category: rections: tor address:	· · · · · · · · · · · · · · · · · · ·	Notes Comment: Cause of transmission Additional cause: Internal user defined tags 1 DAF_Marker_1	DAF_Marker_1=1
	Filter criterion settings      Value     Status     Invalid     Status     Invalid     Invalid     Invalid     Invalid	• • • •	16 • • •	15 • • • • igin Initiator Only IEC conr Originar Value origin:	category: nections: tor address:	* * * * * * * * 0 1 * * * * * * * * 0 1	Notes Comment: Cause of transmission Cause of transmission: Additional cause: Internal user defined tage DAF_Marker_1 DAF_Marker_2	DAF_Marker_1=1
	Filter oriterion setting:     Value     Status     Invalid     Telecontrol blocked      Time status     Invalid     Daylight saving time	• • • •	) • • •	15 • • • • igin Initiator Only IEC conr Originar Value origin: Type of chang	category: rections: tor address:	* * * * * * * * 0 1 * * * * * * * 0 1	Notes Comment: Cause of transmission Additional cause: Internal user defined tage I DAF_Marker_1 DAF_Marker_2 DAF_Marker_2	DAF_Marker_1=1  DAF_Marker_1=1  DAF_Marker_1=1  DAF_Marker_1=1  DAF_Marker_1=1
	Filter criterion setting:     Value     Status     Imaild     Imaild     Imaild     Imaild     Imaild     Imaild     Daylight saving time     Imaild	• • • •	16 • • • 0	15 • • • • igin • Initiator Only IEC conr Origina Value origin: Type of chang	• • • • category: nections: tor address: ge:	• • • • • • • • • • • • • • • • • • •	Notes Comment: Cause of transmission Additional cause: Internal user defined tage I DAF_Marker_1 DAF_Marker_2 DAF_Marker_3	DAF_Marker_1=1

[sc_daf_config, 1, en_US]

In the mapping, assign all duplicate messages to this filter.
 Similarly, all other messages in the DAF must be handled.

#### Control files in IEC 104 and IEC 61850

For a trouble-free transmission, the following parameter settings are necessary in the control files **AKServ.ini** or **IEC61850.ini** which can be set via the corresponding Wizard using Expert View.

7.1 System Overview

- IEC 60870-5-104 Communication Connection
  - AKServ.ini
  - [DEFAULT]
  - Ini-Timeout=60

SICAM IEC 60870-5-10	94 Wizard							×
			S	IEMENS				
Device list	Mapping	Device settings	Global settings	Expert vie	CAM SCC - IEC104 d	ata n	napp	ing
+ 🗏 🗐 📮	✓ AKSe	rvDefault						
Single devices	Ignor	e confirmation/ter	mination	0				
IED_008	Frame	e throughput		0				
	Timeo	out startup		60				
	Inter (	COT		0				
	IVBit2	AS		0				
	Origin	nator address state	2	0				_
	Own	originator address		0	0			
	OV di	stract		1				
	Ring level indication			70				
	SSI_32	2bit send mode		2				-
	Timeout startup After the "Timeout startup" (after established connection) the communication driver will provide the HMI application with values. The "Timeout startup" value has to be bigger than the time needed for General Interrogation to ensure that only real process values are visualized and reported. Values/Ranges: Integer [#####]							
					Finish		Cance	el
Devices: 1 /	1	Use:	0 / 52	2 File:	D:\Import_Data\Single_Device	e*.xml		ad

[sc_SICAM_IEC_60870-5-104_Wizard_device_list, 1, en_US]

#### • IEC 61850 Communication Connection

- IEC61850.ini
- [GENERAL], Ini-Timeout=60, NoReStamping=1
- Ini-Timeout=60
- NoReStamping=1

👼 SICAM IEC 61850 Wizard		– 🗆 X
	SIEM	ENS
Device list	Mapping Device settings Global settings	SICAM SCC - IEC61850 data mapping
+ * * * = -	✓ General	▲
▲ Single devices	Server IP address	
SIP_J (SIP_7SL87)	Standby server IP address	
	Show "Additional cause"	1
Timeout startup		60
	Support substitution	1
	Fault records to SICAM DISTO	0
	No timestamping of GI data	1
	Own originator address	0
	Show originator address	1
	✓ RFC1006	<b>-</b>
	No timestamping of GI data No timestamping of received GI data with curr Values/Ranges: [0] disabled [1] enabled	rent time (default = 0).

[sc_SICAM_IEC_61850_Wizard_device_list_2, 1, en_US]



### NOTE

The newly added event list entries are not shown automatically after the start of the Runtime on the redundant SCC server. These entries are only added after the archive adjustment (system message number 1012209, **REDRT:<ComputerName>: Synchronization finished**) has been completed and the event-list picture is displayed once again.

## 7.2 Data Import

## 7.2.1 SICAM Import/Export Wizard

#### Overview

Use the SICAM Import/Export Wizard to import TEA-X export files from SICAM PAS/PQS or SITIPE. The functions of the SICAM Import/Export Wizard are to a large extent identical with those of other wizards. You can import several TEA-X files from different SICAM PAS/PQS projects. During the import process, the system automatically detects whether the data is an update for an existing project or whether it is an import of an additional station.

You can import the following formats:

- TEAX
- SXD
- SCD
- CID
- ICD
- IID
- XML

Only TEA-X files are exported.

The SICAM Import/Export Wizard can export individual stations from SICAM SCC and import them into a TEA-X file. This file can be edited with SITIPE and then also be imported into a new project.



#### NOTE

Use the SICAM Import/Export Wizard as the standard wizard. If required, you can start the SICAM PAS Wizard or the SICAM IEC Wizard from the context menu of the SICAM Import/Export Wizard.



[sc_SICAM_Import-Export_Import, 2, en_US]

#### Import – Step 1 of 4

- ♦ Click Next >.
- ♦ From the Select the import file selection box, select the file to be imported.

- or -

♦ Click ... to navigate to the file to be imported.

t SICAM Import/Export Wizard 1/4	_		×
	Import/update a station		
Superior State	Select the import file:		
	D:\temp\IEC61850soloPLUS.scd		
	Select or enter a station name:		
We have a second	IEC61850solo V		
	A new station "IEC61850solo" will be created.		
	Initialize:		
- 👔 👯 🛄 No / 🖓 🕅 🚺	Import SICAM graphic object library		
	Create SICAM text library		
The second second second	Create SICAM alarm system		
	Enable Report		
	Show all messages		
	Show warnings/errors only		
	< Back Next >	Cance	el

[sc_SICAM_Import-Export_Import_1, 2, en_US]

Depending on the import format selected, you can assign the station name yourself; otherwise, the name is predefined by the import file, see *Table 7-1*.
ta SICAM Import/Export Wizard 1/4	- 🗆 X
	Import/update a station
Maria and Andrews	Select the import file:
	D:\temp\G7SJ63_4_IP49.sxd
	Station name:
	Test_49
	Initialize:
	Import SICAM graphic object library
- 「「論」メリ 会々 ニート	
The second	
	Z Enable Report
	Show all messages
	<ul> <li>Show warnings/errors only</li> </ul>
N di sasi (Ma	
	< Back Next > Cancel

[sc_SICAM_Import-Export_Import_1_update_station, 2, en_US]

र्ग्ह्र SICAM Import/Export Wizard 1/4	- 🗆 X
	Import/update a station
M. Same	Select the import file:
	D:\temp\G7SJ63_5_IP50.teax
	Station name:
Il a case of the	Test_50
A A A A A A A A A A A A A A A A A A A	Initialize: Import SICAM graphic object library Create SICAM text library Create SICAM alam system
	Enable Report     Show all messages     Shaw warring common acts
	< Back Next > Cancel

[sc_SICAM_Import-Export_Import_1_update_station_teax, 1, en_US]

Table 7-1	File Formats and Station Names

Case	File format	Station name
To be created newly	*.teax	Always predefined
Update	*.teax	Always predefined
To be created newly	*.sxd	Name to be entered by the user
Update	*.sxd	Always predefined
To be created newly	*.scd, *.xml, *.ied, *.icd, *.iid	Name to be entered by the user
Update	*.scd, *.xml, *.ied, *.icd, *.iid	The user must enter a name or select a name from a drop-down list box



## NOTE

When configuring the SICAM SCC link in TOOLBOX II, keep the following in mind:

In principle, the "path" is stored in the hierarchy/group fields up to the device, in the "..." text and processinformation fields the process data-point itself is stored.

The IEC Wizard has adopted the **Variable name**, if any, as a complete WinCC variable name, using the group name only as a "subfolder". If the **Variable name** is empty, the IEC Wizard assembles the WinCC variable name from **Variable group** and **Process information** (variable group + "_" + process information). The Import/Export Wizard creates the WinCC variable name from **Variable group** and **Process information**. This does not use the **Variable name** property in the TOOLBOX II SCC link.

If the SICAM SCC link from the TOOLBOX II library is used, the fields are pre-populated with appropriate formulas.

The archive (TagLogging) has the same rules for the hierarchy and info names, but the maximum string length is shorter.

For the Alarm Logging system, the message group and the message text can be freely assigned and serve the user in operation only to identify the information.

## Import – Step 2 of 4

- ♦ Click Next >.
- ♦ Select the connection to be imported and then click **Next** >.

SICAM Import/Export Wizard 2/4			_		×
	Select your SCC to import				
	Name nb2viec0cg 61850	IP address 127.0.0.1			
P 13 P					
S I IN NO					
	< Back	Next :	>	Cano	el :

[sc_SICAM_Import-Export_Import_2, 1, en_US]

## Import – Step 3 of 4

The data is analyzed and the import progress is shown.

 $\diamond$  Click Next >.

The import starts.

7.2 Data Import



[sc_SICAM_Import-Export_Import_3, 1, en_US]

The import is initiated. The import process can take some time depending on the size of the data to be imported.

## Import – Step 4 of 4

A summary is shown at the end of the import process.



[sc_SICAM_Import-Export_Import_4, 1, en_US]

♦ Click Finish.

#### **Initializing an Empty Project**

You can create a simple, empty SICAM project.

 $\diamond$  Click **Next >**.

In contract to the import process, you cannot select a file here and the station name is also not available.

 $\diamond$  Click Next >.

A SICAM project including all text blocks and settings is available in WinCC. You can further configure this project.

7.2 Data Import



[sc_Initialize_project, 2, en_US]

### Station Conversion to the TEA-X Format

A project created with an IEC Wizard must be converted into a valid TEA-X project. This step must only be carried out once for a project created with an IEC Wizard or a PAS Wizard.



[sc_station_conversion, 2, en_US]

**Convert station to TEA-X** is only available if there is at least 1 station that can be converted. Such are stations that have been imported via PAS Wizard or IEC Wizard.

♦ Click Next >.

SICAM Import/Export Wizard 1/4		-		×
	Station conversion			
Maria and Andrews	Station name:			
	PAS_Station Test_48			
	Initialize:			
The Astrony	Create SICAM text library			
	<ul> <li>Enable Report</li> <li>Show all messages</li> <li>Show warnings/errors only</li> </ul>			
	< Back Nex	t >	Cance	

[sc_station_conversion_1, 1, en_US]

Select the station to be converted.
 For a PAS station, you must first create a TEA-X export file equivalent to PXD on this station. During conversion, specify this new TEA-X file as the import file.

🚼 SICAM Import/Export Wizard 1/4	- 🗆 X	:
	Station conversion	
	Select a station name:	
	PAS_Station V	
	Select the matching TEA-X file.	
The second states of the second se	D:\temp\PXD-Files\43_SmallCC.teax	
	Convert station "PAS_Station" into TEA-X format.	
	Initialize:	
- Tel 12 - Le 12 - Le 18 🚺 - Le	Import SICAM graphic object library	
m. h. h. h. h.	Create SICAM text library	
The second second	Create SICAM alarm system	
	✓ Enable Report	
Visco and all in the second seco	Show all messages	
	Show warnings/errors only	
	< Back Next > Cancel	

[sc_station_conversion_1_teax, 1, en_US]

♦ Afterwards, proceed in the same way as for a standard import process.

🔚 SICAM Import/Export Wizard 2/4			—		$\times$
	Select your SCC to import				
	Name nb2viec0cq 61850	IP address 127.0.0.1			
K					
	< Back	Next	>	Cano	el

[sc_station_conversion_2, 1, en_US]

### Export

The SICAM Import/Export Wizard can export individual stations from SICAM SCC to a TEA-X file. This file can be edited with SITIPE and then imported into a new project.

## ♦ Select Export and click Next >.

ta SICAM Import/Export Wizard	- 🗆 ×
	Select a task
	O Import
	Export
PALL SALE BALL	O Delete station
	O Initialize project
	○ Convert station to TEA-X
5 M M	Only stations previously imported by this wizard can be exported.
	< Back Next > Cancel

[sc_SICAM_Import-Export_station_1, 2, en_US]

**Export** is only available if there is at least 1 station that can be exported. This is valid for stations that had been imported directly or indirectly via TEA-X Wizard (now "Import/Export Wizard"). Such are stations that have **not** been imported via PAS Wizard or IEC Wizard.

Converted stations (siehe Station Conversion to the TEA-X Format, Page 258) can also be exported.

## **Deleting a Station**

♦ Select Delete station.

र्ग्स SICAM Import/Export Wizard	- 🗆 X
SICAM Import/Export Wizard	Select a task  Import Export Delete station Initialize project Convert station to TEA-X
	Only stations previously imported by this wizard can be deleted. 

[sc_SICAM_Import-Export_select_Delete, 1, en_US]

**Delete Station** is only available if there is at least 1 station that can be deleted. This is valid for stations that had been imported directly or indirectly via TEA-X Wizard (now "Import/Export Wizard"). Such are stations that have **not** been imported via PAS Wizard or IEC Wizard.

Converted stations (siehe Station Conversion to the TEA-X Format, Page 258) can also be deleted.

- ♦ Click Next >.
- Select the station to be deleted and click Next >.
   The station is deleted.

7.2 Data Import

SICAM Import/Export Wizard 1/2		_		×
SICAM Import/Export Wizard 1/2	Select your station to delete Station name PASCC_TMP SNMP Test_48 Test_49 Test_50			×
	< Back Ne	əd >	Cance	9

[sc_SICAM_Import-Export_delete_station, 1, en_US]

## 7.2.2 SICAM Wizard

Use the **SICAM PAS Wizard** for the connection of SICAM PAS/PQS stations. To connect SICAM RTUs, IEC 61850 and IEC 60870-5-104 devices, you use the **SICAM IEC Wizard**.

This section describes the proceeding with the SICAM PAS Wizard as an example.



#### NOTE

Differences between the use of the two SICAM Wizards are described in chapter 3.2.4 Initializing a WinCC Project.

## Initializing the project

The SICAM PAS Wizard supports you in initializing your WinCC project. It creates a new station in the project or updates an existing station. To do this, it performs the following tasks:

- Creating SICAM PAS/PQS-specific structure tags
- Importing tags from SICAM PAS/PQS
- Creating administrative tags for the SICAM PAS/PQS system
- Creating the SICAM PAS/PQS-specific alarm system
- Importing alarms/messages from SICAM PAS/PQS
- Importing the SICAM PAS/PQS graphic object library into the project
- Creating measured-value and metered-value archives for SICAM PAS/PQS process data
- Creating the SICAM PAS/PQS-specific text library
- Adding the communication driver

### **Creating structure tags**

The structure tags are required for the data exchange with automation systems or devices. They include the complete structure of a structured tag in SICAM SCC.

The different tags are assigned individual structure tags (see A.1 Structures).



## NOTE

Be aware of the following when upgrading the version of WinCC projects created with a predecessor version:

The structure types of existing projects are automatically changed to Version 9.00. Existing process tags are not changed.

To convert existing tags to the new structure types:

- Delete the process tags using the SICAM PAS Wizard.
- Import the process tags using the SICAM PAS Wizard.

Alternatively, you can adapt existing process tags before the first import using the SICAM SCC 9.00 Wizard as described in chapter 14.8.2 Editing Structure Types.

#### Importing tags

The SICAM PAS Wizard imports the tags from a file provided by SICAM PAS/PQS. This file has the extension **PXD** (e. g. Station1.PXD).

The tags are automatically assigned to the corresponding structure type. Each tag includes several elements. Examples of elements for the monitoring direction:

- the current process value
- the status (e. g. not updated, invalid, overflow, etc.)
- the tag type
- the cause (e. g. spontaneous, periodic, polled, ...)
- the additional cause
- the counters which are counted upon a tag change

The name of the tag imported into SIMATIC WinCC corresponds to the name specified in SICAM PAS/PQS for the tag management of SICAM SCC. Special characters are already replaced by SICAM PAS/PQS UI – Configuration. Any remaining tags will be replaced by the SICAM PAS Wizard during the import process (see appendix *A.3 Character Conversion*).

Additionally, tags are structured in groups. The name of a group corresponds to the hierarchical name without considering the last hierarchical level.

#### Creating administrative tags

The SICAM PAS Wizard creates internal and external SICAM SCC tags. Internal tags are stored in a **SICA-MAdmin** group. External tags are stored in a channel-specific **SICAMAdmin_xxx** group.

#### Creating an Alarm Logging system

The SICAM PAS Wizard allows you to create an alarm system under SICAM SCC that meets the requirements of a SICAM PAS/PQS system.

The alarm system consists of alarm message blocks, message classes, templates for alarm lists (Alarm Logging templates) and texts. The related SICAM-specific objects for

- the event list
- the alarm list
- the protection message list

can be viewed in the Graphics Designer under View > Library > Project Library > Alarm Logging Templates > WinCC V7.x.

Specific list templates are available for the connection to SICAM PAS/PQS and SICAM RTUs/IEC 61850/ IEC 60870-5-104.

## Importing messages

The SICAM PAS Wizard imports messages from the PXD file.

The name of the message imported into SICAM SCC corresponds to the name configured in SICAM PAS/PQS UI – Configuration.

Additionally, each imported message has a unique number. The SICAM PAS normalization DLL is assigned, the value text group 0 is assigned, the specific properties are defined, and the message class **SICAM Message EM** or **SICAM Message DM/WM/RM** is assigned.

The message number is composed of the project ID * 10,000,000 and the value ID.



## NOTE

Make sure that you use unique project IDs when importing several stations. You can configure the project ID in the SICAM PAS/PQS or SICAM TOOLBOX II project. Project IDs starting with 10 are assigned automatically during the SCD import, see note in chapter *Table 7-15*.

### Importing the SICAM graphic object library

The SICAM PAS Wizard loads the SICAM graphic object library into the current project. When importing the SICAM graphic object library, administrative tags are created, and the SICAM functions (C scripts) are copied into the project.

### Creating an archiving system

Process data from SICAM PAS/PQS can be archived in the archiving system. The SICAM PAS/PQS archiving system comprises:

- a process value archive for measured values
- a process value archive for metered values

The archives are created as sequence archives on the hard disk of the PC on which SICAM SCC is installed. Their size is only limited by the capacity of the hard disk.

#### Starting the Wizard

Start the SICAM PAS Wizard in the WinCC Explorer.

To start the SICAM PAS Wizard:

♦ In the WinCC Explorer, double-click SICAM PAS Wizard.

Demo_SCC	Name	Туре
Tag Management		
Menus and toolbars		
Text and graphics lists		
Tag Logging		
SICAM PAS Wizard		
SICAM TEA-X Wizard		
Global Script		
Text Library		
Text Distributor		
Weer Administrator		
Cross-Reference		
Coad Online Changes		
Redundancy		
User Archive		
I lime synchronization		
Horn		
Picture Tree		
Lifebeat Monitoring		

MinCCExplorer - E:\WinCCProjekte\Demo_SCC_V900_WinCC_V74\Demo_SCC.mcp

SICAM PAS Wizard



## NOTE

While the SICAM PAS Wizard is active, do not start any editors in SIMATIC WinCC. Otherwise, the connection of the wizard to a component will be aborted, and errors can occur during the import/update process.

The SICAM PAS Wizard starts.





#### SICAM PAS Wizard

♦ Click Next to continue.

## Entering the station name

- ♦ To add a new station to the project, select Create new station in project under Select station.
- ♦ Enter a unique station name into the entry field (e. g. Station1). The station name is suggested as the name for the logic link in the SICAM PAS PROTOCOL SUITE.



## NOTE

- If you do not want to create a new station, but update an existing station, proceed as follows:
- Click Select existing station.
- Select a station from the list.

To perform an update, the import file must originate from the same SICAM PAS/PQS project.

#### **Selecting parameters**

 Select the desired special-character replacement from the drop-down list box. This selection ensures that the SICAM PAS Wizard replaces those special characters in tag names which cannot be used by SICAM SCC by SICAM SCC-conforming characters.



## NOTE

When editing old projects, you must select an option for the replacement of special characters which complies with the origin of the diagrams used in the project.

If special characters are replaced incorrectly, different tag names can be created, which could possibly cause problems concerning interconnections in these diagrams.

Select SICAM trace window output in order to ensure that the SICAM PAS Wizard starts the SICAM PAS trace window. To provide a concise overview, you can specify that only warnings/errors are shown in the list.

ta SICAM PAS Wizard 1/5		×
General WinC Selec	I Settings C Project: 5-W10\WinCC_Project_Demo_SCC_1\Demo_SCC.mcp t Station : Create new station in project SubstationSouth	
Parar	Select existing station         Image: station         <	
	< Zurück Weiter > Abbrech	nen

[pascc312, 1, en_US]

Figure 7-7 Entering the station name and selecting parameters

 $\diamond$  Click Next to continue.

#### Importing station data and selecting functions

In the following dialog, you can specify which components the SICAM PAS Wizard is to import from SICAM PAS/PQS to SICAM SCC.

- Select Create SICAM components in project to provide the prerequisites for the use of SICAM SCC components in multi-client projects on the client PC or to create SICAM PAS/PQS extensions in the WinCC project without import data from SICAM PAS/PQS.
- ♦ ♦ Select the Import/Update item. The components are now imported into the new station.
- Enter the complete path in the SICAM PAS/PQS data directory (e. g. ...\station1). To do this, click the ... button to open the path selection window.
- Select the file (e. g. station1.PXD) holding the corresponding SICAM process tags from the drop-down list box.

- ♦ Select SICAM process tags.
- Select **SICAM archives** to create the archives in your WinCC project.
- ♦ Select SICAM PAS messages.



## NOTE

When updating an existing station, all entry fields are set to default values. To perform an update, the import file must originate from the same SICAM PAS/PQS project.

SICAM PAS Wizard 2/5		×
Import Settings	specific to the station	
Station name C Create S C Import / SICAM F D:\Impo WinCC C Delete Select Funct SICA SICA SICA	:: Substation South CAM components in project Jpdate AS data folder: t_Data  xd vd V Process Tags M Archives M Messages	
	< Zurück Weiter > Abbreche	n

[pascc313, 2, en_US]

Figure 7-8 Defining the path and the name of the import components

♦ Click Next.



## NOTE

If Delete is selected in dialog 2/5 of the SICAM PAS Wizard, the dialogs 3/5 and 4/5 will be skipped.

### Setting station parameters

The station parameters can be set in the dialog shown below.

The entries for **Channel unit** and **Logical connection** are set by default at SICAM PAS/PQS and can be applied for the first station without changes.

SICAM PAS Wizar	d 3/5			×			
	Import Settings specific to	the station					
	Station name :	Substation South					
	Station parameters :						
	Channel Unit:		PAS Data Server	<b>•</b>			
	Logical Connection	1:	SubstationSouth	<b>_</b>			
			< Zurück W	eiter > Abbrechen			

[pascc314, 2, en_US] Figure 7-9

7-9 Setting Station Parameters for SICAM PAS/PQS



## NOTE

When connecting SICAM PAS/PQS systems with different versions, select the corresponding **Channel unit** in this dialog.

♦ Click Next.



[pascc320, 1, en_US]

Figure 7-10 Note regarding connection parameters

No connection parameters need to be defined when connecting a **SICAM PAS/PQS** station Version 8.00 or later. The connection parameters from the SICAM PAS/PQS import file are applied. For older SICAM PAS/PQS versions, the connection parameters are pre-assigned with default values.

The connection parameters must correspond to the values defined in SICAM PAS/PQS. Check the connection parameters, see 3.2.5 Connection Parameters.



## NOTE

During a data import using the SICAM Wizard, the manually changed connection parameters are overwritten with the parameters from the import file. For this reason, the connection parameters must be checked after the data import.

### Initializing the project

In the following dialog, you can specify the initialization of the WinCC project.

- Select the Import SICAM graphic object library option in order to import the SICAM PAS/PQS graphic object library (including ActiveX Controls) and the SICAM PAS/PQS administrative tags into the WinCC project.
- ♦ Select the Create SICAM text library option to create the text library in the WinCC project.



## NOTE

If the **Create SICAM alarm system** option is selected, the **Create SICAM text library** option must also be selected during the first run.

♦ Activate Create SICAM alarm system to create the alarm system in the WinCC project.

SICAM PAS Wizard 4/5	×
Initializations : Initializations : Initializations : Create SICAM graphic object library Create SICAM text library Create SICAM alam system	×
< <u>B</u> ack	Next > Cancel
[pascc315, 1, en_US]	

Figure 7-11 Defining the project initialization

♦ Click Next.

### Summary

The following dialog shows a summary of the previously defined settings. Check them for correctness.



## NOTE

If one of your settings proves to be incorrect, click **Back** to return to the previous dialog and correct it. The previous dialog opens and you can correct your settings.

- WinCC Project: \\V75-W10\WinCC_Project_Demo_SCC_1\Demo_SCC.mcp - Select Station :	
<pre>\\V75-W10\WinCC_Project_Demo_SCC_1\Demo_SCC.mcp - Select Station :</pre>	
- Select Station :	
New station : Substation South	
Replace Special Characters : conform to SICAW from VS.X.     SICAM Repeater Output	
- SICAM Reporter Output.	
* Import Settings specific to the station	
- Import from SICAM PAS data folder:	
D:\mport Data	
- Select Function :	
SICAM Process Tags : WinCC.pxd	
SICAM Archives : WinCC.pxd	
SICAM Messages : WinCC.pxd	
- Channel Unit : PAS Data Server.	
- Logical Connection : SubstationSouth.	
* Import Settings specific to the project	
Import Settings appendix to project	
<ul> <li>Information and a state of the state of the</li></ul>	
Create SICAM graphic object library.	
	Replace Special Characters : conform to SICAM from V5.x.     SICAM Reporter Output.      Import Settings specific to the station     Import from SICAM PAS data folder:     D:\Import_Data     Select Function :         SICAM Process Tags : WinCC.pxd         SICAM Archives : WinCC.pxd         SICAM Messages : WinCC.pxd         SICAM Messages : WinCC.pxd         SICAM Messages : WinCC.pxd         SICAM connection : SubstationSouth.      Import Settings specific to the project

[pascc316, 1, en_US] Figure 7-12 Checking the settings

♦ Click Finish.

The SICAM PAS Wizard now executes the selected steps.

In the **Report** window, you can observe the processing and see potential error and warnings.

## Viewing the report

As soon as all steps have been completed, you can view the report.

- ✤ To do this, select the **Overview** tab in the **Report** window. The number of errors and warnings is indicated in the **Quit:** row under Messages.
- ♦ Click Close to close the report.

≣ Report — □							
📑 Export 🔮 Print preview 😽 Delete 🔖 Delete all	尹 Export 🗳 Print preview 😼 Delete 🖏 Delete all						
SICAM SCC Runtime Data Server-Topo_PlugIn SICAM SCC Graphics Designer Add-in	SICAM PAS Wizard	4 1					
Messages		^					
Begin: Initialize SICAM graphic object library     Import/Update; OK: Copy file - destination \\SCCDOCU11\WinCC_Project_myNewProject\Library\library.p     Import/Update; OK: Copy file - destination \\SCCDOCU11\WinCC_Project_myNewProject\Library							
<ul> <li>Begin: Create compatibility key script</li> <li>Scripts; Generating compatibility key script ok</li> </ul>							
End: Create compatibility key script		~					
<		>					
		.::					

[pascc317, 1, en_US] Figure 7-13 Viewing the report

i

## NOTE

If the **Report** indicated error or warnings, you should save these messages for viewing and editing them later.

If errors have occurred, the SICAM PAS Wizard requests you to delete the components effected during the next run.



## NOTE

The SICAM PAS Wizard saves its messages in the GWLog.txt file under the path of the project (e.g. ...\project1).

The SICAM PAS Wizard overwrites this file upon each run. Save this file if required.

# 7.2.3 Configuring an IEC 60870-5-104 Connection During Runtime

Online configuration for the IEC60870-5-104 connection is only supported by SICAM IEC Wizard. To avoid a shutdown of the SICAM SCC Runtime in the case of minor configuration changes, an IEC 60870-5-104 station can be extended in SICAM SCC in online mode. Devices and individual items of information can be added and certain parameters can be modified.

## Prerequisites/preparatory steps

In order to be able to extend an IEC 60870-5-104 station in online mode, at least 1 device with at least 1 item of information must be configured.

Please note that only existing IEC 60870-5-104 stations can be extended during runtime. In order to be able to add an IEC 60870-5-104 station in online mode, an empty dummy station including at least the administrative SICAM SCC tags must first be created in offline mode.

## Restrictions

Please note the following restrictions as compared to configuration in offline mode:

- It is not possible to add new WinCC IEC 60870-5-104 stations.
- Configured devices cannot be deleted.

- Configured information cannot be deleted.
- For tags which have already been mapped in the Tag Management the following properties cannot be modified in online mode:
  - Tag name
  - Tag group
  - Tag type
  - Mapping in TagLogging or AlarmLogging
  - Linking indication and command tags
- To configure PAS and IEC 61850 stations the runtime must still be stopped first.
- Redundant systems cannot be configured during runtime.

#### Creating a dummy station for future extensions

To create a dummy station:

♦ Start the SICAM IEC Wizard.

The name cannot be changed later.

- $\diamond$  Create an XML import file with 1 device without data points and the ASDU matching the station.
- ♦ Import this file and configure the **ComFault** or **OprReady** information in the Tag Management.

You can now extend your dummy station during runtime.

This imported dummy device must not be deleted when the station is extended later on.

### Converting legacy projects created with earlier SICAM SCC versions

As a preparatory step you must convert existing projects created with a SICAM SCC version earlier than V8.03 HF1.

Make sure you call up the SICAM IEC Wizard for every IEC 60870-5-104 station with the same import data used during the last import and re-import the graphic object library.

Note that the re-import of the SICAM graphic object library must first be activated in the project-specific settings of the SICAM IEC Wizard.

## 7.2.4 SICAM IEC 104 XML Creator

Use the **SICAM IEC104 XML Creators** to create a parameter file (e.g. Rtu1.xml) for a SICAM RTU or another device with an IEC 60870-5-104 communication connection. This XML file can be imported into your project using the SICAM IEC Wizard. All the parameters required for import are included in the parameter file. A separate parameter file must be created for every RTU and every device. Please note that Microsoft Office is required to create and edit the parameter file.

## 7.2.4.1 General Procedure

#### Installation

To use the SICAM IEC104 XML Creator, the SICAMIEC104XMLCreator.dll must exist and be registered on the computer.

• Computer with SICAM SCC The SICAMIEC104XMLCreator.dll is registered automatically upon the installation of SICAM SCC.

## • Computer without SICAM SCC

On a computer with no SICAM SCC installed the **SICAMIEC104XMLCreator.dll** must be registered separately.

As a prerequisite for registration **.NET Framework ab V2.0** must have been installed. Please note that administrator rights are required to perform the registration.

#### To register the SICAMIEC104XMLCreator.dll:

To register the SICAMIEC104XMLCreator.dll, execute the SICAMIEC104XMLCreator_reg.bat file with administrator rights. To do this, right-click the SICAMIEC104XMLCreator.dll and select Execute as administrator from the context menu.

The batch file must not be located on a network drive or a substituted drive.

#### How to proceed

To create the parameter file (XML file) perform the following 3 steps:

- Save the Excel template file SICAM_IEC104_XMLCreator.xltm included in the scope of delivery as an XLSM file.
- Enter the parameters of your device in the **XLSM** file, e.g. Rtu1.xlsm.
- Create the parameter file (XML file) from the XLSM file.

For a detailed description of the procedure refer to 7.2.4.3 Creating a Parameter File.



## NOTE

You can edit Excel files using Excel versions 2007, 2010, or 2013. Furthermore, the 32-bit version of Microsoft Excel must be installed.

#### XLSM file

The entries in the XLSM file are divided as follows:

- Communication parameters, lines 4 to 7
- Data points and their parameters, from line 11

The XLSM file consists of 3 sheets:

- CreatelEC104Variables
  - This sheet includes the actual parameters.
- Help This sheet includes help texts.
- Example

This sheet provides an example of a SICAM RTU with 2 LRUs and their data points.

### 7.2.4.2 Parameters and Data Types

Table 7-2	Communication	parameters
-----------	---------------	------------

Parameter	Description	Default value / Value range	Recom- mended value
RTU Name	Name of the SICAM RTU		
Timeout response t1	Monitoring time for transmitting or testing the APDU	<b>15</b> 1 to 255 s	
Timeout transmit acknowledge t2	Monitoring time for acknowledgment in case of a missing data message	<b>10</b> 1 to 255 s	t2 < t1

Parameter	Description	Default value / Value range	Recom- mended value
Test frame period t3	Monitoring time for the transmission of S frames in case of an extended idle time	<b>20</b> 1 to 255 s	t3 > t1
Transmit window	Maximum difference between the sequence number received and the transmission of the status tags	<b>12</b> 1 to 32767 APDU	
Receive window (w)	Acknowledgment takes place after the receipt of w frames in I format at the latest.	8 1 to 32767 APDU	w < 2/3 k
TCP/IP address	TCP/IP address		

The values indicated in **bold** are default values in accordance with the EN 60870-5-104 standard.

## **Data Point Parameters**

Parameter	Description	Value range
LRU name	Name of the LRU	
ASDU Service data unit of the application layer		1 to 2047
Information name	Name of the item of information	
Data type	IEC 104 data type	
IOA	Information address	1 to 16777214
Feedback link	Only for commands: Information name of the corresponding message	
SCC Tag name	Name of the SICAM SCC tag	

Table 7-3 Data Point Parameters



## NOTE

The information address is not checked.

Please note that you are responsible for the correctness of all parameters.

## IEC 104 Data Types

SP (TI 30)	Single-point indication with time stamp CP56Time2a
DP (TI 31)	Double-point indication with time stamp CP56Time2a
ST (TI 32)	Tap position indication with time stamp CP56Time2a
BO (TI 33)	Bit pattern indication, 32 bits, with time stamp CP56Time2a
ME_TD (TI 34)	Measured value, normalized value with time stamp CP56Time2a
ME_TE (TI 35)	Measured value, scaled value with time stamp CP56Time2a
ME_TF (TI 36)	Measured value, shortened floating point number with time stamp CP56Time2a
IT (TI 37)	Metered value with time stamp CP56Time2a
SC (TI 45)	Single command
DC (TI 46)	Double command
RC (TI 47)	Regulating step command
BO (TI 51)	Bit pattern, 32 bits
SE_NA (TI 48)	Set-point control command, normalized value
SE_NB (TI 49)	Set-point control command, scaled value
SE_NC (TI 50)	Set-point control command, short floating point number



## NOTE

The corresponding type identifier with time (TI > 30) must also be configured for data types without time (TI < 30).

## 7.2.4.3 Creating a Parameter File

After the installation of SICAM SCC the template file is available in the following directory: **..\Programme \Siemens Energy\SICAM\SCC\misc\IEC104Configuration**.

To create a parameter file:

♦ Open the SICAM_IEC104_XMLCreator.xltm template file in Microsoft Excel.

4	А	В	С	D	E	F	G	Н	1	J	K
		Create XML file								SIEMENS SICAM SCC	
-		Trucout	Terrorent	Test				Turnerali	Dessive		
2		Ilmeout	limeout	Test frame				Transmit	Receive		
3	RTU Name	response t1	transmit acknowledge t2	period t3				window	window (w)	TCP/IP Address	to XML
4										1.1.1.1	4
5	City	15	10	20				12	8		
6											
0											
9										Number of datapoints added to XML file:	20
		• • • • • •		- · · · · · · · · · · · · · · · · · · ·							
10	LRU name	ASDU	Information name	Data type	IOA1	IOA2	IOA3	IOA	Feedback link	SCC Tag name	to XML
11	East	1	OperatingState	SP (TI 30)	2	0	0	2		City_East_OperatingState	4
12	East	1	RemoteControl	DP (TI 31)	4	0	0	4		City_East_RemoteControl	4
13	East	1	StepPosition	ST (TI 32)	105	0	0	105		City_East_StepPosition	4
14	East	1	BitPattern	BO (TI 33)	208	0	0	208		City_East_BitPattern	4
15	East	1	Meas1	ME_TD (TI 34)	116	0	0	116		City_East_Meas1	4
16	East	1	Meas2	ME_TE (TI 35)	118	0	0	118		City_East_Meas2	4
17	East	1	MeasFloat	ME_TF (TI 36)	120	0	0	120		City_East_MeasFloat	4
18	East	1	SingleCommand	SC (TI 45)	234	3	0	1002		City_East_SingleCommand	4
19	East	1	DoubleCommand	DC (TI 46)	236	3	0	1004		City_East_DoubleCommand	1
20	East	1	Meter1	IT (TI 37)	176	4	0	1200		City_East_Meter1	× .
21	East	1	SetPoint	SE_NC (TI 50)	242	3	0	1010		City_East_SetPoint	4
22	West	2	StepPosition	ST (TI 32)	105	0	0	105		City_West_StepPosition	4
23	West	2	BitPattern	BO (TI 33)	208	0	0	208		City_West_BitPattern	4
24	West	2	Meas1	ME_TD (TI 34)	116	0	0	116		City_West_Meas1	4
25	West	2	Meas2	ME_TE (TI 35)	118	0	0	118		City_West_Meas2	4
26	West	2	MeasFloat	ME_TF (TI 36)	120	0	0	120		City_West_MeasFloat	4
27	West	2	SingleCommand	SC (TI 45)	234	3	0	1002		City_West_SingleCommand	4
28	West	2	DoubleCommand	DC (TI 46)	236	3	0	1004		City_West_DoubleCommand	×
29	West	2	Meter1	IT (TI 37)	176	4	0	1200		City_West_Meter1	4
30	West	2	SetPoint	SE_NC (TI 50)	242	3	0	1010		City_West_SetPoint	4
31	West	3	SingleCommand	SC (TI 45)	234	3	0	1002		City_West_SingleCommand	×
32	West	2	DoubleCommand	DC (TI 46)	236	3	0	1004		City_West_DoubleCommand	×
33	West	2	Meter?	IT (TI 37)	176	4	0	1200		City_West_Meter?	×

[excel-datei, 1, en_US]

Figure 7-14 VSICAM_IEC104_XMLCreator.xltm template file

- ♦ Save this file e.g. as Rtu1.xlsm (Excel file with macros). You can use this file to define the parameters of your SICAM RTU.
- ♦ Enter the parameters for your SICAM RTU.

Enter at least the following parameters:

- Name of the SICAM RTU
- TCP/IP address
- 1 data point with its parameters
- 1 LRU

The example in the screenshot above shows the parameters defined for 1 SICAM RTU with 2 LRUs (East, West).

Note the entries in the SCC Tag name column: This column shows the tag names indicated later in SICAM SCC. The following characters must not be used for parameters consisting of texts:

- Blank " \$ % ' * :? @ \
- Make sure you also check which characters are permitted in your destination system.
- Click Create XML file to create the parameter file, e.g. Rtu1.xml. It may be necessary to activate macros before clicking this button.

The XML file always has the same name as the Excel file and is saved in the directory in which the Excel file has been opened. All incorrect data points which were not exported to the Rtu1.xml file are listed in an additional **Rtu1.log** file.

- ♦ Create a separate parameter file for each SICAM RTU.
- ♦ Import the parameter file into your project via the **WinCCExplorer** using the **SICAM IEC Wizard**.

# 7.3 SICAM Communication Connection - Tag Management

SICAM SCC makes available the following SICAM communication connections:

- SICAM PAS PROTOCOL SUITE (SICAM PAS channel DLL) for the connection of SICAM PAS stations For the connection of older SICAM PAS systems see 10 Different SICAM PAS Versions.
- SICAM IEC COMMUNICATION SUITE (SICAM IEC channel DLL) for the connection of SICAM RTUs, IEC 61850 and IEC 60870-5-104 devices

# 7.3.1 SICAM PAS PROTOCOL SUITE

## Overview

The **SICAM PAS PROTOCOL SUITE** provides for the connection of SICAM SCC to the SICAM PAS Full Server. Besides this, it controls this process data connection.

The (process) connection between SICAM PAS and SICAM SCC or SIMATIC WinCC is ensured by the SICAM PAS PROTOCOL SUITE. The SICAM PAS channel DLL logs on to the SICAM SCC proxy driver during runtime in order to exchange process information.



[pascc403, 1, en_US]

Figure 7-15 SICAM PAS PROTOCOL SUITE in the WinCC Explorer

## Performance characteristics

The SICAM PAS PROTOCOL SUITE has the following performance characteristics:

- Event-controlled update of the process image
- Time stamps from the process via raw data tags and the SICAM PAS normalization DLL
- Automatic start and stop via SIMATIC WinCC and SICAM PAS UI Operation
- Connection of different or redundant SICAM PAS projects parallel to SIMATIC WinCC with automatic switchover in case of faults

## Tasks

The SICAM PAS PROTOCOL SUITE performs the following tasks:

- Checking the consistency of the parameter settings
- Connect to the SICAM SCC proxy driver
- Forwarding of display and indication tags to SIMATIC WinCC
- Forwarding of commands to SICAM PAS
- Monitoring of the connection to the SICAM PAS system
- Control of SICAM PAS communication components
- Substitution of values
- Control of switching authorities

### Compatibility key

A compatibility key is used in order to ensure that the project version of SICAM PAS is compatible with the project version of SICAM SCC. This key is checked by a script upon the activation of the runtime operation. If an error is detected during this check, the WinCC Runtime is stopped and an error message is displayed. The compatibility key is irrelevant for SICAM RTUS.

For projects with an extremely large number of process tags the compatibility key upon the start-up of WinCC Runtime can only be checked after several seconds. To prevent the operation of the project until the compatibility key has been checked, a picture must be configured which is positioned on top of the process images. This picture is switched off depending on the result of the compatibility key check. To do this, compare the external and internal CompKey... tags of the corresponding SICAM PAS connection. Place a picture window on top of the start picture which you hide if the process values of the CompyKey... tags are identical.

#### Tags

The SICAM PAS PROTOCOL SUITE logs on to the SICAM SCC proxy driver in order to poll the required tags. Indication tags and display tags for the representation of process diagrams are polled during this process. Additionally, system-internal tags (e. g. the project ID, compatibility key) are required from the SICAM PAS Full system.

The distinction between a **display tag** and/or an **indication tag** is based on the specific tag information created by the SICAM PAS Wizard during the creation of the tags. Furthermore, the ValueID of the corresponding tags is included in this specific tag information. Via the ValueID, the SICAM PAS PROTOCOL SUITE can perform an assignment between SICAM PAS tags and WinCC tags.

- SIMATIC WinCC uses **display tags** for process visualization.
- Unlike the display tags, the **indication tags** are not determined by the process diagram.

## Licensing

With regard to the SICAM PAS PROTOCOL SUITE a distinction is made between 2 licenses, i.e. the license for SICAM SCC - Configuration and the license for SICAM SCC - Runtime.

- If the license for SICAM SCC Configuration is missing, the access to properties of connections and tags is locked and the import of process tags with the Wizard is not possible.
- If the license for SICAM SCC Runtime is missing, you can start the Runtime in Demo mode, see 2.3.1 Design Variants.

## 7.3.2 SICAM IEC COMMUNICATION SUITE

#### Overview

The **SICAM IEC COMMUNICATION SUITE** is required for the process data interfacing of SICAM SCC to SICAM RTUs and IEC 61850/IEC 60870-5-104 devices, as well as for controlling the connection.

7.3 SICAM Communication Connection - Tag Management

SICAM RTUs/IEC 61850/IEC 60870-5-104 devices are connected to SICAM SCC or SIMATIC WinCC via the SICAM IEC COMMUNICATION SUITE. The SICAM IEC COMMUNICATION SUITE logs on to the devices during runtime in order to exchange process information.

III Tag Management - WinCC Configuration	Studio				-	- 🗆	×			
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp										
Tag Management «	Find	•	📂 Prop		*					
🗈 🍄 Internal tags 🔷 🔨	Name	^	□ Select	ion						
- SICAM PAS PROTOCOL SUITE	1 ActivateOnlineConfig_1202		Object	type	Connection					
- PAS Data Server	2 AlarmListFilter_1202		Object	name						
⊕-I     SubstationSouth	3 CompKey_Ext_1202		Generation							
- L System Info	4 ConnectionName_1202		Name		SubstationEast					
B-II System Info	5 ConnectionState_1202		ID		8					
SystemInfo	6 ExecGI_1202		Connection Parameters							
SICAM IEC Communication Suit	7 ForceConnectionState_1202			ment	CTC111 150 Com	alastia a C				
LEC 60970 5 104 Data Server	8 InitiatorCategory_1202		Commu	inication driver	SICAM IEC Comm	unication Su	lice			
IEC 61950 Data Server	9 MSG_Ack_1202		Variou	er urnic	IEC 01850 Data S	erver				
EC OTODO DALA SERVER	10 MSG_Queue_1202		Creato	TD	0					
<u>H</u> → SubstationEast	11 ProjectID_Ext_1202		Last Ch	ande	22.08.2017.08:3	5:09				
E-Structure tags	12 RedundancyMaster_1202		2000 01	ango	2210012017 0010					
PAS_Command	13 SubstationEast_IED_000000001_c_Steuerung_Q0_EIN_AUSCSWI_Position.A									
PAS_Command_DEMO	14 SubstationEast_IED_000000001_c_Steuerung_Q0_EIN_AUSCSWI_Position.C									
< >	15 SubstationEast_IED_00000001_c_Steuerung_Q0_EIN_AUSCSWI_Position.C									
ililit	16 SubstationEast_IED_00000001_c_Steuerung_Q0_EIN_AUSCSWI_Position.C									
iiii Tag wanagement	17 SubstationEast_IED_00000001_c_Steuerung_Q0_EIN_AUSCSWI_Position.R									
Alarm logging	18 SubstationEast_IED_00000001_c_Steuerung_Q0_EIN_AUSCSWI_Position.V									
	19 SubstationEast_IED_00000001_c_Steuerung_Q0_EIN_AUSCSWI_Position.V									
Tag Logging	20 SubstationEast_IED_00000001_c_Steuerung_Q0_EIN_AUSCSWI_Position.V									
Text Library	21 SubstationEast_IED_00000001_c_Steuerung_Q1_EIN_AUSCSWI_Position.A									
	22 SubstationEast_IED_00000001_c_Steuerung_Q1_EIN_AUSCSWI_Position.C									
ill llear Administrator	23 SubstationEast_IED_00000001_c_Steuerung_Q1_EIN_AUSCSWI_Position.C									
Tr Oser Administrator	24 SubstationEast_IED_00000001_c_Steuerung_Q1_EIN_AUSCSWI_Position.C	:								
User Archive	25 SubstationEast_IED_00000001_c_Steuerung_Q1_EIN_AUSCSWI_Position.R									
	26 SubstationEast_IED_00000001_c_Steuerung_Q1_EIN_AUSCSWI_Position.V									
📢 Horn	27 SubstationEast_IED_00000001_c_Steuerung_Q1_EIN_AUSCSWI_Position.V									
	28 SubstationEast_IED_00000001_c_Steuerung_Q1_EIN_AUSCSWI_Position.V	~								
T 11 *	H + H Groups Tags C >	:								
Ready NUM	English (United States)			Table: 97 Tags	100 % 😑 🗕	-0	- (+)			

[pascc403_1703, 1, en_US]

Figure 7-16 SICAM IEC COMMUNICATION SUITE in the WinCC Explorer

#### Performance characteristics

The SICAM IEC COMMUNICATION SUITE has the following performance characteristics:

- Event-controlled update of the process image
- Time stamps from the process via raw data tags and the SICAM PAS normalization DLL
- Automatic start and stop via SIMATIC WinCC
- Parallel connection of different or redundant SICAM RTUs to SIMATIC WinCC with automatic switchover in case of faults
- Connection of different IEC 61850/IEC 60870-5-104 devices

### Tasks

The SICAM IEC COMMUNICATION SUITE performs the following tasks:

- Connection to the SICAM RTUs/IEC 61850/IEC 60870-5-104 devices
- Forwarding of display and indication tags to SIMATIC WinCC
- Forwarding of commands to the SICAM RTUs substation controller/IEC 61850/IEC 60870-5-104 devices
- Monitoring of the connection to the SICAM RTUs substation controller/IEC 61850/IEC 60870-5-104 devices

#### Tags

To retrieve the process data required, the SICAM IEC COMMUNICATION SUITE logs on to the SICAM RTUs/IEC 61850/IEC 60870-5-104 devices. This data includes the process information for messages in WinCC Alarm Logging and the tags required for the display of process diagrams in the Tag Management.

During the import process, the wizard creates a ValueID for addressing each item of information in WinCC. To show the assignment of the ValueID to the external telegram address, open the properties of a tags address and view the specific tag information (address parameters).

### Licensing

With regard to the SICAM IEC COMMUNICATION SUITE a distinction is made between 2 licenses, i.e. the license for SICAM SCC - Configuration and the license for SICAM SCC - Runtime.

- If the license for SICAM SCC Configuration is missing, access to the properties of connections and tags is denied and no process tags can be imported with the Wizard.
- If the license for SICAM SCC Runtime is missing, you can start the Runtime in Demo mode, see chapter 2.3.1 Design Variants.

### System messages

The **Communication fault (ComFault)** and **Operational readiness (OprReady)** tag types can be configured as status messages in the SICAM TOOLBOX II for the IEC 60870-5-104 and IEC 61850 connections. For an IEC 61850 connection the **general interrogation** can be also configured as status message.

During the import process for directly connected IEC 61850 devices the **ComFault**, **OprReady** and **GIStatus** tags are provided as status messages of the corresponding device for mapping. They can be mapped like normal process tags.

The **GIStatus** tag can have the following 4 status values:

- 0 = General interrogation never run
- 1 = General interrogation completed successfully
- 2 = General interrogation running
- 3 = General interrogation failed

In redundant systems the system messages from both SIMATIC WinCC servers are entered in message lists. The name of the causing system is entered in the message lists in the **Supplementary information** column.

#### **Command logging**

The following is logged in the Additional cause column in the message lists:

- The qualifiers of command transmitted when issuing the command
- The causes indicated by the device in case of an unsuccessful command output

#### Showing the Originator Address in Message Lists

To show the originator address in the **Location** column, **origin_userstate=1** must be set for IEC 61850 in the IEC61850.INI file of the [GENERAL] driver. The device-specific parameter [IEDxxx] **orldent_mode** must be defined according to the device specification (0 to SAT200: <IP address> Origin:<OriginatorAddress> / 1 to <OriginatorAddress> (numeric, 1Byte)). For IEC60870-5-104, the [DEFAULT] **HerkAdrStati=1** parameter must be set in the AKServ.INI file.

#### Qualifier of Command (QoC) for IEC 60870-5-104

In order to be able to use **Qualifier of Command** (QoC: sync / no sync, interlocked / not interlocked) during switching, you must activate the QoC functionality. To do this, set the **SendQOC** attribute to **1** in the **[Default]** section of the **AKServ.ini** file (SendQOC=0 deactivates the QoC function).

The file is available in the project directory under GWData > StationName > ComConfig104 > str.

#### 1-of-N Command Interlocking

With the parameter **COMMAND_GRP** all commands of a command group (i.e. all with the same command group number) are interlocked against each other, so only 1 command can be executed at the same time. Commands triggered during command interlocking are refused and acknowledged to SICAM SCC with **COT=7** (Confimation) PN-.

The configuration is done via Toolbox, the Import Wizard writes the following lines in the AKServ.ini file:

[Default] CommandDelay=5 ; delaytime for locking of command groups [sec], default=0 CommandTimeout=200 ; timeout for unlocking of command groups [sec], default=300

### **New Variable Parameter**

In XML import file (Toolbox): Parameter name: **COMMAND_GRP (Command group number)** Data type: unsigned integer Range of values: 0 to 65535 Default value: 0

### Description

The following is logged in the IECChannel_IEC104Driver.log trace file: "Command '<xxx>' rejected, because command '<yyy>' in same group is running"

Only after sending commands has been terminated (**Termination**, **Cancel**, or **Confirmation PN-**) and the time delay for the command (CommandDelay) has been expired, a new command can be sent.

An incomplete sequence of commands (e.g. **Termination** has not been received) would cause an infinite interlock of the command group. The parameter **CommandTimeout** is used to avoid this. When this timer has expired (after sending commands has started) the command group is unlocked. CommandTimeout=0 disables the safety mechanism.

The following is logged in the IECChannel_IEC104Driver.log trace file:

"Unlocking of commandgroup <nn> which contains control: '<yyy>'"

### Substitute



## NOTE

Substituting is only possible on IEC 61850 data points with Functional Constraint (FC) SV, e.g. SubVal. For IEC 61850 devices, substitution is usually performed to the XCBR or XCSWI data point. Alternatively, you can create a new **SubVal2IED = 1** entry in the 61850.ini file under [GENERAL]; in this case, the .stVal tag can be used directly for substitution.

## SICAM DISTO

For more detailed information on the communication between SICAM DISTO and the IEC 61850-Client, refer to chapter 7.10 Communication with SICAM DISTO.

## Time Correction for DST

For SCC computers with Windows Time Zones **DST** option located on the southern hemisphere, use a workaround for time correction for IEC104 Communication Suite process signals.

Disable the DST settings in the **TMGF.str** project configuration file (in folder **<project>\GWData\<station> \ComConfig104 \str\)**. Use the following settings:

## 7.3.3 IEC 61850 Connection

The IEC 61850 driver supports **Buffered Reporting** using **dynamic datasets**. The driver successfully establishes the communication, uses the persistently saved assignment Datatset/Buffered Control Block (BRCB), and queries the buffer values in the server which have been changed since the last clearing of the connection. Under the following scenarios, it is not possible to query buffered values from the server upon the first establishment of a connection:

- Using the IEC Import Wizard to change the data model or the communication parameters of an IEC 61850 connection
- Restart of the IEC 61850 device (the dynamic datasets are deleted in the process)
- Another IEC 61850 Client uses a BRCB reserved by the IEC 61850 driver.
- When copying the SCC project, the persistent Dataset/BRCB assignment is copied together with the SCC project. The IEC 61850 driver of the 2nd SCC Runtime cannot use these BRCBs and activates its self-created dynamic datasets using free BRCBs.

## NOTE

During the direct connection of IEC 61850 devices you can define in the device-specific parameters which of the following communication drivers shall be used:

- Static or Dynamic Dataset
- Unbuffered or Buffered Report

When selecting Buffered Report, you can additionally define whether or not you want buffered messages to be logged in the Alarm Logging (a) or (b).

If SICAM SCC is used redundantly, (b) must be selected.



## NOTE

Substituting is only possible on IEC 61850 data points with Functional Constraint (FC) SV, e.g. SubVal. For IEC 61850 devices, substitution is usually performed to the XCBR or XCSWI data point.

Alternatively, you can create a new **SubVal2IED = 1** entry in the 61850.ini file under [GENERAL]; in this case, the .stVal tag can be used directly for substitution.

For more information, see 4.8.9 Support of Controllable Analogue Process Value (CDC = APC).

## 7.3.4 IEC 61850: Treatment of data with set Test Bit

Standardmäßig werden empfangene Daten unabhängig vom Zustand des Test-Bits (**Quality.test**) im SICAM SCC verarbeitet, d.h. in den Bildern und Listen angezeigt.

By default, in SICAM SCC received data is processed regardless of the state of the test bit (**Quality.test**), i.e. it is displayed in the pictures and lists.

To discard the data with set test bit (**Quality.test** = **true**) in the IEC 61850 driver and not process it in SICAM SCC, configure the following in the configuration file IEC61850.INI:

[GENERAL] DiscardTestBit=1

# 7.4 Alarm Logging

The Alarm Logging component of SIMATIC WinCC serves as a basis for the Alarm Logging system. It ensures that data is logged in the correct chronological order.

# 7.4.1 Alarm Logging System

The SICAM PAS Alarm Logging system differs from standard logging systems with regard to the information transmitted with an alarm message.

By default, SIMATIC WinCC cyclically updates all information regarding the process state.

This mechanism is sufficient for visualization in diagrams.

Alarms, however, must not be lost and must be processed in the correct chronological order.

### Raw data tag

SICAM PAS alarms are transmitted to SIMATIC WinCC as raw data tags with a time stamp and additional values.

### **Normalization DLL**

For SIMATIC WinCC Alarm Logging, a SICAM PAS normalization DLL decodes the contents of the raw data tag. It creates an alarm with a resolution of 1 ms in the Alarm Logging system.

### Correct chronological order

Based on the time stamp of the raw data tag, alarms can be sorted chronologically in the alarm lists in order to ensure that they are shown in the correct order of their appearance.

### Alarm lists

You can set any filters also to textual process value columns in the alarm lists (SIMATIC WinCC V7.0 SP1 or later).

## 7.4.2 SICAM Normalization DLL

Combined with the SICAM communication connection, the SICAM normalization DLL provides the basis for the alarming and logging of data in correct chronological order.

The SICAM normalization DLL prepares the data of the source system (SICAM PAS, SICAM RTUs or IEC 61850/IEC 60870-5-104 devices) in a SICAM-specific manner for SIMATIC WinCC Alarm Logging.

#### SICAM normalization DLL

The SICAM normalization DLL evaluates the additional information transmitted in the process values and generates an alarm with the corresponding alarm texts in the Alarm Logging system.

## The file name is **PASNORM.NLL**.

The SICAM normalization DLL supports the hiding and blocking of messages for a SIMATIC WinCC server. The message block is not set in SICAM PAS/SICAM RTUs. It must therefore be set separately on each individual SIMATIC WinCC computer with a process connection.

## Additional information

The following additional information is available:

- Value
- Location
- Cause

- Status
- Additional cause
- ID number²
- Additional information
- Time status
- Flag (SICAM PAS flag used by the Alarm Logging system to suppress internal messages which are irrelevant for typical applications. This suppression corresponds to the default setting.)

For more detailed information, refer to Structure Elements, Page 524.

#### **Text library**

The normalization DLL retrieves the alarm texts from the text library. The texts are stored in the text library in the language used.

To view the texts, click **Text Library > Open** in the WinCC Explorer. Texts with the **text IDs 599** to **2216** are available for new projects. These texts can be customized to meet the requirements of specific projects. Furthermore, the user can add additional language columns for translated texts.

Text Library - W	inCC Configur	ation Studio				-		×
<u>F</u> ile <u>E</u> dit <u>V</u> iew	Too <u>l</u> s <u>H</u> elp	p						
Text Lib «	Text [/	AII ]	Fi	ind 🔎 <del>-</del>		Properties - Text		*
Text Library	ID	German (Germany)	English (United States)	Spanish (Spain, Traditional Sort)	< E	Selection		
	1 1	Störung	Error	Error		Object type	Text	
	2 2	+	+	+		Object name		
	3 3	-	-	-	E	General		
	4 4	+/-	+/-	+/-		ID	9	
	5 5	*	*	*	E	Texts		
	6 6	System, quittierpflichtig	System, requires acknowledgment	Sistema, acuse obligatorio		German (Germany)	Warnung	
	7 7	System, ohne Quittierung	System, without acknowledgment	Sistema, sin acuse		English (United States)	Warning	
	8 8	Alarm	Alarm	Alarma		Spanish (Spain, Tradicional Sort)	Advertencia	
	9 9	Warnung	Warning	Advertencia				
	10 10	Fehler	Failure	Error.				
	11 11	Leittechnik	Process control system	Sistema de control de procesos				
	12 12	Systemmeldungen	System messages	Avisos de sistema				
	13 13	Bedienmeldungen	Operator input messages	Avisos de operador				
	14 14	Datum	Date	Fecha				
	15 15	Uhrzeit	Time	Hora				
	16 16	Dauer	Duration	Duración				
	17 17	Sommer- / Winterzeit	Daylight Saving / Standard Time	Horario verano / invierno				
	18 18	Zustand	Status	Estado				
	19 19	Quittierstatus	Acknowledgment Status	Estado de acuse				
	20 20	Nummer	Number	Número				
	21 21	Klasse	Class	Clase				
	22 22	Art	Туре	Тіро				
	23 23	AG/CPU-Nummer	Controller/CPU Number	Número PLC/CPU				
	24 24	Variable	Tag	Variable				
	25 26	Archivierung	Archiving	Archivación				
	26 27	Protokollierung	Logging	Registro en informe				
	27 28	Kommentar	Comments	Comentario				
	28 29	Infotext	Info Text	Texto informativo				
	29 30	Loop in Alarm	Loop in Alarm	Loop in Alarm				
	30 31	Rechnername	Computer Name	Nombre de equipo				
IIII Tan Manan	31 32	Benutzername	User name	Nombre de usuario				
Tag Manag	32 33	Priorität	Priority	Prioridad				
Alarm logg	33 34	Meldetext	Message text	Texto de aviso				
	34 35	Störort	Point of error	Lugar de avería	IF			
Tag Logging	35 36	Block: 3	Block: 3	Bloque: 3				
	36 37	Block: 4	Block: 4	Bloque: 4				
🏢 🕅 📶 🖷 🗉	<b>H 4 P H</b>	Text	. <	>	.:			
Ready NUM				Table: 2612 Text   100 % 😑	-0	÷.,		

[pascc401, 1, en_US]

Figure 7-17 Text Library

The texts for the value of a process tag (e. g. ON/OFF) in the text library are subdivided into the **value text** groups 0 to 16. Value text group 0 is the default group, and its texts should not be modified. The texts in groups 1 to 16 can be customized to meet specific requirements.

² If the devices are connected via SICAM RTUs and directly via IEC 61850/IEC 60870-5-104, this additional information is not available.

The value text group whose texts are to be displayed in the alarm lists can be defined in the **Value Text** column for each alarm in the Alarm Logging system.

For SICAM PAS V8.02 or later you can configure the value text group assignment in **SICAM PAS – Configuration**. For older SICAM PAS versions or if no configuration has been performed, the value text group 0 is predefined as standard.



# NOTE

For accelerated searching of certain value text groups (e.g. value text group 5), click **Edit > Find > Value text group 5**.

To show the value of an alarm instead of the alarm text, value text group 255 can be entered for this value.

### Alarm Logging

To open the **Alarm Logging** editor in the WinCC Explorer, click **Alarm Logging > Open**. Enter the number of the value text group in the **Value Text** column. 0 is the default group.

🗹 Alarm logging - WinCC Configuratio	n Stud	lio								-	-		
<u>File E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp													
Alarm logging «		Message blocks [ All ] Find						• م		Prop	erties	s - Me »	*
		Used	Message block	Number of characters	Alignment	Flash	Leading zeros	Format ^	E	Selecti	ion		
🖶 🖼 Störung	1	1	Datum	0	Left			Day.Month.Year (		Object	type	Message blo	oc
🐵 🖼 SICAM Meldung	2	V	Uhrzeit	0	Left			Hour:Minute:Sec		Object	name	Message blo	oc
🗄 🖼 SICAM Meldung DM/WM/RN	3	V	Dauer	0	Left								
🗉 🖼 SICAM Meldung mit Quittien	4		Sommer- / Winterzeit	1	Left								
B-SICAM Meldung mit Quittien	5	1	Zustand	5	Left								
III-SICAM Schutzmeldung	6	1	Quittierstatus	5	Left								
SICAM Schutzmeldung WM	7	9	Nummer	9	Left								
System quittieroflichtig	8		Klasse	8	Left								
System, dutterprietug	9		Art	2	Left								
System, onne Quittierung	10		AG/CPU-Nummer	2	Left								
H-= Miessage blocks	11		Variable	1	Left								
Message groups	12		Archivierung	1	Left								
- Ed System messages	13		Protokollierung	1	Left								
	14		Kommentar	1	Left								
⊕–5m AS Messages	15		Infotext	1	Left								
	16		Loop in Alarm	1	Left								
	17		Rechnername	10	Left								
	18		Benutzername	10	Left								
	19		Priorität	3	Left								
	20		Klassenpriorität	3	Left								
	21	V	Meldungsgruppe	64	Left								
	22	V	Störort	10	Left								
	23	V	Meldungstext	25	Left								
	24		Block: 4	10	Left								
	25		Block: 5	10	Left								
	26	1	Einheit	5	Left								
	27		Block: 7	10	Left								
	28		Block: 8	10	Left								
	29		Block: 9	10	Left								
< >	30		Werttextgruppe	64	Left								
	31	<b>V</b>	Wert	10	Left								
Tag Management	32		Ort	20	Left								
_1	33		Verursachung	20	Left								
Alarm logging	34		Status (Validity)	20	Left								-
Tag Logging	35		Zusatzverursachung	40	Left								
	36		Kennummer	20	Left								
🏢 🧌 🗰 🗰 🕶	14 4	• •	Message blocks		<			>					
								0		0	_		
Ready NUM				German (Germany)			Table: 4	10 Message blocks   1	00%	9		( <del>†</del> )	

[pascc402, 1, en_US]

Figure 7-18 Alarm Logging



## NOTE

The value text group is only predefined for process values for which a text can be shown. Measured/ metered values are always shown as numerical values.

# 7.4.3 Using the Alarm Logging Extension

In order to be able to use the alarm logging extension in a project, the Alarm Logging system must be generated in the project.

Afterwards, SICAM PAS alarm messages can be imported into this Alarm Logging system.
#### Creating an Alarm Logging system

Use the **SICAM PAS Wizard** to generate an Alarm Logging system in your new WinCC project which meets the requirements of SICAM PAS.

The Alarm Logging system consists of:

- Alarm message blocks
- Message classes
- Print layouts
- Texts

The corresponding graphic objects for the connection to SICAM PAS, SICAM RTUs or IEC 61850/IEC 60870-5-104 devices are:

- Event list
- Warning message list
- Protection message list

These graphic objects are available in the Graphics Designer under View > Library > Project Library > Alarm Logging Templates.

#### **Moving Messages**

If you move messages with the SICAM SCC AlarmLogging Editor to other reporting classes, make sure that messages from a message class with

- a name containing EM can only be moved to other message classes with names containing EM;
- a name containing DM/WM/RM can only be moved to other message classes with names containing DM/WM/RM.

This is because the configuration of these message classes, the data types of the process values and the processing in the communication channel as well as the standardization DLL are coordinated.

In the message types of a message class, the **Without status "went out"** parameter must not be changed and has to be equal for all message types of this message class.

To not display instances of messages with specific states in the lists, use the Dynamic Alarm Filter (see 7.5 Dynamic Alarm Filter (DAF))

# 7.4.4 Value Texts

By default, for the texts of the **Value** process-value row the texts of the configured value text group (default = 0) are used depending on the data type of the message. The WinCC text library contains 16 further value text groups which you can use and change freely (groups 1 to 16).

To assign texts to dedicated integer values of a process information that are not covered by the value text groups, proceed as follows:

#### ♦ Enter your text in the Text Library.

Only the next free text can be used. This first text **ID** is used for the value 0. The subsequent text IDs are used for further values. Enter all required texts at the same time.

Text Library - WinCC Configurati	on Studio					- • ×
<u>File E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp						
Text Library «	Text [	All ]	Find	<del>ب</del> ک	📑 Properties - Text	»
	ID	German (Germany)	English (United States	) ^	Selection	
	2542 2542	ComFault	ComFault		Object type Text	
	2543 2543	OprReady	OprReady		Object name	
	2544 2544	GIStatus	GIStatus		General	
	2545 2545	0	0		ID 2545	
	2546 2546	A	A		E Texts	
	2547 2547	В	В		German (Gerr U	
	2548 2548	С	С		English (Unite	
	2549 2549	D	D			
Tag Management	2550 2550	E	E			
111 ray management	2551 2551	F	F			
Alarm logging	2552 2552	2445	2445			
	2553	<b>X</b>	XX			
Tag Logging	2554					
	2555			*		
	нчьы	Text		▶		
Ready NUM			German (Germany) S	election: 1 Text	Table: 2552 Text 100 % 😑	

[sc_value_text_txtlib, 1, en_US]

- If you only need high values (e.g. 128 to 135), you can define an offset for the calculation of the value text group entry in the Alarm Logging. Thus, you do not have to enter 127 empty texts (in this example) in the text library.
- ♦ In the Alarm Logging Editor in the Value text group column of the message, enter the start ID from the text library; the start value must be at least 256.

lorm logging "	Mar		LAS Morra	nor 1	1	Find		o _ ]	Broportion Mos	<i>m</i>
	i wes	sayes	[AS Messa	yes j	alessan an anna	Pillu	and the second second		Coloring	saye
Messages	Num	per	Message Typ	e Pr	iot message Group	Message Lext	Unit Value text grou	nb v	Chiect time	Marraga
Error	340 1000	02055	Alarm_101	0	75J07_5IP_75L87	Application/general.Authority.station	0		Object type	Message 10000206
🕀 🖼 SICAM Message	347 1000	02056	Alarm_161	0	7SJ67_SIP_7SL87	Application/general.Authority.station/remote	0		Object name	Message 10000206.
E SICAM Message DI/TR/FB	348 1000	02057	Alarm_161	0	7SJ67_SIP_7SL87	Application/general.Authority.remote	0		E General	
SICAM Message with Acknowledgment	349 1000	02058	Alarm_161	0	7SJ67_SIP_7SL87	Application/general.Authority.local/station/remote	0		Number	100002061
SICAM Message with Acknowledgment o	350 1000	02060	Alarm_161	0	7SJ67_SIP_7SL87	CB1/CircuitBreaker.Mode (controlable)	0		Message class	SICAM Message
SICAM Protection Mercage	351 1000	02061	Alarm_161	0	7SJ67_SIP_7SL87	CB1/Control.State	2445		Message Type	Alarm_161
SICAM Protection Message	352 1000	02062	Alarm_161	0	7SJ67_SIP_7SL87	CB1/Control.Authority Station	0			
• • •	353 1000	02063	Alarm_177	0	7SJ67_SIP_7SL87	CB1/CircuitBreaker.Position 3-phase	0			
	354 1000	02064	Alarm_177	0	7SJ67_SIP_7SL87	CB1/CircuitBreaker.Position 3-phase.subVal	0	-		
		Mess	anes Text	ists /	/					

[sc_value_text_alarm, 1, en_US]

# 7.4.5 Message Coloring

In SIMATIC WinCC, messages are represented in different colors depending on the message state. The message states are:

- Came in
- Went out
- Acknowledged

With SICAM SCC V8.04, the **Message completed** message state can be indicated with an additional color, e.g. as soon as the processing of a fault has been completed.

The advantage of the additional color is that completed messages are no longer just displayed as **Acknowl-edged** or **Went out**, but a defined representation for completed processes is now possible.

This function is available if the **Alarm Logging Color Extension** option has been selected during the customized installation of SICAM SCC. If this is the case, the **CCAlarmColorProcessExtension.ini** file is stored in the **MELD** project directory when creating a SIMATIC WinCC project. You can edit this file - see the paragraphs below.



## NOTE

You can subsequently activate the Alarm Logging Color Extension option via a customized installation of SICAM SCC.

As an example, the paragraphs below describe the configuration and representation in SIMATIC WinCC for various message settings and sequences in the message lists. The **Message completed** message state is represented using a black font on a gray background.

#### Configuring message coloring

To configure the coloring of messages:

♦ Open the Properties dialog of the message type for which you want to configure message coloring.

☑ Alarm logging - WinCC Configuration Studio <u>F</u> ile <u>E</u> dit <u>V</u> iew Too]s <u>H</u> elp							- 0	×
Alarm logging «	🖂 Messages	[Alar Find		۶ -	🖼 Properties - Message Ty	ype		»
	Number	Message tag	Message bit	Status tag \land	Tag for central signaling device			^
Error	1 💥	ж			Status Texts			
Alarm	2	٩			Text "came in"	-		
Warning	3				Text "went out"			
	4				Text "acknowledged"	A		
	5				Text "came in and went out"			
E CAM Message	6				🗆 Tags			
Alarm_161	7				Status tag			
	0				Status bit	0		
Error_163	0				Lock tag			
🖶 🖼 SICAM Message DI/TR/FB	9				Lock bit	0		
	10				Acknowledgment tag			
	11				Acknowledgment bit	0		
Fron 179	12				Colors			
SICAM Mercage with Acknowledgment	13				Font color "came in"	255; 17; 0		
Alarra 102	14				Background color "came in"	255; 255; 255		
Alarm_195	15				Font color "went out"	0; 212; 0		
Warning_194	16				Background color "went out"	255; 255; 255		
Error_195	17				Font color "acknowledged"	208; 0; 10		
Image: SICAM Message with Acknowledgment o	18				Background color "acknowledge	ed" 🗌 255; 255; 255		
👜 🖼 SICAM Protection Message	19				Translation "Name"			
👜 🖼 SICAM Protection Message TR	20				Name (ID)	140		
/	21				Name (DEU)	Ereignis_193		
	22				Name (ENU)	Alarm_193		
Tag Management	23				Name (ESP)	Empty Text		_
	24				Translation "came in"			
Alarm logging	25				"came in" (ID)	3		~
Tag Logging	26				Colors			
222	29							
	H A F H Mess	ages	<	>				
Ready NUM			English (U	nited States)	L	100 % 😑		-+

[prop colors, 1, en US]

Figure 7-19 Configuring message coloring

♦ Configure the text and background colors for the Came in, Went out, and Acknowledged message states.

To activate and configure the coloring of the **Message completed** message state:

♦ Open the **CCAlarmColorProcessExtension.ini** file in the **MELD** project directory using a text editor.

The file includes the following entries: [Settings] Enabled=1 [GlobalColors] CompletedBack=c0c0c0 CompletedFore=000000 #[GlobalStateTexts] #Come=2 #ComeAcked=5 #Go=3 #GoAcked=5

- Under [Settings] set the Enabled entry to 1 in order to activate the function (0 =OFF, 1=ON). This ensures that the last message of a message cycle is displayed in accordance with the settings performed under [GlobalColors].
- ♦ Via **CompletedBack** and **CompletedFore** define the background and font colors of the message.

In the example, the background is gray and the font is represented in black. The entries correspond to the RGB values of a color. These RGB color values are available in the SIMATIC WinCC Graphics Designer under the color settings for any object (Color selection - HTML code).

To enable the display of user-defined texts in the Status system message block of the Alarm logging, remove the character # at the start of the line.

Texts that are stored under the corresponding ID in the text library in the current runtime language are displayed. You can configure both the ID in the INI file and the text in the text library. All messages are processed according to the selected type.

#### Example 1

The following settings are defined in the **Configure message classes** dialog, **Acknowledgment** tab:

- The messages have the states **Came in** and **Went out**.
- The Came in and Went out messages must be acknowledged.

🐋 Alarm logging - WinCC Configuration Studio									-		×
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp											
Alarm logging «	-	🗹 🕅 Find		₽ -	][	🖼 Properties - Message Typ	be				»
	~	Number	Function name	^		Selection					^
Error_163		1 ※	1			Object type	Message Type				
SICAM Message DI/TR/FB		2				Object name	Alarm_193				
Alarm 177		3				General					
Warning 178		4				Name	Alarm_193				
Fron 179		5				Message type (ID)	193				
		6				Message class	SICAM Message with A	cknowledg	ment		
SICAM Message with Acknowledgment		7				Author	0				
Alarm_193		8				Acknowledgment Theory					
		9				Acknowledgment "came in"					
Error_195		10				Acknowledgment "went out"					
👜 🖼 SICAM Message with Acknowledgment o		11				Flash On					
BICAM Protection Message		12				Only for initial value					
SICAM Protection Message TR	-H	12				Without status "went out"					
System requires acknowledgment	H	13				Unique user					
System, requires deknowledgment		14				Comment					
		15				Central signaling device					
Hessage blocks		16				Acknowledgment key					
Message groups		17				Tag for central signaling device					
		18				Status Texts					
		19				Text "came in"	-				
⊕ - 🕎 AS Messages		20				Text "went out"					
	<b>۲</b>   -	21				Text "acknowledged"	A				
< >>	-13	22				Text "came in and went out"					
IIII Ten Management		23				🗆 Tags					
Tag Management		24				Status tag					
		25				Status bit	0				~
		25			1F						
Tag Logging		20		-		Acknowledgment Theory					
	-11:	27		_							
● 索 🖾 🦷	•	28 ∢ ∢ ⊁ ⊁ <u>Mess</u>	ages / I <	>	:						
Ready NUM			English	(Unite	d S	tates)		100 % 🤆	)	-0	- (+ ) .;

[prop_example_1, 1, en_US]

Figure 7-20 Example 1, configuring message classes

The RAISED - Ack - CLEARED - Ack message sequence is shown as follows in the event list:

326	10000012	WIVS	19.12.2011	15:35:48,671	COM	SICAM_PAS\vmware_xx	ClockSync	RAISED
327	10000012	WIVS	19.12.2011	15:35:59,965	QUIT	SICAM_PAS\vmware_xx	ClockSync	RAISED
328	10000012	WIVS	19.12.2011	15:36:09,793	GO	SICAM_PAS\vmware_xx	ClockSync	CLEARED
329	10000012	WIVS	19.12.2011	15:36:13,856	QUIT	SICAM_PAS\vmware_xx	ClockSync	CLEARED

[list_example_11, 1, --_--]

The RAISED - CLEARED - Ack message sequence is shown as follows in the event list:

319	10000012	WIVN	19.12.2011	15:20:23,612	COM	SICAM_PAS\vmware_xx	ClockSync	RAISED
320	10000012	W   VN	19.12.2011	15:20:29,023	GO	SICAM_PAS\vmware_xx	ClockSync	CLEARED
321	10000012	WIVN	19.12.2011	15:20:36,822	QUIT	SICAM_PAS\vmware_xx	ClockSync	CLEARED

[list_example_12, 1, --_--]

#### Example 2

The following settings are defined in the Configure message classes dialog, Acknowledgment tab:

- The messages have the states **Came in** and **Went out**.
- The **Came in** message must be acknowledged.

😒 Alarm logging - WinCC Configuration Studio						-		×
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp								
Alarm logging	x 🖂	M Find		<del>ب</del> م	🖼 Properties - Message T	Гуре		»
	^	Number	Function name	^	Selection			^
Error 163	1	<u>ж</u>			Object type	Message Type		
SICAM Message DI/TR/FB	2		-0		Object name	Alarm_193		
Alarm 177	3				🗆 General			
Warning 178	4				Name	Alarm_193		
Error 170	5				Message type (ID)	193		
	6				Message class	SICAM Message with Acknowledgment		
SICAM Message with Acknowledgment	7				Author	0		
Alarm_193	8				Acknowledgment Theory			
	0				Acknowledgment "came in"			
	10				Acknowledgment "went out"			
	10				Flash On			
GICAM Protection Message	11				Only for initial value			
H-SICAM Protection Message TR	12				Without status "went out"			
System requires acknowledgment	13				Unique user			
The system, requires decisioned grient	14				Comment			
System, without acknowledgment	15				Central signaling device			
	16				Acknowledgment key			
- Message groups	17				Tag for central signaling device			_
	18				Status Texts			
-🔀 Limit monitoring	19				Text "came in"	-		
🗄 🔄 AS Messages	20				Text "went out"	-		
	× 21				Text "acknowledged"	A		
< >>	22				Text "came in and went out"			_
III Tan Managament	23				🗆 Tags			
Tag management	24				Status tag			
Alarm logging	25				Status bit	0		~
	25							
Tag Logging	20				Acknowledgment Theory			
333	2/							
🗰 🗰 🕀 🛣	× 20 H 4	► H Mes	sages / K	>				
Ready NUM			Engli	ish (United	States)	100 %		-
icady inom			Liigi	s (onneed	states	100 /2 (	$\checkmark$	Ψ.

[prop_example_2, 1, en_US]

Figure 7-21 Example 2, configuring message classes

The RAISED - Ack - CLEARED message sequence is shown as follows in the event list:

316	10000012	WIVN	19.12.2011	15:19:29,102	COM	SICAM_PAS\vmware_xx	ClockSync	RAISED
317	10000012	WIVN	19.12.2011	15:19:39,664	QUIT	SICAM_PAS\vmware_xx	ClockSync	RAISED
318	10000012	WIVN	19.12.2011	15:19:50,580	GO	SICAM_PAS\vmware_xx	ClockSync	CLEARED

[list_example_21, 1, --_--]

The RAISED - CLEARED - Ack message sequence is shown as follows in the event list:

319	10000012	W   VN	19.12.2011	15:20:23,612	COM	SICAM_PAS\vmware_xx	ClockSync	RAISED
320	10000012	WIVN	19.12.2011	15:20:29,023	GO	SICAM_PAS\vmware_xx	ClockSync	CLEARED
321	10000012	WIVN	19.12.2011	15:20:36,822	QUIT	SICAM_PAS\vmware_xx	ClockSync	CLEARED

[list_example_22, 1, --_--]

#### Example 3

The following settings are defined in the **Configure message classes** dialog, **Acknowledgment** tab:

- The messages only have the state **Came in**.
- The **Came in** message must be acknowledged.

7.4 Alarm Logging

Studio - WinCC Configuration Studio						-		×	
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp									
Alarm logging «	M Find	م	•	5	🖁 Properties - Message Ty	pe		»	
Warning_162	Number	Function name	^	Ξ	Selection			^	~
Error 163	1 💥	7			Object type	Message Type			
SICAM Message DI/TR/FB	2	-			Object name	Alarm_193			
Alarm 177	3			Ξ	General				
Warning 179	4				Name	Alarm_193			
	5				Message type (ID)	193			
	6				Message class	SICAM Message with Acknowledgment			
SICAM Message with Acknowledgment	7				Author	0			
	0				Acknowledgment Theory				
	0				Acknowledgment "came in"				
Error_195	9				Acknowledgment "went out"				
SICAM Message with Acknowledgment o	10				Flash On				
H-SICAM Protection Message	11				Only for initial value				
SICAM Protection Message TR	12				Without status "went out"				
Surtem requires acknowledgment	13				Unique user				
System, requires acknowledgment	14				Comment				
System, without acknowledgment	15			Ξ	Central signaling device				
I I Message blocks	16				Acknowledgment key				
- 🔁 Message groups	17				Tag for central signaling device				
	18			Ξ	Status Texts				
-🔄 Limit monitoring	19				Text "came in"	-			
AS Messages	20				Text "went out"				
	21				Text "acknowledged"	A			
< >	- 22				Text "came in and went out"				
	23			Ξ	Tags				
Tag Management	24				Status tag				
Alarm logging	24				Status bit	0			,
Alarin logging	23								=
Tag Logging	20			(	Colors				
	2/								
■ ₩ Ⅲ ● 左 🗷 -	28 II I I I I Mes	sages / I <	•						
Ready NUM		English (Ur	nited	Sta	tes)	100 % 😑	-0		

[prop_example_3, 1, en_US]

Figure 7-22 Example 3, configuring message classes

The RAISED - Ack message sequence is shown as follows in the event list:



[list_example_31, 1, en_US]

# 7.4.6 Flexible Configuration of the Alarm Logging System

To facilitate the interaction of SICAM SCC with other products such as SIMATIC STEP7 projects (WinCC OS Project Editor) or PCS 7, the SICAM SCC Alarm Logging System can be adapted to the Alarm Logging System in an existing SIMATIC WinCC project.

#### How to proceed

In SICAM SCC the Alarm Logging System can be flexibly configured in order to write texts or process values into the same columns created for SIMATIC STEP7 or PCS 7 projects.

The IDs of message blocks and message classes can be configured in the **PASNorm.ini** file. The configuration influences both the generation of the SICAM SCC Alarm Logging System during the import of the configuration data and also the Normalization DLL which writes the current process data into the desired data blocks during runtime. The default entries can be transferred to other message block IDs or deactivated.

#### Configuration of the PASNorm.ini file

A template for the configuration of the Alarm Logging System (**_PASNorm_.ini**) is available in the **misc** subfolder of the SICAM SCC installation directory. This template can be adapted before the start of a SICAM Wizard and saved as **PASNorm.ini** in the same directory. The PASNorm.ini is copied into the WinCC project directory when running a SICAM Wizard for the first time in a **newly created WinCC project**. For this reason any subsequent changes must be performed in the file stored in the project directory.



# NOTE

The message lists (WinCC Alarm Control) included in the scope of delivery of the SICAM graphic object library are pre-configured for the SICAM SCC standard. In order to be able to use them, they must be adapted to the modified Alarm Logging System structure (column display and arrangement, SICAM filter settings in the Properties under **Message Lists > Fixed selection > Edit**).



# NOTE

The modified **PASNorm.ini** file in the SICAM SCC installation directory is reused when creating a new WinCC project. To configure new projects based on the SICAM SCC standard once again or to use a different configuration, the PASNorm.ini file must be deleted or adapted before creating a new WinCC project using a SICAM Wizard.

#### Settings for the runtime (behavior of the Normalization DLL)

In the **## RUNTIME Behavior ##** section you configure the data for the processing of process values via the Normalization DLL during the SIMATIC WinCC runtime.

#### Process value blocks

You can adapt the use of process value blocks via the Normalization DLL in the **PASNorm.ini**. The process value blocks for the configuration mode must be modified analogously.

The use of the process value blocks can be adapted via the **PASNorm DLL** in the **PASNorm.ini**. The process value blocks for the configuration mode must be modified analogously.

- **Runtime mode** column The **RB** identifier is used to identify the process value blocks.
- **Default ID** column Corresponds to the process value block number which has been fixedly defined so far.
- **Process data block name** column Description of the text block.
- New block ID column Newly defined block number. In the default setting this block number is identical to the default ID.
- Used Yes/No column

Defines whether the process value block is to be filled with process data during the SIMATIC WinCC runtime.

# 7.5 Dynamic Alarm Filter (DAF)

# 7.5.1 Overview

The **Dynamic Alarm Filter** (DAF) allows you to decide which – and how – status changes of a message or an analog value are entered into the SICAM SCC message lists or written into a trigger variable.

- You can create several DAFs. There are binary DAFs (with a value of up to 32 bits) and numerical (analog values) DAFs.
- Each DAF is written into a table line by line and you define a corresponding state/criterion and a reaction in each line.
- You can integrate additional, user-defined criteria into the decision matrix which you can control via WinCC (DAF_Marker1 ... 8).
- This means that you can, for example, process a spontaneous message in a different manner than the command acknowledgment from a switch.
- You can define that no entries are created in the message lists for certain status changes.
- Furthermore, you can define value ranges for analog values. A message is shown if an analog value exceeds this range. This ensures that a message is not entered for each value change.
- You can read out the user name from a WinCC variable and transfer it to the message lists (user name DAF, process value block 10).
- In addition, you can describe a trigger variable for each state and, e.g., trigger an action.

The DAFs configured can be assigned to one or several messages.



## NOTE

In order to use the DAF functionality, SIMATIC WinCC V7.4 SP1 Upd5 or later is required.



## NOTE

To work with DAF, the entire project must be adapted accordingly. Legacy projects continue to run without DAF by default. Since message lists with DAF do not work completely in the same way as message lists without DAF, different templates are available in the library.

#### Advantages

DAFs provide the following advantages:

- DAFs can be used multiple times. A DAF can be linked to several messages based on different data types.
- Value ranges are defined and a message is shown if a range is exceeded, whereas process value changes within the defined range do not trigger a message (threshold function).
- DAFs enable status requests.

#### **User Interface**

The **Dynamic alarm filter** function is operated via the **SICAM Dynamic Alarm Filter Configurator** window subdivided into the following 2 dialogs:

- In the SICAM SCC Dynamic Alarm Filter Configuration dialog, you define states (filter criteria) to be checked for the tags. See 7.5.3 Configuration.
- In the SICAM SCC Dynamic Alarm Filter Mapping dialog, the messages must be assigned the corresponding DAFs. See 7.5.4 *Mapping*.

#### User name in message lists

To write the user name into the message lists, the **DAF_UserName** text tag is created in the SICAMDAF tag group when creating the SICAM project.

The text must not exceed 30 characters. The contents of the tag are written into Process value block 10 (user name) of the AlarmLogging when creating a message. This process value block can be shown in the message lists. You can freely define the contents of the tags during the runtime. Example: The name of the current user can be written into the tag when triggering a command.

The **@CurrentUserName** tag was not used because it is computer-specific and because the user who is logged on to the process control client does not need to be identical with, e.g., the user logged on to the WinCC server creating the message.

#### NOTE

This function is only available if the Dynamic Alarm Filter (DAF) is used.

# 7.5.2 Starting the Dynamic Alarm Filter Function

♦ In the WinCC Explorer, double-click SICAM Dynamic Alarm Filter.



The SICAM SCC – Dynamic Alarm Filter Configurator opens.

# 7.5.3 Configuration

1	2 3	4	
😫 SICAM dynamic alarm filter configurator			- <b>-</b> ×
		SICAM SCC.	- dynamic alarm filter configuration SIEMENS
Dynamic alarm filter list	Configured filter criteria	Evant list Alarm list Notes	
▲ Binary	1		
<ul> <li>A Numeric</li> </ul>	01	GI - ON GI - OFF	
SI with alarm when ON			
Alarm when ON filter template     SI with alarm when OFF			~
Alarm when OFF filter template			
	✓ Filter criterion settings Value		Notes
	31 24 23 16 • • • • • • • • • • •		Comment: GI - ON
	Status O	rigin  Initiator category:	Cause of transmission Cause of transmission: General interr.
	Bay blocked     Overflow	Only IEC connections:	Additional cause:
	Telecontrol blocked Time status	Originator address:	Internal user defined tags
	Invalid	Value origin:	DAF_Marker_2     DAF_Marker_6
1	Daylight saving time     Timestamp replaced	Type of change: v	DAF_Marker_3     DAF_Marker_7     DAF_Marker_8
9			
	System action	lessage text	Trigger variable
	○ No old/new comparison ✓ Show in event list	Value text group:     Value text group:	Trigger variable:
	✓ Show in alarm list Acknowledge "came in"	Originator address text Id:	Background color:
	Auto-Acknowledge of former entries	Add user name (value of tag 'DAF_UserName')	Font color: Acknowledgment colors
	Re-enter at startup		Background color:
	J (		
			Next > OK Cancel Apply
Alarm filter Binary: 1 Numeric: 1	Jarm ON: 1 Alarm OFF: 1 Filter criteria: 7 / 7	File: D:\Projects\WinCCV7.5SP1\Doku\SICAMDAF\SicamDAF.xml	
		Ġ	6
[le_daf_ui_cor	ig, 3, en_US]		
(1)	Dynamic alarm filter list, Page .	298	
(7)	Configured filter criteria, Page .	299	
(∠)		00	
(2)	Filter criterion settings, Page 30	00	
(2) (3) (4)	Filter criterion settings, Page 30 Filter criterion actions, Page 30	12	
(2) (3) (4) (5)	Filter criterion settings, Page 30 Filter criterion actions, Page 30 Information bar	02	
(2) (3) (4) (5)	Filter criterion settings, Page 30 Filter criterion actions, Page 30 Information bar The information bar provides us filters or the number of filter cr	92 seful information, such as the nu iteria.	umber of binary and numerical

Click **Apply** to save all the settings performed so far. Click **Next >** to open the **7.5.4** *Mapping*. Click **OK** to apply all settings and close the window.

## Dynamic alarm filter list

This list shows all existing DAFs. It is sub-divided according to the following 2 alarm filter types:

• Binary alarm filters

A binary DAF enables the bit-oriented evaluation of any state and status bits of messages. In addition, you can evaluate digital values (e.g. bit patterns and metered values).

#### • Numerical alarm filters

A numerical DAF enables the evaluation of any value ranges and status bits of digital and analog values mapped to the message lists. In contrast to the binary DAF, the evaluation is based on numerical values. This means that not the raw value, but the value converted to the measuring range is evaluated (following a linear or non-linear value adaptation).

#### • Filter for Single-Point Indication with Alarm when ON

A filter type for single-point indications only which sets the alarm for a pending indication (10) and resets it for a non-pending indication (01).

#### • Filter for Single-Point Indication with Alarm when OFF

A filter type for single-point indications only which sets the alarm for a non-pending indication (01) and resets it for a pending indication (10).

All types are configured and mapped in the same dialog. The display of the value in the filter criteria is the only difference.

lcon	Keyboard	Function
+	<ctrl> + <n></n></ctrl>	Add new filter
		A new filter always has the default name ALARMFILTER and should be renamed.
	<ctrl> + <c></c></ctrl>	Add filter copy
		A copied filter always has the default name ALARMFILTER and should be renamed.
	<del></del>	Remove filter
ар	<f2></f2>	Rename filter
only via co	ntext menu	Move filter
		Moves the filter to an other alarm filter type

Table 7-4 Controls

You can also call up the functions via a context menu (by right-clicking the menu item).

#### Configured filter criteria

A DAF can include any number of filter criteria shown in this list together with the states to be checked. The priority of the filter criteria – and of the states to be checked – decreases from top to bottom. This means that the check starts at the top of the list and runs until a filter criterion is true. In this case, all following filter criteria are not checked.

If one or several sub-criteria exist for the matching filter criteria, these sub-criteria are also checked in the order described above. If a sub-criterion is true, only the actions for this sub-criterion are executed; the actions defined for the corresponding main filter criterion are not executed. If no sub-criterion matches, the actions defined for the main filter criterion are executed.

If no filter criterion matches the variable status or the latest known filter criterion applies again, no list entry occurs. When stopping the runtime, the currently queued filter criteria of all variables are stored and will be imported again during re-start of the runtime.

CONTROIS

lcon	Keyboard	Function
+	<ctrl> + <n></n></ctrl>	Ad new filter criterion
=+	<ctrl> + <c></c></ctrl>	Add filter-criterion copy
×	<del></del>	Remove filter criterion

lcon	Keyboard	Function
<	<ctrl> + ←</ctrl>	Use as main filter criterion
	<ctrl> + ↑</ctrl>	Move up – increase priority
~	<ctrl> + ↓</ctrl>	Move down – lower priority
>	<ctrl> + →</ctrl>	Use as sub-filter criterion A sub-criterion is shown with the following riterion.
		cannot include any subordinate sub-criteria.

You can also call up the functions via a context menu (by right-clicking the menu item).

By default, **Value**, **Status**, **Time status**, **Event list**, **Alarm list** and **Notes** are shown in the header. Right-click the header to open a context menu. Via the items of this context menu, you can show or hide further columns of the **Filter criterion settings** and the **Filter criterion actions**.

#### **Filter criterion settings**

Via the **Filter criterion settings** you can define conditions to be fulfilled in order to execute the actions defined under **Filter criterion actions**.

Parameters	Description
Value	
Binary alarm filters	Shows the individual bits (0 to 31) of the tag value from the Alarm Logging. These can be evaluated individually:
	<ul> <li>0 (OFF) The bit is checked for the logical value 0</li> <li>1 (ON) The bit is checked for the logical value 1</li> <li>(none = default) The bit is masked out and is not considered</li> <li>(rising edge) The bit changes from 0 to 1</li> <li>(falling edge) The bit changes from 1 to 0</li> </ul>
	<ul> <li>(alternating)</li> <li>The bit changes from 0 to 1 or from 1 to 0</li> </ul>
Numeric alarm filters	The value or value range and the hysteresis can be indicated.

Table 7-6	Parameters	of the	Filter	Criteria
	rurumeters	or the	inter	cincenta

Parameters	Description
Single-point indication with alarm	Shows the least significant bits (0 and 1) of the tag value from the Alarm Logging.
Single-point indication with alarm	These can be evaluated individually as for binary alarm filters (see
for OFF	above).
Remark	
Comment	Enter a comment, e.g. in order to explain how the filter criterion is
	applied.
	criteria by double-clicking the corresponding entry in the Notes
	column.
Status	
Invalid	The following settings are possible for each status:
Bay blocking	• 0 (OFF)
Telecontrol blocking	• 1 (ON)
Substituted	• (rising; from 0 to 1)
Overflow	• [ (falling; from 1 to 0)
	• (alternating; from 0 to 1 or from 1 to 0)
Time status	
Invalid	The following settings can be defined for each status:
Daylight saving time	• 0 (OFF)
Time stamp replaced	• 1 (ON)
	<ul> <li>trising; from 0 to 1)</li> </ul>
	• (falling: from 1 to 0)
	• $(alternating; from 0 to 1 or from 1 to 0)$
Origin	
Initiator category	The following settings can be defined for the initiator category:
	• (none)
	<ul> <li>Irrelevant</li> </ul>
	• local
	Near
	Remote
	Automatic
	Automatic bay
	Process
	DIGSL local
	Device invalid
	Device Invalid
For IEC connections only:	If the originator address is used, <b>origin userstate=1</b> must be set for
Originator address	IEC 61850 in the IEC61850.INI file of the [GENERAL] driver. The device-
-	specific parameter [IEDxxx] orldent_mode must be defined according
	to the device specification (U to SAT200: <ip address=""> Origin:<origina- torAddress&gt; / 1 to<originatoraddress> (numeric, 18vte)).</originatoraddress></origina- </ip>
	For IEC60870-5-104, the [DEFAULT] HerkAdrStati=1 parameter must be
	set in the AKServ.INI file.

7.5 Dynamic Alarm Filter (DAF)

Parameters	Description
Initiator category	The following settings can be defined for the initiator category:
	• (none)
	• Direct (from source)
	Undefined origin
	• From int. process image
	• From buffer
	1 initiator category per filter criterion can be selected.
For PAS connections only:	The following settings are possible for the change ID:
Change ID	• (none)
	• Initial
	(First change of this value after restarting SICAM PAS [SessionID new, 1st change of the SICAM PAS-COVCounter ³ ])
	No change of COVCounter
	(Message already received, no process value change [SessionID and COVCounter unchanged])
	Normal
	(The value or status of the process value has changed [SessionID unchanged, COVCounter increased])
Cause of transmission	
Cause of transmission	Here you can select from the list of all PAS causes of transmission, Page 306.
	1 PAS transmission cause per filter criterion can be selected.
Additional cause	Here you can select from the list of all PAS additional causes, Page 306.
	1 PAS additional cause per filter criterion can be selected.
User-defined tags	
DAF_Marker_1 8	These are bit tags created automatically after the Wizard run.
	You can freely control the tag values during the runtime and use them
	e.g. in order to activate/deactivate individual filter criteria or activate/ deactivate messages for certain operating states.

### **Filter criterion actions**

Table 7-7Parameter for filter criterion actions

Parameters	Description
System behavior	·
No old/new comparison	If this option is not activated (default setting), messages are rejected if their filtered state is similar to the filtered state of the previous message.
	If this option is activated, the comparison between the current and the previous filter result is neglected. This allows you, for example, to inte- grate cyclically transmitted metered values into the message lists even if these values have not changed.
Show in event list	If this checkbox is activated, the status is shown in the event list. You can also activate this option directly in the <b>Configured filter</b>

³ COV: Change of value

Parameters	Description
Show in alarm list	If this checkbox is activated, the status is shown in the alarm list.
	You can also activate this option directly in the <b>Configured filter</b> criteria list in the <b>Alarm list</b> column.
Acknowledgement for "Came in" and "Went out"	If <b>Show in alarm list</b> is activated, you can define whether or not <b>Came</b> <b>in</b> or <b>Came in/Went out</b> is acknowledged.
Automatic acknowledgement of old entries	If <b>Show in alarm list</b> is activated, you can also define whether previous instances of this message must be acknowledged automatically.
Blinking	If <b>Show in alarm list</b> is activated, you can also define whether the status is shown as blinking in the alarm list.
	In this case, <b>Blinking</b> must be activated in the <b>AlarmLogging</b> for the message type and in the corresponding message blocks. In the <b>Alarm-Control</b> , <b>Blinking</b> must also be activated in the diagrams (pictures) for the corresponding message blocks.
	With these settings you can define different representation variants.
Re-enter upon system start	If <b>Show in alarm list</b> is activated, you can additionally define here whether the first message after the start of the SICAM SCC Runtime shall be entered in the alarm list even if it has not changed compared to the previous message.
Message text	
Value text group	Select whether you want to display the message from a value text group (SCC default setting or Groups 1 to 16) or show the process value directly.
Text ld (> 255)	Alternatively, you can enter a text ID for a text to be displayed. This text is used instead of the text from the value text groups.
Originator address text ld	You can define a text ID for the originator address which is additionally shown in the <b>ID number</b> column.
Add user name	If you select this option, the value of the internal <b>DAF_UserName</b> tag for this message is added to the XXX process value column.
	Alarm list The current <b>DAF_UserName</b> is entered upon every message change.
Trigger variable	
Trigger tag	It is also possible to trigger a tag as an action.
	Select the corresponding trigger variable from the tag selection dialog.
	Be aware that it must be <b>binary</b> . It is always set to <b>1</b> and can be reset by the user. You can use it e.g. as a trigger for scripts or in order to control a collective display of various messages which is reset by an acknowl-edgment.
Colors	Select the background and font color in which you want the message to be displayed in this specific message state. If this option is not selected, the colors of the message type configured in the Alarm Logging are applied.
Acknowledgement colors	Select the background and font colors in which you want the Acknowl- edged messages to be displayed in this specific message state. If this option is not selected, the colors of the message type configured in the Alarm Logging are applied.

# 7.5.4 Mapping

STACK SUC-VITABLE         Control Statu         Status           ge Group         Message Name         Message Number         Atsigned DAF         Daf         Daf           CCL2DBLE 66870-5.103 Matter         Oppflexedy         10000062         Organizational indication         Daf         <	per control of the second seco					CICAN	CCC dunamia diarra filtar a	CIER (EA)
ge Group         Message Nume         Message Nume         Data Type         Assigned DAF           CCCL2DEC 66870-5103 Matter         Op/Ready         10000062         Organizational indication         Image: Control of	ge Group         Message Name           CCCLUDICE 60870-5.103 Master         Oppressional indication         Oppressional indication         Imary Operational Indication         Imary Operatindicatin Indition         Imary Operational Indication	sages				SICAM	Dynamic Alarmfilter	napping SIEMEN
CCC201EC 66870-5-130 Mater         Op-Ready         Image Constrained indication         Image Constrained indication           CCC201EC 66870-5-130 Mater         Constraint         Image Constraint         Im	Columb column         Column <thcolum< th=""> <thcol< th=""><th>sage Group</th><th>Message Name</th><th>Message Number</th><th>Data Type</th><th>Assigned DAF</th><th>DAF</th><th>Туре</th></thcol<></thcolum<>	sage Group	Message Name	Message Number	Data Type	Assigned DAF	DAF	Туре
CCC201EC 68879-5120 Master         Openable         Organizational indication         Prof. 1000000000000000000000000000000000000	CCCC201EC 68070-5128 Matel         Openational indicational indindicational indicational indicational indicational indicational i				•			
CCCLDUEC 66870-5103 Mater         _com/aut         1000068         Organizational indication         mg/inDAf_01         Binary           CCCLDUEC 66870 Clented, Dyr         1000092         Organizational indication         mg/inDAf_02         Binary           CCCLDUEC 66870 Clented, SSI01         Opr         1000092         Organizational indication         mg/inDAf_01         Numeric           CCCLDUEC 66870 Clented, SSI01         Oprenady         1000073         Organizational indication         mg/inDAf_02         Numeric           CCLDUEC 66870 Clented, SSI01         Oprenady         1000073         Organizational indication         Numeric           CCLDUEC 66870 Clented, SSI01         Oprenady         1000074         Organizational indication         Numeric           CCLDUEC 66870 Clented, SSI01         Schutz LluxOSFX         10000582         Organizational indication         Numeric           CCLDUEC 66870 Clented, SSI01         Schutz LluxOSFX         Pulse switching command         Numeric         Numeric           CCLDUEC 66870 Clented, SSI01         Schutz LluxOSFX         Pulse switching command         Numeric         Numeric           CCLDUEC 66870 Clented, SSI01         Schutz LluxOSFX         Pulse switching command         Numeric         Numeric           CCLDUEC 66870 Clented, SSI01         Schutz LluxOSFX	CCCLDVEC 68870-130 Mate	SCCCL20\IEC 60870-5-103 Maste	r _OprReady	10000062	Organizational indication		BinaryDAF_Default	Binary
CCC20VEC 64850 Client 645801         Org         10000088         Organizational indication         mylinDAF_02         Binary           CCC20VEC 64850 Client645801         Opr 0         1000073         Organizational indication         mylinDAF_02         Numeric           CCC20VEC 64850 Client615801         Opr Andu         1000073         Organizational indication         mylinDAF_02         Numeric           CCC20VEC 64850 Client615801         Opr Andu         1000073         Organizational indication         mylinDAF_02         Numeric           CCC20VEC 64850 Client615801         Opr Andu         1000073         Organizational indication         mylinDAF_02         Numeric           CCC20VEC 64850 Client615801         Constraiteonal indication         Constraiteonal indication         Mumeric         Numeric           CCC20VEC 64850 Client615801         Cytanizational indication         Constraiteonal indication         Numeric         Numeric           CCC20VEC 64850 Client615801         Cytanizational indication         1000058         Pulse switching command         Numeric         Numeric           CCC20VE 64850 Client615801         Cytanizational indication         1000058         Pulse switching command         Numeric         Numeric           CCC20VE 64850 Client615801         Cytanizational indication         Numeric         Numeric	CCL2DUEC 61850 Client618501         Opr         10000088         Organizational indication         mylinDAF_02         Numeric           CCL2DUEC 61850 Client618501         Opr         10000190         Organizational indication         mylinDAF_02         Numeric           CCL2DUEC 61850 Client618501         Opr6ady         10000774         Organizational indication         mylinDAF_02         Numeric           CCL2DUEC 61850 Client618501         Opr         10000584         Organizational indication         Numeric           CCL2DUEC 61850 Client618501         Opr         10000582         Organizational indication         Numeric           CCL2DUEC 61850 Client618501         Statusperson         10000582         Pule switching command         Numeric           CCL2DUEC 61850 Client618501         Statusperson         10000582         Pule switching command         Numeric           CCL2DUEC 61850 Client618501         Statusperson         1000058         Pule switching command         Numeric           CCL2DUEC 61850 Client618501         Statusperson         1000059         Pule switching command         Numeric           CCL2DUEC 61850 Client618501         Statusperson         1000059         Pule switching command         Numeric           CCL2DUEC 61850 Client618501         Statusperson         1000059         Single-point in	SCCCL20\JEC 60870-5-103 Maste	r _ComFault	10000063	Organizational indication		myBinDAF_01	Binary
CCCL2DUEC 61890 Client/618500         C-Steueung/Q0_1-Position/Imeringe         10000019         Pulse sinching command         ImplumDAF_01         Numeric           CCCL2DUEC 61800 Client/618500         C-Steueung/Q0_1-Position/Imeringe         10000194         Organizational indication         ImplumDAF_01         Numeric           CCCL2DUEC 61800 Client/618500         C-Steueung/Q0_1-Position/Imeringe         10000574         Organizational indication         Immeric           CCL2DUEC 61800 Client/618500         C-Steueung/Q0_1-Position         10000580         Organizational indication         Immeric         Immeric           CCL2DUEC 61800 Client/618500         S-LastStepErrer         10000580         Organizational indication         Immeric         Immeric         Immeric           CCL2DUEC 61800 Client/618500         S-LastStepErrer         10000581         Pulse witching command         Immeric         Immeric         Immeric           CCL2DUEC 61800 Client/618500         S-Lasterung/Q1_1-Position         10000586         Pulse witching command         Immeric	CCCL2DEC 61890 Client618910         Chronic 1000092         Organizational indication         myNumDAF_01         Numeric           CCCL2DEC 61805 Olient618910         Chronic 10000971         Organizational indication         myNumDAF_02         Numeric           CCCL2DEC 61805 Olient618910         Chronic 11000071         Organizational indication         myNumDAF_02         Numeric           CCCL2DEC 61805 Olient618900         Chronic 11000071         Organizational indication         myNumDAF_02         Numeric           CCCL2DEC 61805 Olient618900         Chronic 1000072         Organizational indication         myNumDAF_02         Numeric           CCCL2DEC 61805 Olient618901         Systemary QL Position         1000058         Pule switching command         myNumDAF_02         Numeric           CCCL2DEC 61805 Olient618901         Systemary QL Position         1000058         Pule switching command         myNumDAF_02         Numeric           CCCL2DEC 61805 Olient618901         Systemary QL Position         1000058         Pule switching command         myNumDAF_02         Numeric           CCCL2DEC 61805 Olient618901         Systemary QL Position         1000059         Pule switching command         myNumDAF_02         MyNumDAF_02         MyNumDAF_02           CCL2DEC 61805 Olient618901         Systemary QL Position         1000059         Pule switching comman	SCCCL20\JEC 61850 Client	_Opr	10000088	Organizational indication		myBinDAF_02	Binary
CCL2DUEC 61850 Client/051800         Cynerus/021_Dosition-Ulwrerige         10000573         Organizational indication         Numeric           CCL2DUEC 61850 Client/051800         Cynerkadry         10000574         Organizational indication         Numeric           CCL2DUEC 61850 Client/051800         Cynerkadry         10000574         Organizational indication         Numeric           CCL2DUEC 61850 Client/051800         Sry LastStopEror         10000582         Organizational indication         Numeric           CCL2DUEC 61850 Client/051800         Sry LastStopEror         10000582         Organizational indication         Numeric           CCL2DUEC 61850 Client/051801         Steurung/021_Dosition-Ulwrerige         10000584         Pulse switching command         Numeric           CCL2DUEC 61850 Client/051801         Csteurung/021_Dosition-Ulwrerige         10000586         Pulse switching command         Numeric           CCL2DUEC 61850 Client/051801         Csteurung/021_Dosition-Ulwrerige         10000591         Pulse switching command         Numeric           CCL2DUEC 61850 Client/051801         Csteurung/021_Dosition-Ulwrerige         10000591         Pulse switching command         Numeric           CCL2DUEC 61850 Client/051801         Csteurung/021_Position-Ulwrerige         10000591         Pulse switching command         Numeric           CCL2DUEC 61850 Client/	CCL2DUEC 61830 Client/051800         CPReady         1000073         Organizational indication         Numeric           CCL2DUEC 61830 Client/051800         Confrault         10000774         Organizational indication         Numeric           CCL2DUEC 61830 Client/051800         Confrault         10000784         Organizational indication         Numeric           CCL2DUEC 61830 Client/051800         Op         10000580         Organizational indication         Numeric           CCL2DUEC 61830 Client/051800         Statestrup/QL Position         10000581         Pulse witching command         Numeric           CCL2DUEC 61830 Client/051800         Statestrup/QL Position         10000581         Pulse witching command         Numeric           CCL2DUEC 61830 Client/051800         Steterung/QL Position         10000581         Pulse witching command         Numeric           CCL2DUEC 61830 Client/051800         Steterung/QL Position         10000581         Pulse witching command         Numeric           CCL2DUEC 61830 Client/051801         Steterung/QL Position         10000581         Pulse witching command         Numeric           CCL2DUEC 61830 Client/051801         Steterung/QL Position         10000590         Pulse witching command         Numeric           CCL2DUEC 61830 Client/051801         Steterung/QL Positon         10000591         Pulse w	SCCCL20\JEC 61850 Client\61850	II _Opr	10000092	Organizational indication		myNumDAF_01	Numeric
CCL2DUEC 61850 Client/61850         Confault         10000574         Organizational indication           CCL2DUEC 61850 Client/61850         Confault         10000574         Organizational indication           CCL2DUEC 61850 Client/61850         Confault         10000580         Organizational indication         Indication           CCL2DUEC 61850 Client/61850         CStuetturg/OQL_Position         10000582         Organizational indication         Indication           CCL2DUEC 61850 Client/61850         CStuetturg/OQL_Position         10000584         Pulse switching command           CCL2DUEC 61850 Client/618500         CStueturg/OQL_Position         10000586         Pulse switching command           CCL2DUEC 61850 Client/618500         CStueturg/QL_Position         10000586         Pulse switching command           CCL2DUEC 61850 Client/618500         CStueturg/QL_Position Inverriege         10000598         Pulse switching command           CCL2DUEC 61850 Client/618500         CStueturg/QL_Position Inverriege         10000591         Pulse switching command           CCL2DUEC 61850 Client/618500         CStueturg/QL_Position Inverriege         10000592         Pulse switching command           CCL2DUEC 61850 Client/618500         Cstueturg/QL_Position Inverriege         10000594         Single-point indication           CCL2DUEC 61850 Client/618500         Cstueturg/QL_Position Inver	CCL2DUEC 61830 Client/61830         Charles/Sell         Mumerischer Filter 1         Numerischer Filter 1           CCL2DUEC 61830 Client/61830         Op         10000574         Organizational indication           CCL2DUEC 61830 Client/618300         Op         10000580         Organizational indication           CCL2DUEC 61830 Client/618301         SilastStepError         10000582         Organizational indication           CCL2DUEC 61830 Client/618301         SilastStepError         10000584         Paties witching command           CCL2DUEC 61830 Client/618301         SilastStepError         10000585         Paties witching command           CCL2DUEC 61830 Client/618301         Silasterumg/O2 1-Positon Ilumering         10000586         Paties witching command           CCL2DUEC 61830 Client/618301         Silasterumg/O2 1-Positon Ilumering         10000587         Paties witching command           CCL2DUEC 61830 Client/618301         Steurung/O2 1-Positon Ilumering         10000580         Paties witching command           CCL2DUEC 61830 Client/618301         Steurung/O2 1-Positon Ilumering         10000591         Paties witching command           CCL2DUEC 61830 Client/618301         Steurung/O2 1-Positon Ilumering         10000592         Paties witching command           CCL2DUEC 61830 Client/618301         Steurung/O2 1-Positon Ilumering         10000595         Single-point indi	SCCCL20\IEC 61850 Client\61850	C_Steuerung/Q0_1.Position.Unverriege	10000109	Pulse switching command		F myNumDAF_02	Numeric
CCL2DUEC 61850 Client618500         _Comfault         10000574         Organizational indication           CCL2DUEC 61850 Client618500         SYL LestSperfor         10000582         Organizational indication           CCL2DUEC 61850 Client618500 <stl lestsperfor<="" td="">         10000584         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000584         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000586         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000587         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000587         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000587         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000589         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000589         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000591         Pulse switching command           CCL2DUEC 61850 Client618500         <steurung q0_1position<="" td="">         10000591         Pulse switching command</steurung></steurung></steurung></steurung></steurung></steurung></steurung></steurung></steurung></stl>	CCL2DUEC 61850 Client/61850         ComFault         1000074         Organizational indication           CCL2DUEC 61850 Client/618500         YS_LastSopErrer         10000580         Organizational indication         Indication           CCL2DUEC 61850 Client/618500         C_Steurung/Q2_1Position         10000584         Pules witching command           CCL2DUEC 61850 Client/618500         C_Steurung/Q2_1Position         10000584         Pules witching command           CCL2DUEC 61850 Client/618500         C_Steurung/Q2_1Position/Unversige         10000586         Pules witching command           CCL2DUEC 61850 Client/618500         C_Steurung/Q2_1Position/Unversige         10000586         Pules witching command           CCL2DUEC 61850 Client/618500         C_Steurung/Q2_1Position/Unversige         10000586         Pules witching command           CCL2DUEC 61850 Client/618500         C_Steurung/Q2_1Position/Unversige         10000597         Pules witching command           CCL2DUEC 61850 Client/618500         C_steurung/Q2_1Position/Unversige         10000591         Pules witching command           CCL2DUEC 61850 Client/618500         C_steurung/Q2_1Position         10000592         Pules witching command           CCL2DUEC 61850 Client/618500         Steurung/SQ1_Position/Unversige         10000592         Pules witching command           CCL2DUEC 61850 Client/618500         Steurung/Q2_1Posit	SCCCL20\IEC 61850 Client\61850	II _OprReady	10000573	Organizational indication		Numerischer Filter 1	Numeric
CCL2DUEC 61850 Client/61850         Cyr         10000580         Organizational indication           CCL2DUEC 61850 Client/618501         SchutsLLN05PS5CE         10000582         Stepoint analog, standardized           CCL2DUEC 61850 Client/618501         SchutsLLN05PS5CE         10000583         Stepoint analog, standardized           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position IMverriege         10000586         Pulse witching command           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position IMverriege         10000586         Pulse witching command           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position IMverriege         10000588         Pulse witching command           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position IMverriege         10000598         Pulse witching command           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position IMverriege         10000598         Pulse witching command           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position IMverriege         10000592         Pulse witching command           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position IMverriege         10000592         Pulse witching command           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position IMverriege         10000592         Pulse witching command           CCL2DUEC 61850 Client/618501         Steurung/QL I-Position	CCL2DUEC 61850 Client/61850         Cyr         10000582         Organizational indication           CCL2DUEC 61850 Client/618501         CychutSLLN05SP55CE         10000582         Stepoint analog, standardized           CCL2DUEC 61850 Client/618501         CychutSLLN05SP55CE         10000582         Pulse witching command           CCL2DUEC 61850 Client/618501         CychutSLLN05SP55CE         10000586         Pulse witching command           CCL2DUEC 61850 Client/618501         Cysteerung/QL 1-Position         10000586         Pulse witching command           CCL2DUEC 61850 Client/618501         Cysteerung/QL 1-Position         10000586         Pulse witching command           CCL2DUEC 61850 Client/618501         Cysteerung/QL 1-Position         10000588         Pulse witching command           CCL2DUEC 61850 Client/618501         Cysteerung/QL 1-Position         10000588         Pulse witching command           CCL2DUEC 61850 Client/618501         Cysteerung/QL 1-Position         10000598         Pulse witching command           CCL2DUEC 61850 Client/618501         Cysteerung/QL 1-Position         10000598         Pulse witching command           CCL2DUEC 61850 Client/618501         Cysteerung/QL 1-Position         10000599         Pulse witching command           CCL2DUEC 61850 Client/618501         Steuerung/QL 1-Position         10000599         Single-point indication <td>CCCL20\IEC 61850 Client\61850</td> <td>ComFault</td> <td>10000574</td> <td>Organizational indication</td> <td></td> <td></td> <td></td>	CCCL20\IEC 61850 Client\61850	ComFault	10000574	Organizational indication			
CCL2DUEC 61850 Client615800 (S-ChutSLLM05SPSCCE)         10000582         Object and additional control of the set of the se	CCL2DUEC 61850 Climen618500 (S-thurstLN058756C8 1000783 Septint analog, standardized           CCL2DUEC 61850 Climen618500 (S-thurstLN058756C8 1000783 Pulse witching command           CCL2DUEC 61850 Climen618500 (S-thurstLN058756C8 1000783 Pulse witching command           CCL2DUEC 61850 Climen618500 (S-thurstLN058756C8 1000783 Pulse witching command           CCL2DUEC 61850 Climen618500 (S-thurstLN05870 Pulse witching command           CCL2DUEC 61850 Climen618500 (S-thurstLN05800 Pulse witching command           CCL2DUEC 61850 Climen618500 (S-thurstLN0590 Pulse witching command           CCL2DUEC 61850 Climen618500 Steurung/02.Position Hurstleig H000595 Pulse witching command           CCL2DUEC 61850 Climen618500 Steurung/02.Position Hurstleig H000595 Single-point indication           CCL2DUEC 61850 Climen618500 Steurung/02.Position Hurstleig H000595 Single-point indication           CCL2DUEC 61850 Climen618500 Steurung/02.Position Hurstleig H000595 Single-point indication           CCL2DUEC 61850 Climen618500 Steurung/02.Position Hurstleig H000596 Single-point indication	CCCL20\JEC 61850 Client\61850	lf_Opr	10000580	Organizational indication		H	
CCL2DUEC 61850 Client618508 (_Schurz5LUNSSPSSCC8         1000583         Setpoint analog, standardized           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position IUmerriege         1000584         Pules withching command           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000586         Pules withching command           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000586         Pules withching command           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000588         Pules withching command           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000580         Pules withching command           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000590         Pules withching command           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000592         Pules withching command           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000593         Pules withching command           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000595         Single-point indication           CCL2DUEC 61850 Client618508 (_Steurung/Q)_1Position Unwerriege         1000595         Single-point indication           CCL2DUEC 61850 Client618508 (Steurung/Q)_1Position Unwerriege         1000595         Single-point indication           CCL2DUEC 61850 Client618508 (Steurung/Q)_1Position U	CCL2DUEC 61850 Climeh61850[Schurz5LU055PSGC8 1000584         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position IUmerrige         1000585         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position IUmerrige         1000586         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position IUmerrige         1000586         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position IUmerrige         1000587         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position IUmerrige         1000587         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position IUmerrige         1000597         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position I         1000598         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position I         1000598         Pulse switching command           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position I         1000598         Single-point indication           CCL2DUEC 61850 Climeh61850[Steurung/Q1_Position IUmerrige         1000595         Single-point indication           CCL2DUEC 61850 Climeh61850[ _Steurung/Q1_Position IUmerrige         1000598         Single-point indication           CCL2DUEC 61850 Climeh61850[ _Steurung/Q1_Position.IUmerriges I         1000595         Single-point indi	CCCL20\IEC 61850 Client\61850	IF SYS_LastStopError	10000582	Organizational indication			
CLUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000585         Pulse withing command           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000585         Pulse withing command           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000586         Pulse withing command           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000587         Pulse withing command           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000598)         Pulse withing command           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000595)         Pulse withing command           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000595)         Pulse withing command           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000595         Single-point indication           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000596         Single-point indication           CCUZUE ClassO Clamb13503 (Steurung/QL_Position.Umerriege 1000596         Single-point indication           CCUZUE ClassO Clamb13503 (Steurung/QL_Position         10000596         Single-point indication           CCUZUE ClassO Clamb13503 (Steurung/QL_Positi	CLCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000586         Pulse withing command           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000586         Pulse withing command           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000587         Pulse withing command           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000586         Pulse withing command           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000587         Pulse withing command           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000598         Pulse withing command           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000599         Pulse withing command           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000592         Pulse withing command           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000594         Single-point indication           CCLUVEC 61350 Clemh61350(_Stevenung/QL1Position.Uwerrige)         10000597         Singl	SCCCL20\IEC 61850 Client\61850	c_Schutz\$LLN0\$SP\$SGCB	10000583	Setpoint analog, standardized			
CCL2DUEC 61850 Client618500 _SteurungQ1_Position_Unverrige         10000586         Pulse switching command           CCL2DUEC 61850 Client618500 _SteurungQ1_Position 10000590         Pulse switching command           CCL2DUEC 61850 Client618500 _SteurungQ1_Position_Unverrige 10000591         Pulse switching command           CCL2DUEC 61850 Client618500 _SteurungQ1_Position_Unverrige 10000591         Pulse switching command           CCL2DUEC 61850 Client618500 _SteurungQ1_Position_Unverrige 10000593         Pulse switching command           CCL2DUEC 61850 Client618500 _SteurungQ1_Position_Unverrige 10000593         Single-point indication           CCL2DUEC 61850 Client618500 Steurung/Stourg_Smmemledug         10000595         Single-point indication           CCL2DUEC 61850 Client618500 Steurung/C0_1_Position Unverrige1 10000595         Single-point indication         CCL2DUEC 61850 Client618500 Steurung/C0_1_Position Unverrige1 10000595           CCL2DUEC 61850 Client618500 Steurung/C0_1_Position Unverrige1 10000597         Single-point indication         CCL2DUEC 61850 Client618500 Steurung/C0_1_Position Unverrige1 10000597           CCL2DUEC 61850 Client618500 Steurung/C0_1_Position Unverrige1 10000597         Single-point indication	CCL2DUEC 61850 Clem6163800       Steurung/Q1_Position.Unverriege       10000586       Pulse writching command         CCL2DUEC 61850 Clem6163800       Steurung/Q1_Position.Unverriege       10000587       Pulse writching command         CCL2DUEC 61850 Clem6163800       Steurung/Q1_Position.Unverriege       10000587       Pulse writching command         CCL2DUEC 61850 Clem6163800       Steurung/Q2_Position.Unverriege       10000589       Pulse writching command         CCL2DUEC 61850 Clem6163800       Steurung/Q2_Position.Unverriege       10000590       Pulse writching command         CCL2DUEC 61850 Clem6163800       Steurung/Q2_Position.Unverriege       10000592       Pulse writching command         CCL2DUEC 61850 Clem6163800       Steurung/Q3_Position.Unverriege       10000592       Pulse writching command         CCL2DUEC 61850 Clem6163800       Steurung/Q3_Position.Unverriege       10000595       Single-point indication         CCL2DUEC 61850 Clem6163800       Steurung/A1gemein.Schlohett       10000595       Single-point indication         CCL2DUEC 61850 Clem6163800       Steurung/A1gemein.Schlohett       10000596       Single-point indication         CCL2DUEC 61850 Clem6163800       Steurung/A1gemein.Schlohett       10000596       Single-point indication         CCL2DUEC 61850 Clem6163800       Steurung/A1gemein.Schlohett       10000596       Single-point indication <td>CCCL20\IEC 61850 Client\61850</td> <td>If c_Steuerung/Q0_1.Position</td> <td>10000584</td> <td>Pulse switching command</td> <td></td> <td></td> <td></td>	CCCL20\IEC 61850 Client\61850	If c_Steuerung/Q0_1.Position	10000584	Pulse switching command			
CCL2DUEC 61850 Clenhf15800         SteurungQL1Position.Umerringe 10000587         Pulse switching command           CCL2DUEC 61850 Clenhf15800         SteurungQL1Position.Umerringe 10000587         Pulse switching command           CCL2DUEC 61850 Clenhf15800         SteurungQL2.Position.Umerringe 10000588         Pulse switching command           CCL2DUEC 61850 Clenhf15800         SteurungQL2.Position.Umerringe 10000597         Pulse switching command           CCL2DUEC 61850 Clenhf15800         SteurungQL2.Position.Umerringe 10000597         Pulse switching command           CCL2DUEC 61850 Clenhf15800         SteurungQL2.Position.Umerringe 10000593         Single-point indication           CCL2DUEC 61850 Clenhf15800         SteurungQL2.Position.Umerringe 10000595         Single-point indication           CCL2DUEC 61850 Clenhf15800         SteurungQL2.Position.Umerringe1         10000596         Single-point indication           CCL2DUEC 61850 Clenhf15800         SteurungQL2.Position.Umerringe1         10000598         Double-point indication           CCL2DUEC 61850 Clenhf15800         SteurungQL2.P	CCL2DUEC 61850 Clenh618500         SteurungQ1_Position Unverrige         10000580         Pulse witching command           CCL2DUEC 61850 Clenh618500         SteurungQ1_Position Unverrige         10000580         Pulse witching command           CCL2DUEC 61850 Clenh618500         SteurungQ1Q_1Position Unverrige         10000580         Pulse witching command           CCL2DUEC 61850 Clenh618500         SteurungQ1Q_1Position Unverrige         10000590         Pulse witching command           CCL2DUEC 61850 Clenh618500         SteurungQ1Q_1Position Unverrige         10000590         Pulse witching command           CCL2DUEC 61850 Clenh618500         SteurungQ1Q_1Position Unverrige         10000593         Pulse witching command           CCL2DUEC 61850 Clenh618500         SteurungQ1Q_1Position Unverrige         10000593         Pulse witching command           CCL2DUEC 61850 Clenh618500         SteurungQ1Q_1Position Unverrige         10000595         Single-point indication           CCL2DUEC 61850 Clenh618500         SteurungQ1Q_1Position Unverrige1         10000596         Single-point indication           CCL2DUEC 61850 Clenh618500         SteurungQ0_1Position Unverrige1         10000597         Single-point indication           CCL2DUEC 61850 Clenh618500         SteurungQ0_1Position Selekteri         10000598         Double-point indication           CCL2DUEC 61850 Clenh618500         SteurungQ0_1Position	SCCCL20\IEC 61850 Client\61850	I c_Steuerung/Q0_1.Position.Unverriege	10000585	Pulse switching command			
CLCLDVIEC 61830 Clenth618300         Steurung/QL_Position 10000588         Pulse switching command           CLCLDVIEC 61850 Clenth618500         Steurung/QL_Position 10000589         Pulse switching command           CLCLDVIEC 61850 Clenth618501         Steurung/QL_Position 10000589         Pulse switching command           CLCLDVIEC 61850 Clenth618501         Steurung/QL_Position 10000590         Pulse switching command           CLCLDVIEC 61850 Clenth618501         Steurung/QL_Position 10000590         Pulse switching command           CLCLDVIEC 61850 Clenth618501         Steurung/QL_Position 10000591         Pulse switching command           CLCLDVIEC 61850 Clenth618501         Steurung/QL_Position 10000592         Pulse switching command           CLCLDVIEC 61850 Clenth618501         Steurung/QL_Position 10000593         Single-point indication           CLCLDVIEC 61850 Clenth618501         Steurung/Strung Sammelmedlung         10000594         Single-point indication           CLCLDVIEC 61850 Clenth618501         Steurung/QL_Position 1         10000597         Single-point indication           CLCLDVIEC 61850 Clenth618503         Steurung/QL_Position 1         10000597         Single-point indication           CLCLDVIEC 61850 Clenth618503         Steurung/QL_Position 1         10000597         Single-point indication           CLLDVIEC 61850 Clenth618503         Steurung/QL_Position 10000597         Single-point	CLCLDUE C1830 Clenth15300         Cysterung/Q1_Position.Unverriege         10000580         Pulse switching command           CCLDUE C1830 Clenth15300         Cysterung/Q1_Position.Unverriege         10000580         Pulse switching command           CCLDUE C1830 Clenth15300         Cysterung/Q1_Position.Unverriege         10000590         Pulse switching command           CCLDUE C1830 Clenth15300         Cysterung/Q1_Position.Unverriege         10000590         Pulse switching command           CCLDUE C1830 Clenth15300         Cysterung/Q1_Position.Unverriege         10000591         Pulse switching command           CCLDUE C1830 Clenth15300         Cysterung/Q1_Position.Unverriege         10000592         Pulse switching command           CCLDUE C1830 Clenth15300         Sterung/Q1_Position.Unverriege         10000594         Single-point indication           CCLDUE C1830 Clenth15301         Sterung/Q1_Position.Unverriege         10000594         Single-point indication           CCLDUE C1830 Clenth15301         Sterung/Q1_Position.Unverriege         10000596         Single-point indication           CCLDUE C1830 Clenth15301         Sterung/Q1_Position.Unverriege         10000598         Duuble-point indication           CCLDUE C1830 Clenth15801         Sterung/Q1_Position.Unverriege         10000598         Duuble-point indication           CCLDUE C1830 Clenth158030         Sterung/Q1_Position.Unverriege1	CCCL20\IEC 61850 Client\61850	If c_Steuerung/Q1_1.Position	10000586	Pulse switching command			
CLCUDIC 61850 Clenth51800 (Steurung/QL1Position.Umerriege) 1000589         Pulse switching command           CCLUDIC 61850 Clenth51800 (Steurung/QL1Position.Umerriege) 1000599         Pulse switching command           CCLUDIC 61850 Clenth51800 (Steurung/QL1Position.Umerriege) 1000599         Pulse switching command           CCLUDIC 61850 Clenth618500 (Steurung/QL1Position.Umerriege) 1000599         Pulse switching command           CCLUDIC 61850 Clenth618500 (Steurung/QL1Position.Umerriege) 1000599         Pulse switching command           CCLUDIC 61850 Clenth618500 (Steurung/QL1Position.Umerriege) 1000593         Pulse switching command           CCLUDIC 61850 Clenth618500 (Steurung/Stourg,Smmelmedlug) 1000594         Single-point indication           CCLUDIC 61850 Clenth618500 (Steurung/Stourg,Smmelmedlug) 1000595         Single-point indication           CCLUDIC 61850 Clenth618500 (Steurung/OL).Position.Umerriege) 1000595         Single-point indication           CCLUDIC 61850 Clenth618500 (Steurung/OL).Position.Umerriege) 1000595         Single-point indication           CCLUDIC 61850 Clenth618500 (Steurung/OL).Position.Umerriege) 1000595         Single-point indication           CCLUDIC 61850 Clenth618500 (Steurung/OL).Position.Selektiet 10000595         Single-point indication           CCLUDIC 61850 Clenth618500 (Steurung/OL).Position.Selektiet 10000595         Single-point indication           CCLUDIC 61850 Clenth618500 (Steurung/OL).Position.Selektiet 10000603         Single-point indication	CLCLUDUE Cl3SD Clenhf35301         Cysteurung/Q1_Position.Umerreige         10000589         Pulse switching command           CCLUDUE Cl3SD Clenhf35301         Cysteurung/Q1_Position.Umerreige         10000590         Pulse switching command           CCLUDUE Cl3SD Clenhf35301         Cysteurung/Q1_Position.Umerreige         10000590         Pulse switching command           CCLUDUE Cl3SD Clenhf35301         Cysteurung/Q1_Position.Umerreige         10000590         Pulse switching command           CCLUDUE Cl3SD Clenhf35301         Cysteurung/Q1_Position.Umerreige         10000592         Pulse switching command           CCLUDUE Cl3SD Clenhf35301         Cysteurung/C9_1-Position.Umerreige         10000594         Pulse switching command           CCLUDUE Cl3SD Clenhf35301         Steurung/Staumg/StammeIndug         10000595         Single-point indication           CCLUDUE Cl3SD Clenhf35301         Steurung/C1_Position.Umerreige1         10000595         Single-point indication           CCLUDUE Cl3SD Clenhf35301         Steurung/C0_1_Position.Umerreige1         10000595         Single-point indication           CCLUDUE Cl3SD Clenhf35301         Steurung/C0_1_Position.Umerreige1         10000596         Single-point indication           CCLUDUE Cl3SD Clenhf35301         Steurung/C1_1_Position.Umerreige1         10000599         Single-point indication           CCL2DUE Cl3SD Clenhf35301         Steurung/C1	CCCL20\IEC 61850 Client\61850	I c_Steuerung/Q1_1.Position.Unverriege	10000587	Pulse switching command			
CCLUDIEC 61890 Client/61890         Exteurum/Q2_1Position/Liveringe         10000590         Pulse witching command           CCLUDIEC 61850 Client/61890         Exteurum/Q2_1Position/Liveringe         10000590         Pulse witching command           CCLUDIEC 61850 Client/61890         Exteurum/Q2_1Position/Liveringe         10000591         Pulse witching command           CCLUDIEC 61850 Client/61890         Exteurum/Q2_1Position/Liveringe         10000592         Pulse witching command           CCLUDIEC 61850 Client/61890         Exteurum/Q3_1Position/Liveringe         10000592         Pulse witching command           CCLUDIEC 61850 Client/618501         Exteurum/Q3_1Position/Liveringe         10000593         Pulse witching command           CCLUDIEC 61850 Client/618501         Exteurum/Q3_1Position/Liveringe         10000596         Single-point indication           CCLUDIEC 61850 Client/618501         Exteurum/Q3_1Position         10000597         Single-point indication           CCLUDIEC 61850 Client/618501         Exteurum/Q3_1Position         10000598         Double-point indication           CCLUDIEC 61850 Client/618501         Exteurum/Q3_1Position         10000597         Single-point indication           CCLUDIEC 61850 Client/618501         Exteurum/Q3_1Position         10000598         Single-point indication           CCLUDIEC 61850 Client/618501         Exteurum/Q3_1Position <t< td=""><td>CCLC2DUEC 61850 Clem618500         C-Steurung/Q2_1-Position         10000590         Pulse witching command           CCL2DUEC 61850 Clem618500         C-Steurung/Q2_1-Position         10000590         Pulse witching command           CCL2DUEC 61850 Clem618500         C-Steurung/Q2_1-Position         10000590         Pulse witching command           CCL2DUEC 61850 Clem618500         C-steurung/Q2_1-Position         10000592         Pulse witching command           CCL2DUEC 61850 Clem618500         Steurung/Storung Ammanmelmed/g         10000592         Pulse witching command           CCL2DUEC 61850 Clem618500         Steurung/Storung Ammanmelmed/g         10000594         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Storung Ammanmelmed/g         10000596         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q0_1-Position         10000597         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q0_1-Position         10000599         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q0_1-Position         10000599         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q1_1-Position         10000600         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q1_1-Position-Inverrieget         10000601         Single-point in</td><td>SCCCL20/IEC 61850 Client/61850</td><td>If c_Steuerung/Q2_1.Position</td><td>10000588</td><td>Pulse switching command</td><td></td><td></td><td></td></t<>	CCLC2DUEC 61850 Clem618500         C-Steurung/Q2_1-Position         10000590         Pulse witching command           CCL2DUEC 61850 Clem618500         C-Steurung/Q2_1-Position         10000590         Pulse witching command           CCL2DUEC 61850 Clem618500         C-Steurung/Q2_1-Position         10000590         Pulse witching command           CCL2DUEC 61850 Clem618500         C-steurung/Q2_1-Position         10000592         Pulse witching command           CCL2DUEC 61850 Clem618500         Steurung/Storung Ammanmelmed/g         10000592         Pulse witching command           CCL2DUEC 61850 Clem618500         Steurung/Storung Ammanmelmed/g         10000594         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Storung Ammanmelmed/g         10000596         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q0_1-Position         10000597         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q0_1-Position         10000599         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q0_1-Position         10000599         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q1_1-Position         10000600         Single-point indication           CCL2DUEC 61850 Clem618500         Steurung/Q1_1-Position-Inverrieget         10000601         Single-point in	SCCCL20/IEC 61850 Client/61850	If c_Steuerung/Q2_1.Position	10000588	Pulse switching command			
CLCLOVIC 61830 Clenth61830(_SteverungQL_Position.Unverriege)         Pulse switching command           CCLOVIC 61830 Clenth61830(_SteverungQL_Position.Unverriege)         Pulse switching command           CCLOVIC 61830 Clenth61830(_SteverungQL_Position.Unverriege)         Pulse switching command           CCLOVIC 61830 Clenth61830(_SteverungQL_Position.Unverriege)         Single-point indication           CCLOVIC 61830 Clenth61850(_SteverungQL_Position.Unverriege)         Single-point indication           CCLOVIC 61830 Clenth61850(_SteverungVQL_Position.Unverriege)         Single-point indication           CCLOVIC 61830 Clenth61850(_SteverungVQL_Position.Unverriege)         10000597         Single-point indication           CCLOVIC 61830 Clenth61850(_SteverungVQL_Position.SteverungVQL_Position.Unverriege)         10000590         Single-point indication           CCLOVIC 61830 Clenth61850(_SteverungVQL_Position.Unverriege)         10000600         Single-point indication           CCLOVIC 61830 Clenth61850(_SteverungVQL_Position.Unverriege)         10000600         Single-point indication           CCLOVIC 61850 Clenth61850(_St	CLCLOVEC 61850 Clenh61850(_SteverungQE_1-Position Unverrige)         10000591         Pulse withing command           CCLOVEC 61850 Clenh61850(_SteverungQE_1-Position Unverrige)         10000592         Pulse withing command           CCLOVEC 61850 Clenh61850(_SteverungQE_1-Position Unverrige)         10000592         Pulse withing command           CCLOVEC 61850 Clenh61850(_SteverungQE_1-Position Unverrige)         10000593         Pulse withing command           CCLOVEC 61850 Clenh61850(_SteverungQE_1-Position Unverrige)         10000593         Pulse withing command           CCLOVEC 61850 Clenh61850(_SteverungAIstermineHeld 10000595         Single-point indication           CCLOVEC 61850 Clenh61850(_SteverungAIstermineHeld 10000595         Single-point indication           CCLOVEC 61850 Clenh61850(_SteverungAIstermineHeld 10000595         Single-point indication           CCLOVEC 61850 Clenh61850(_SteverungAIstermineHeld 10000596         Single-point indication           CCLOVEC 61850 Clenh61850(_SteverungAIstermineHeld 10000603         Single-point indication	SCCCL20/IEC 61850 Client/61850	I c_Steuerung/Q2_1.Position.Unverriege	10000589	Pulse switching command		<b>  </b>	
CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Unverriegel         D000592         Pulse switching command           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Unverriegel         D000592         Pulse switching command           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Unverriegel         D000592         Pulse switching command           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Unverriegel         D000595         Single-point indication           CLCLOVIC 61850 Clenth61850(_Steurung)G10000000         Single-point indication         CLCLOVIC 61850 Clenth61850(_Steurung)G100000000           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Unverriegel         D0000596         Single-point indication           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Unverriegel         D0000599         Double-point indication           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Unverriegel         D0000000         Single-point indication           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Selekitet         10000600         Single-point indication           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Selekitet         10000600         Single-point indication           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Selekitet         10000601         Double-point indication           CLCLOVIC 61850 Clenth61850(_Steurung)Q_1_Position.Selekitet         10000602         Single-point indication           CLLOVIC 61850 Clenth61850(_Steu	CLCLOVEC 61850 Clenkfib300         SteverungQQ_1-Position Liverrige         10000592         Pulse switching command           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000592         Pulse switching command           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000592         Pulse switching command           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000595         Single-point indication           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000595         Single-point indication           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000596         Single-point indication           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000596         Single-point indication           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000597         Single-point indication           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000600         Single-point indication           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000601         Single-point indication           CCLOVEC 61850 Clenkfib301         SteverungQQ_1-Position Liverrige         10000603         Single-point indication           CCLOVEC 61850 Clenkfib301         SteverungQ	SCCCL20/JEC 61850 Client/61850	It c_Steuerung/Q8_1.Position	10000590	Pulse switching command			
CLCLDUEC 61830 Client618500         Csteurung/Q2_1Position_Unwerrige         U0000992         Pulse switching command           CLCLDUEC 61830 Client618500         Steurung/S1000994         Single-point indication           CLCLDUEC 61850 Client618500         Steurung/S1000997         Single-point indication           CLCLDUEC 61850 Client618500         Steurung/S1000997         Single-point indication           CLCLDUEC 61850 Client618500         Steurung/C0_1Position         U0000997         Single-point indication           CLCLDUEC 61850 Client618500         Steurung/C0_1Position         U0000999         Single-point indication           CLCLDUEC 61850 Client618500         Steurung/C0_1Position         U0000600         Single-point indication           CLLDUEC 61850 Client618500         Steurung/C0_1Position         U0000601         Double-point indication           CLLDUEC 61850 Client618500         Steurung/C0_1Position.Unwerriget         10000601         Double-point indication           CLLDUEC 61850 Client618500         Steurung/	CCLCDUEC 61850 Client618500         Steurung/02_1-Position Unverriegel         Pulse winkling command           CCLCDUEC 61850 Client618500         Steurung/03_1-Position Unverriegel         Pulse winkling command           CCLCDUEC 61850 Client618500         Steurung/03_1-Position Unverriegel         Pulse winkling command           CCLCDUEC 61850 Client618500         Steurung/03_1-Position Unverriegel         Pulse winkling           CCLCDUEC 61850 Client618500         Steurung/03_1-Position Unverriegel         Pulse winkling           CCLCDUEC 61850 Client618500         Steurung/00_1-Position         Pulse winkling           CCLCDUEC 61850 Client618500         Steurung/00_1-Position         Pulse winkling           CCLCDUEC 61850 Client618500         Steurung/00_1-Position         Pulse winkling           CCLDUEC 61850 Client618500         Steurung/00_1-Position         Pulse winkling           CCLDUEC 61850 Client618500         Steurung/01_1-Position Unverriegel         Double-point indication           CCLDUEC 61850 Client618500         Steurung/02_1-Position Unverriegel	SCCCL20/IEC 61850 Client/61850	II c_Steuerung/Q8_1.Position.Unverriege	10000591	Pulse switching command			
CLCLOVIC 61830 Client/618301 Steueung/CLPosition.Unverrieget         10000594         Single-point indication           CLCLOVIC 61830 Client/618301 Steueung/CLPosition.Unverrieget         10000594         Single-point indication           CLCLOVIC 61830 Client/618301 Steueung/CLPosition.Unverrieget         10000594         Single-point indication           CLCLOVIC 61830 Client/618301 Steueung/CLPosition.Unverrieget         10000595         Single-point indication           CLCLOVIC 61830 Client/618301 Steueung/CLPosition.Unverrieget         10000598         Double-point indication           CLCLOVIC 61830 Client/618303 Steueung/CLPosition.Unverrieget         10000598         Double-point indication           CLCLOVIC 61830 Client/618303 Steueung/CLPosition.Setketiet         10000599         Single-point indication           CLCLOVIC 61830 Client/618303 Steueung/CLPosition.Setketiet         10000590         Single-point indication           CLCLOVIC 61830 Client/618303 Steueung/CLLPosition.Setketiet         10000600         Single-point indication           CLCLOVIC 61830 Client/618303 Steueung/CLLPosition.Setketiet         10000602         Single-point indication           CLCLOVIC 61830 Client/618303 Steueung/CLLPosition.Setketiet         10000602         Single-point indication           CLCLOVIC 61830 Client/618303 Steueung/CLLPosition.Setketiet         10000603         Single-point indication           CLLOVIC 61830 Client/618303 Steueung/CLLPosition.Setketiet	CCLC2DUEC 61850 Client618500         Steurung/Q0_LPosition.Umerrieget         10000594         Single-point indication           CCLC2DUEC 61850 Client618500         Steurung/Q0_LPosition.Umerrieget         10000594         Single-point indication           CCLC2DUEC 61850 Client618500         Steurung/Q0_LPosition.Umerrieget         10000594         Single-point indication           CCLC2DUEC 61850 Client618500         Steurung/Q0_LPosition.Umerrieget         10000596         Single-point indication           CCLC2DUEC 61850 Client618500         Steurung/Q0_LPosition.Umerrieget         10000597         Single-point indication           CCLC2DUEC 61850 Client618500         Steurung/Q0_LPosition.Umerrieget         10000596         Single-point indication           CCLC2DUEC 61850 Client618500         Steurung/Q1_LPosition.Umerrieget         10000596         Single-point indication           CCLC2DUEC 61850 Client618500         Steurung/Q1_LPosition.Umerrieget         10000600         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/Q1_LPosition.Umerrieget         10000601         Double-point indication           CCL2DUEC 61850 Client618500         Steurung/Q2_LPosition.Umerrieget         10000603         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/Q2_LPosition.Umerrieget         10000664         Double-point indication           CCL2DUEC 61850 Client618	CCCL20/JEC 61850 Client(61850	In c_steuerung/Q9_1.Position	10000592	Pulse switching command		<b>  </b>	
CLCDUEC 61850 Clenth618501 Steurung/CLPosition Jammendeugl (2000595         Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CLPosition Umerriegel 10000596         Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CLPosition Umerriegel 10000596         Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CLPosition Umerriegel 10000597         Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CLPosition Umerriegel 10000597         Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CL_Position Umerriegel 10000598         Double-point indication           CLCDUEC 61850 Clenth618501 Steurung/CL_Position Umerriegel 10000598         Double-point indication           CLCDUEC 61850 Clenth618501 Steurung/CL_Position Umerriegel 10000600 Single-point indication         CLCDUEC 61850 Clenth618501 Steurung/CL_Position Umerriegel 10000603 Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CL_Position Settert         10000603 Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CL_Position Settert         10000603 Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CL_Position Settert         10000603 Single-point indication           CLCDUEC 61850 Clenth618501 Steurung/CL_Position Umerriegel 10000603 Single-point indication         CLCDUEC 61850 Clenth618501 Steurung/CL_Position Settert           CLCDUEC 61850 Clenth618501 Steurung/CL_Position Umerriegel 10000605 Single-point indication         CLCDUEC 61850 Clenth618501 Steurung/CL_	CCL2DUEC 61350 Client/613500         Steurung/Client/613500         Steurung/Client/613500         Steurung/Client/613500	CCCL20/IEC 61850 Client/61850	In C_Steuerung/Q9_1.Position.Unverriege	10000593	Pulse switching command			
CLCLOVIC 61830 Clerkfib300         Steverung/Q1_proving/warmsammemied         2000393         Single-point indication           CLCLOVIC 61830 Clerkfib300         Steverung/Q0_proving/warmsammemied         2000397         Single-point indication           CLCLOVIC 61830 Clerkfib300         Steverung/Q0_proving/warmsammemied         2000397         Single-point indication           CCLOVIC 61830 Clerkfib300         Steverung/Q0_proving/warmsammemied         2000397         Single-point indication           CCLOVIC 61830 Clerkfib300         Steverung/Q0_proving/warmsammemied         2000398         Double-point indication           CCLOVIC 61830 Clerkfib300         Steverung/Q0_proving/warmsammemied         2000399         Single-point indication           CCLOVIC 61830 Clerkfib3000         Single-point indication             CCLOVIC 61830 Clerkfib3000         Single-point indication             CCLOVIC 61830 Clerkfib3000         Single-point indication             CCLOVIC 61830 Clerkfib3000         Single-point indication             CCLOVIC 61830 Clerkfib3000         Single-point indication             CCLOVIC 61830 Clerkfib30000         Single-point indication             CCLOVIC 61830 Clerkfib3000000000000000000000000000000000000	CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Urverrigel         10000990         Single-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Urverrigel         10000990         Single-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Urverrigel         10000990         Single-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Selektert         10000990         Single-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Selektert         10000690         Single-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Selektert         10000601         Double-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Selektert         10000602         Single-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Urverrigel         10000602         Single-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Urverrigel         10000603         Single-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Urverrigel         10000604         Double-point indication           CCL2DUEC 61350 Clemt613500         Steurung/OQ_1-Position.Urverrigel         10000605         Single-point indication           CCL2DUEC 61350 Clemt613500	SCCCL20/JEC 61850 Client/61850	It Steuerung/Storung.Sammeimeidung	10000594	Single-point indication			
CLC2DEC 61350 Client/613500         Steurung/QD_1Position_Umerriegel         10000597         Single-point indication           CLC2DEC 61350 Client/613500         Steurung/QD_1Position_Umerriegel         10000597         Single-point indication           CLC2DEC 61350 Client/613500         Steurung/QD_1Position_Umerriegel         10000598         Double-point indication           CLC2DEC 61350 Client/613500         Steurung/QD_1Position_Umerriegel         10000598         Double-point indication           CLC2DEC 61350 Client/613500         Steurung/QD_1Position_Umerriegel         10000600         Single-point indication           CLC2DEC 61350 Client/613500         Steurung/QD_1Position_Umerriegel         10000600         Single-point indication           CLC2DEC 61350 Client/613500         Steurung/QD_1Position_Setektier         10000601         Double-point indication           CLC2DEC 61350 Client/613500         Steurung/QD_1Position_Setektier         10000603         Single-point indication           CL2DEC 61350 Client/613500         Steurung/QD_2.Position_Setektier         10000603         Single-point indication           CL2DEC 61350 Client/613500         Steurung/QD_2.Position_Setektier         10000605         Single-point indication           CL2DEC 61350 Client/613500         Steurung/QB_2.Position_Umerriegel         10000605         Single-point indication           CL2DEC 61350 Client/613500	CCL2DUEC 01300 Climit(31500)         Steurung/(O_LPosition/Inverriegel)         10000597         Single-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LPosition/Inverriegel)         10000598         Double-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LPosition/Inverriegel)         10000599         Single-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LPosition/Inverriegel)         10000600         Single-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LLPosition/Inverriegel)         10000600         Single-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LLPosition/Inverriegel)         10000601         Double-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LLPosition/Selectier)         10000601         Double-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LLPosition/Selectier)         10000603         Single-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LLPosition/Inverriegel)         10000604         Double-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LLPosition/Selectier)         10000665         Single-point indication           CCL2DUEC 01350 Climit(31500)         Steurung/(O_LLPosition-Selectier)         10000665         Single-point indication	SCCCL20/IEC 61850 Client/61850	Il Steuerung/Storung.warnsammeimeide	10000595	Single-point indication			
CLC2USE C6150 Clemth615501         Steurumg/Q0_1Position         1000059         Double-point indication           CLC2USE C6150 Clemth615501         Steurumg/Q0_1Position         1000059         Double-point indication           CLC2USE C6150 Clemth615501         Steurumg/Q0_1Position         1000059         Double-point indication           CLC2USE C6150 Clemth615501         Steurumg/Q1_1Position         1000059         Single-point indication           CLC2USE C6150 Clemth615501         Steurumg/Q1_1Position         10000600         Single-point indication           CLC2USE C6150 Clemth615501         Steurumg/Q1_1Position         10000601         Double-point indication           CLC2USE C6150 Clemth615501         Steurumg/Q1_1Position         10000603         Single-point indication           CL2USE C6150 Clemth615501         Steurumg/Q2_1Position         10000603         Single-point indication           CL2USE C6150 Clemth615501         Steurumg/Q2_1Position         10000604         Double-point indication           CL2USE C6150 Clemth615501         Steurumg/Q3_1Position         10000605         Single-point indication           CL2USE C6150 Clemth615501         Steurumg/Q3_1Position         10000605         Single-point indication           CL2USE C61500 Clemth615501         Steurumg/Q3_1Position         10000605         Single-point indication           CL2	CCL2DUEC 61805 Climent618500         Steurung/Q0_LPosition         10000598         Double-point indication           CCL2DUEC 61850 Climent618500         Steurung/Q0_LPosition.Werreiget         10000599         Single-point indication           CCL2DUEC 61850 Climent618500         Steurung/Q0_LPosition.Selektiert         10000599         Single-point indication           CCL2DUEC 61850 Climent618500         Steurung/Q1_LPosition.Unverrieget         10000600         Single-point indication           CCL2DUEC 61850 Climent618500         Steurung/Q1_LPosition.Unverrieget         10000600         Single-point indication           CCL2DUEC 61850 Climent618500         Steurung/Q1_LPosition.Unverrieget         10000601         Double-point indication           CCL2DUEC 61850 Climent618500         Steurung/Q2_LPosition.Unverrieget         10000604         Double-point indication           CCL2DUEC 61850 Climent618500         Steurung/Q2_LPosition.Selektiert         10000605         Single-point indication           CCL2DUEC 61850 Climent618500<	CCCL20/JEC 61850 Client/61850	Il Steverung/Aligemein.schhoneit	10000590	Single-point indication			
CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Stektier         100000599         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Winerriget         10000599         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Winerriget         10000600         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Winerriget         10000602         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Winerriget         10000602         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Winerriget         10000603         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Winerriget         10000603         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Stektier         10000603         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Stektier         10000605         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Stektier         10000605         Single-point indication           CCL2DUEC 61850 Client618500         Steureung/Q_1_Position_Winerriget         10000605         Single-point indication           CCL2DUEC 61850 Client618500<	CCCL20LEC 61850 Clent/618500         Steurung/Q0_1_Position.Stektier         10000599         Single-point indication           CCCL20LEC 61850 Clent/618500         Steurung/Q1_1_Position.Werrigget         10000590         Single-point indication           CCCL20LEC 61850 Clent/618500         Steurung/Q1_1_Position.Werrigget         10000602         Single-point indication           CCCL20LEC 61850 Clent/618500         Steurung/Q1_1_Position.Stektier         10000602         Single-point indication           CCCL20LEC 61850 Clent/618500         Steurung/Q1_1_Position.Werrigget         10000602         Single-point indication           CCCL20LEC 61850 Clent/618500         Steurung/Q2_1_Position.Merrigget         10000603         Single-point indication           CCCL20LEC 61850 Clent/618500         Steurung/Q2_1_Position.Merrigget         10000603         Single-point indication           CCCL20LEC 61850 Clent/618500         Steurung/Q2_1_Position.Merrigget         10000605         Single-point indication           CCL20LEC 61850 Clent/618500         Steurung/Q2_1_Position.Merrigget         10000605         Single-point indication           CCL20LEC 61850 Clent/618500         Steurung/Q2_1_Position.Merrigget         10000605         Single-point indication           CCL20LEC 61850 Clent/618500         Steurung/Q2_1.Position.Merrigget         10000605         Single-point indication           CCL20LEC 61850 Clent/61850	CCCL20/IEC 61850 Client/61850	Il Stevenung/Q0_1.Position.UnVerriegelt	10000597	Double-point indication			
CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000600         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000600         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000602         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000602         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000603         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000603         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000603         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000605         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000605         Single-point indication           CCL2DUEC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000605         Single-point indication           C/2.20EC 61850 Client618500         Steurung/(C)_1_Position.Umerrieget         10000607         Double-roint indication           C/2.20EC 6	CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.Unverrieget         10000600         Single-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.Unverrieget         10000600         Single-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.Unverrieget         10000603         Single-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.SetKeiter         10000603         Single-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.Unverrieget         10000603         Single-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.Unverrieget         10000604         Double-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.SetKeiter         10000606         Single-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.SetKeiter         10000606         Single-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.SetKeiter         10000606         Single-point indication           CCCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.Unverrieget         10000606         Single-point indication           CCL2DUEC 61850 Client/618500[         Steuerung/(2)_1Position.Unverrieget         100000605         Single-point indication	SCCCI 20/JEC 61850 Client/61850	Stevenung/Q0_1.Position	10000599	Single-point indication		<b>  </b>	
CCL2DUEC 61850 Client/61850()         Steuerung/Q1_Position         10000601         Double-point indication           CCL2DUEC 61850 Client/61850()         Steuerung/Q1_Position         10000601         Double-point indication           CCL2DUEC 61850 Client/61850()         Steuerung/Q1_Position         Single-point indication            CCL2DUEC 61850 Client/61850()         Steuerung/Q1_Position         Single-point indication            CCL2DUEC 61850 Client/61850()         Steuerung/Q1_Position         Double-point indication            CCL2DUEC 61850 Client/61850()         Steuerung/Q1_Position         Double-point indication            CCL2DUEC 61850 Client/61850()         Steuerung/Q1_Position         Single-point indication            CCL2DUEC 61850 Client/61850()         Steuerung/Q3_Position         Double-point indication            CL2DUEC 61850 Client/61850()         Steuerung/Q3_Position         Double-point indication	CCL2DUEC 61850 Client/618500         Steuerung/Q1_LPosition         10000601         Double-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q1_LPosition.Uverreigel         10000601         Double-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q1_LPosition.Uverreigel         10000601         Double-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q1_LPosition.Uverreigel         10000604         Double-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q1_LPosition.Uverreigel         10000604         Double-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q2_LPosition.Setkeiter         10000606         Single-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q2_LPosition.Uverreigel         10000606         Single-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q2_LPosition.Uverreigel         10000606         Single-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q2_LPosition.Uverreigel         10000606         Single-point indication           CCL2DUEC 61850 Client/618500         Steuerung/Q2_LPosition.Setkeiter         10000607         Double-point indication	SCCCI 20/JEC 61850 Client/61850	Stevening/Q0_1Position.Selectient	10000600	Single-point indication			
CCL2DUEC 61850 Client/61850II Steurung/Q1_1Position_Selektier         10000602         Single-point indication           CCL2DUEC 61850 Client/61850II Steurung/Q2_1Position_Unversiget         10000603         Single-point indication           CCL2DUEC 61850 Client/61850II Steurung/Q2_1Position_Selektier         10000603         Single-point indication           CCL2DUEC 61850 Client/61850II Steurung/Q2_1Position_Selektier         10000605         Single-point indication           CCL2DUEC 61850 Client/61850II Steurung/Q2_1Position_Selektier         10000605         Single-point indication           CCL2DUEC 61850 Client/61850II Steurung/Q2_1Position_Unversiget         10000605         Single-point indication           CCL2DUEC 61850 Client/61850II Steurung/Q2_1Position_Unversiget         10000605         Single-point indication           CCL2DUEC 61850 Client/61850II Steurung/Q3_1Position_Unversiget         10000605         Single-point indication           CCL2DUEC 61850 Client/61850II Steurung/Q3_1Position_Unversiget         10000607         Double-point indication	CCL2DUEC 61850 Client/618500]         Steureung/02_1_Position.Selektier         10000602         Single-point indication           CCL2DUEC 61850 Client/618500]         Steureung/02_1_Position.Selektier         10000602         Single-point indication           CCL2DUEC 61850 Client/618500]         Steureung/02_1_Position.Selektier         10000603         Single-point indication           CCL2DUEC 61850 Client/618500]         Steureung/02_1_Position.Selektier         10000605         Single-point indication           CCL2DUEC 61850 Client/618500]         Steureung/02_1_Position.Selektier         10000605         Single-point indication           CCL2DUEC 61850 Client/618500]         Steureung/02_1.Position.Selektier         10000605         Single-point indication	SCCCI 20\IEC 61850 Client\61850	Steverung/Q1_1Position	10000601	Double-point indication			
CCL2DUEC 61850 Client/61850II         Steuerung/Q2_1Position.Umverrieget         10000603         Single-point indication           CCL2DUEC 61850 Client/61850II         Steuerung/Q2_1Position         10000604         Double-point indication           CCL2DUEC 61850 Client/61850II         Steuerung/Q2_1Position.Umverrieget         10000605         Single-point indication           CCL2DUEC 61850 Client/61850II         Steuerung/Q3_1Position.Umverrieget         10000605         Single-point indication           CCL2DUEC 61850 Client/61850II         Steurung/Q3_1Position.Umverrieget         10000607         Single-point indication	CCL2DUEC 61850 Client/61850/l         Steuerung/Q2_1.Position.Unverrieget         10000603         Single-point indication           CCL2DUEC 61850 Client/61850/l         Steuerung/Q2_1.Position.Setketier         10000604         Double-point indication           CCL2DUEC 61850 Client/61850/l         Steuerung/Q2_1.Position.Setketier         10000606         Single-point indication	CCCL20\IEC 61850 Client\61850	I Steverung/O1 1.Position Selectient	10000602	Single-point indication			
CCL20UEC 61850 Client/618508         Steuerung/Q2_1Position         10000694         Double-point indication           CCL20UEC 61850 Client/618508         Steuerung/Q2_1Position_Stelektiet         10000605         Single-point indication           CCL20UEC 61850 Client/618508         Steuerung/Q2_1Position_Unversight         10000605         Single-point indication           CCL20UEC 61850 Client/618508         Steuerung/Q2_1Position_Unversight         10000607         Single-point indication           CCL20UEC 61850 Client/618508         Steuerung/Q2_1Position_Unversight         10000607         Double-point indication	CCCL20UEC 61850 Client/61850II         Steuerung/Q2_1Position         10000604         Double-point indication           CCCL20UEC 61850 Client/61850II         Steuerung/Q2_1Position_Slekkiert         10000605         Single-point indication           CCCL20UEC 61850 Client/61850II         Steuerung/Q3_1Position_Unversiget         10000605         Single-point indication           CCCL20UEC 61850 Client/61850II         Steuerung/Q3_1Position_Unversiget         10000607         Double-point indication           CCCL20UEC 61850 Client/61850II         Steuerung/Q3_1Position         Double-point indication         Double-point indication           CCCL20UEC 61850 Client/61850II         Steuerung/Q3_1Position_Slekkiert         10000607         Double-point indication         Double-point indication	SCCCI 20/JEC 61850 Client/61850	Steuerung/Q2 1 Position Unverriegelt	10000603	Single-point indication			
ICCL20UEC 61850 Client/618500         Steuerung/Q2_1Position_Stelektiert         10000605         Single-point indication           ICCL20UEC 61850 Client/618500         Steuerung/Q3_Position_Unversigned         10000605         Single-point indication           ICCL20UEC 61850 Client/618500         Steuerung/Q3_Position_Unversigned         10000605         Single-point indication           ICCL20UEC 61850 Client/618500         Steuerung/Q3_Position_Unversigned         10000607         Single-point indication	CCCL20UEC 61850 Client/618500         Steuerung/Q2_1.Position Selektiert         10000605         Single-point indication           CCCL20UEC 61850 Client/618500         Steuerung/Q3_1.Position_Vereningelt         10000606         Single-point indication           CCCL20UEC 61850 Client/6185001         Steuerung/Q3_1.Position         10000606         Single-point indication           CCCL20UEC 61850 Client/6185001         Steuerung/Q3_1.Position Selektiert         10000606         Single-point indication           CCCL20UEC 61850 Client/6185001         Steuerung/Q3_1.Position-Selektiert         10000606         Single-point indication	CCCL20\IEC 61850 Client\61850	I Steuerung/O2 1.Position	10000604	Double-point indication			
CCL20/EC 61850 Client/61850/ Steuerung/Q8_LPosition.Unverriegelt 10000606 Single-point indication CCL20/EC 61850 Client/61850/I Steuerung/Q8_LPosition 10000607 Double-point indication CCL20/EC 61850 Client/61850/II Steuerung/Q8_LPosition 10000607 Double-point indication CCL20/EC 61850 Client/61850/II Steuerung/Q8_LPosition 10000607	CCCL20UEC 61850 Client/61850/I Steuerung/Q8_1.Position.Unverriegelt         10000607         Single-point indication           CCCL20UEC 61850 Client/61850/I Steuerung/Q8_1.Position         10000607         Double-point indication           CCCL20UEC 61850 Client/61850/I Steuerung/Q8_1.Position.Selektiert         10000608         Single-point indication	CCCL20\JEC 61850 Client\61850	I Steverung/Q2 1.Position Selection	10000605	Single-point indication			
CCI20UEC 61850 Client/61850II Steuerung/C8.1 Position 10000607 Double-point indication	CCCL20UEC 61850 Client/618508         Steuerung/Q8_1.Position         10000607         Double-point indication           CCCL20UEC 61850 Client/618508         Steuerung/Q8_1.Position Selektiert         10000608         Single-point indication         P	CCCL20\IEC 61850 Client\61850	If Steuerung/O8 1.Position.Unverriegelt	10000606	Single-point indication			
	CCCL20UEC 61850 Client/618500 Steverung/Q8_1Position Selektiert 10000006 Single-point indication	SCCCL20/JEC 61850 Client/61850	Steuerung/O8 1.Position	10000607	Double-point indication			
CCL20/EC 61850 Client/61850I Steuerung/08 1.Position Selektiert 10000608 Single-point indication			Steuerung/O8 1.Position.Selektiert	10000608	Single-point indication			
	CCC20/LEC 61850 Client/b1850/ij Steuerung/Q8_1.Position.Selektiert 10000608 Single-point indication	\SCCCL20\JEC 61850 Client\61850 \SCCCL20\JEC 61850 Client\61850 \SCCCL20\JEC 61850 Client\61850 \SCCCL20\JEC 61850 Client\61850 \SCCCL20\JEC 61850 Client\61850 \SCCCL20\JEC 61850 Client\61850	I Steuerung/Q2_1.Position Unverriegelt Steuerung/Q2_1.Position I Steuerung/Q2_1.Position Selektiert I Steuerung/Q8_1.Position.Unverriegelt I Steuerung/Q8_1.Position	10000603 10000604 10000605 10000606 10000607	Single-point indication Double-point indication Single-point indication Single-point indication Double-point indication			
		SCCCL20\IEC 61850 Client\61850						

- (1) Messages, Page 304
- (2) Selection filter for messages, Page 304
- (3) Dynamic alarm filter, Page 305
- (4) Selection filters for DAFs, Page 305
- (5) Information bar

The information bar provides useful information, such as the number of binary and numerical filters or the total number of messages.

(6) Buttons

Click **Apply** to save all the settings performed; click **< Back** to return to the 7.5.3 *Configuration* of the filter criteria. Click **OK** to apply all settings and close the window.

#### Messages

This list shows all the messages imported into your SICAM SCC project.

#### Selection filter for messages

You can filter the list in order to reduce its size and browse for specific messages. All columns are available as filter criteria.

- Message Group (free text)
- Message (free text)
- Message Number (free text)

- Data Type (list box which automatically shows all available data types)
- Assigned DAF (list box which automatically shows all configured DAFs)

You can, for example, only show double-point indications with "einaus" in the Message Name:

Messages				
Message Group	Message Name	Message Number	Data Type	Assigned DAF
	einaus		Double-point indication 🔹	•
FS1\SCCCL20\IEC 60870-5-103 Master	q0_einaus	10002506	Double-point indication	BinaryDAF_Default
FS1\SCCCL20\IEC 60870-5-103 Master	q1_einaus	10002507	Double-point indication	myNumDAF_01
FS1\SCCCL20\IEC 60870-5-103 Master	q2_einaus	10002508	Double-point indication	myBinDAF_02
FS1\SCCCL20\IEC 60870-5-103 Master	q9_einaus	10002509	Double-point indication	
FS1\SCCCL20\IEC 60870-5-103 Master	q8_einaus	10002510	Double-point indication	myBinDAF_02

[sc_daf map filter, 1, en_US]



#### NOTE

For the free texts for Message Group and Message you can use ".", "?" and "*" as wildcards.

#### Dynamic alarm filter

This list shows all configured DAFs.

In order to assign a DAF to a message, drag and drop the DAF from the list to the message selected. To perform multiple assignments (i.e. assign a DAF to several messages), press the Shift or Alt key in order to select several messages and then drag the corresponding DAF to these messages.

In just one step, you can e.g. assign the DAF **myBinDAF_01** to the messages **q1_einaus**, **q2_einaus** and **q8_einaus** from the example above (see *Selection filter for messages*, *Page 304*):

Messages					Dynamic Alarmfilter	
Message Group	Message Name	Message Number	Data Type	Assigned DAF	DAF	Туре
	einaus		Double-point indication 🔹	•		•
FS1\SCCCL20\IEC 60870-5-103 Master	q0_einaus	10002506	Double-point indication	BinaryDAF_Default	BinaryDAF_Default	Binary
FS1\SCCCL20\IEC 60870-5-103 Master	q1_einaus	10002507	Double-point indication	myBinDAF_02	myBioDAF_01	Binary
FS1\SCCCL20\JEC 60870-5-103 Master	q2_einaus	10002508	Double-point indication	myBinDAF_02	myBinDAF_02	Binary
FS1\SCCCL20\IEC 60870-5-103 Master	q9_einaus	10002509	Double-point indication		myNumDAF_01	Numeric
FS1\SCCCL20\JEC 60870-5-103 Master	q8_einaus	10002510	Double-point indication	myBinDAF_02	myNumDAF_02	Numeric
					Numerischer Filter 1	Numeric

[sc_daf map dnd, 1, en_US]

To assign a DAF to several messages, you can double-click the messages in the **Dynamic alarm filter** column and then select the corresponding DAF from the selection list:

Message Group	Message Name	Message Number	Data Type	Assigned DAF	
	einaus		Double-point indication 🔹		•]
FS1\SCCCL20\IEC 60870-5-103 Master	q0_einaus	10002506	Double-point indication	BinaryDAF_Default	
FS1\SCCCL20\IEC 60870-5-103 Master	q1_einaus	10002507	Double-point indication	myNumDAF_01	
FS1\SCCCL20\IEC 60870-5-103 Master	q2_einaus	10002508	Double-point indication	myBinDAF_02	-
FS1\SCCCL20\IEC 60870-5-103 Master	q9_einaus	10002509	Double-point indication	(none)	
FS1\SCCCL20\IEC 60870-5-103 Master	q8_einaus	10002510	Double-point indication	BinaryDAF_Default	
				myBinDAF_01 myBinDAF 02	
				Numerischer Filter 1	
				myNumDAF_01	
				myNumDAF_02	

[sc_daf map listbox, 1, en_US]

To delete DAF assignments, either select them individually (from the **(none)** list or press **<Del>** in the selected line) or perform a multiple selection (select several lines and then press **<Del>**). To undo a multiple selection, press **<Esc>**.

#### Selection filters for DAFs

You can filter the list in order to reduce its size and browse for specific DAFs. All columns are available as filter criteria.

- Name (free text)
- Type (list box: none, binary, numerical, SI with alarm when ON, SI with alarm when OFF)

- SI with alarm when ON
- SI with alarm when OFF

# 7.5.5 Assignment Tables

#### PAS causes of transmission

The following table serves for the assignment of IEC values to SICAM PAS values. SICAM PAS also uses additional values.

	-	_		
IEC-COT	PN Bit ⁴	SE Bit ⁵	PAS-COT	InitiatorCategory
				empty=elrrelevant (0)
COT_GA (2)	-	-	eGeneralInterrogation (8)	
COT_SPONTAN (3)	-	-	eSpontaneous (1)	
COT_ACTIVATION (6)	-	1	eSelect (16)	
	-	0	eCommand (19)	
COT_CONFIRMATION (7)	0	1	eSelectConfPos (17)	
	1	1	eSelectConfNeg (18)	
	0	0	eCommandConfPos (20)	
	1	0	eCommandConfNeg (21)	
COT_DEACTIVATE (8)	-	-	eAbort (25)	
COT_CONFDEACTIVATE (9)	0	-	eAbortConfPos (26)	
	1	-	eAbortConfNeg (27)	
COT_TERMINATION (10)	0	1	eSelectTermPos (39)	
	1	1	eSelectTermNeg (40)	
	0	0	eCommandTermPos (35)	
	1	0	eCommandTermNeg (36)	
COT_RUECKMFERNBEF (11)	-	-	eReturnInformation (34)	eNearControl (2)
COT_RUECKMNAHBEF (12)	-	-	eReturnInformation (34)	eLocalControl (1)
COT_BACKGROUNDSCAN (20)	-	-	eGeneralInterrogation (8)	

Table 7-8 IEC-COT ⇔ PAS-COT Assignment Table

#### PAS additional causes

The following table serves for the assignment of IEC values to SICAM PAS values. SICAM PAS also uses additional values.

Table 7-9	IEC-AddCause ⇔ PAS-AddCause Assignment Table
-----------	----------------------------------------------

IEC-AddCause	PAS-AddCause
unknown (0)	eAddCPositive (0)
not_supported (1)	eAddCCommandNotAccepted (41)
Blocked_by_switching_hierachy (2)	eAddCAuthorityViolation (99)
Select_failed (3)	eAddCCommandNotAccepted (41)
Invalid_position (4)	eAddCPlausibilityError (114)
Position_reached (5)	eAddCStateAlreadyReached (117)
Parameter_change_in_execution (6)	eAddCParameterError (98)

⁴ PN Bit: 1 = negative confirmation, 0 = positive confirmation

⁵ SE Bit: 1 = select, 0 = execute

IEC-AddCause	PAS-AddCause
Step_limit (7)	CDC=BSC:
	Value=2 (closed)
	eAddCUpperBoundReached (112)
	Otherwise: eAddCLowerBoundReached (113)
	Otherwise: eAddCPositive (0)
Blocked_by_mode (8)	eAddCOutputBlockageSet (102)
Blocked_by_process (9)	eAddCOutputBlockageSet (102)
Blocked_by_interlocking (10)	eAddCSwitchingErrorProtectionInterlock (97)
Blocked_by_synchrocheck (11)	eAddCSychronizationPreconditionFailure (115)
Command_already_in_execution (12)	eAddCTooManyActiveCommands 38()
Blocked_by_health (13)	eAddCDeviceStatus (116)
One_of_n_control (14)	eAddCOneOutOfNErrorSoftware (121)
Abortion_by_cancel (15)	eAddCCommandNotAccepted (41)
Time_limit_over (16)	eAddCMonitoringTimeExpired (118)
Abortion_by_trip (17)	eAddCCommandNotAccepted (41)
Object_not_selected (18)	eAddCCommandNotAccepted (41)
Object_already_selected (19)	eAddCCommandNotAccepted (41)
No_access_authority (20)	eAddCAuthorityViolation (99)
Ended_with_overshoot (21	eAddCOverload (105)
Abortion_due_to_deviation (22)	eAddCCommandNotAccepted (41)
Abortion_by_communication_loss (23)	eAddCCommandNotAccepted (41)
Blocked_by_command (24)	eAddCOutputBlockageSet (102)
None (25)	eAddCCommandNotAccepted (41)
Inconsistent_parameters (26)	eAddCParameterError (98)
Locked_by_other_client (27)	eAddCOneOutOfNErrorSoftware (121)

# 7.6 SICAM Functions

#### Overview

The SICAM functions complement the default functions of SIMATIC WinCC. The SICAM functions are C scripts. When a project is created, they are copied as project functions and made available by a SICAM Wizard. SICAM functions can be used for the processing of commands, alarms and measured values.

C scripts can be opened and edited using the C Editor. For more detailed information, refer to the documentation of SIMATIC WinCC.

# 7.6.1 Commands

Use the SICAM functions described in this paragraph for issuing commands. The following functions are available:

Table 7-10	SICAM	functions	for	command	execution
	510/ 11/1	ranceions		communa	checation

Name	Meaning
SCC_Command_Analog	Issuing of commands for analog values
SCC_Command	Issuing of commands for digital values
SCC_CommandExecute	Command execution, for two-step command output

The SICAM command output functions are available in the WinCC Explorer under **Global Script/C Editor/ Project Functions/SICAMSCC/Command**.

The SICAM command output functions can be used depending on the individual tag type.

By default, the **SCC_Command_Analog** and **SCC_Command** functions perform the complete command output. In order to transmit the command in 2 steps, customize the scripts and additionally call up the **SCC_CommandExecute** function. The related description is available in the corresponding scripts.



[pascc701, 1, en_US]

Figure 7-23 SICAM command output functions

## 7.6.1.1 Command for Floating Point Values

#### Format

The SICAM command output function in Float number format has the following structure:

void SCC_CommandAnalog ( char* p_cTagName, float p_fValue, DWORD p_dwValueType, DWORD p_dwDuration, DWORD p_dwCOT )

#### Description

Use this function to issue a command in **Float** format. The name of the command tag is used as transfer parameter (e.g. **Bay01_device02** or **Bay01_device02.value**).

The tag can be any structure element (Value, Cause, Valuetype, CmdCounter).

Additionally, you transfer a value of the Float type (e.g. in order to output an analog setpoint), the number format (e. g. **22** for an analog setpoint), the command duration in milliseconds (ms), and the cause identifier. For more detailed information on number formats, refer to appendix A.1.3.

#### Suggested trigger

Suggested trigger for the PAS_Command_Float function:

As trigger for this function, you can use any action of an object, e. g. a click a button.



# NOTE

Use a Windows object of the **Slider Object** type (in the Graphics Designer of SIMATIC WinCC) in order to create a variable definition of an analog setpoint in floating point format via the **value** structure element.

#### 7.6.1.2 Command for Digital Values

#### Format

The SICAM command output function based on the **Signed integer** number format has the following structure:

void SCC_Command ( char* p_cTagName, int p_iValue, DWORD p_dwValueType, DWORD p dwDuration, DWORD p dwCOT, BOOL p bNoSynch, BOOL p bNoLock )

#### Description

Use this function to issue a command in **PAS_Command_Integer** format. The name of the command tag is used as transfer parameter (e. g. **Bay01_device03** or **Bay01_device03.value**).

The tag can be any structure element (Value, Cause, Valuetype, CmdCounter).

Additionally, you transfer the switching direction (1=OFF, 2=ON for a pulse command), the number format (e. g. **14** for a pulse command), the command duration in milliseconds (ms), the cause identifier, and the bits for the Qualifier of Command (QoC, for the IEC Communication Suite). For more detailed information on number formats, refer to appendix A.1.3.

#### Suggested trigger

Suggested trigger for the **Command output with the Integer number format** function: As trigger for this function, you can use any action of an object, e.g. a click a button.

#### 7.6.1.3 Command Execute

#### Format

The Command Execute function has the following format: void SCC_CommandExecute(char* p_cTagName)

#### Description

This function executes a command. To do this, the value of the **CmdCounter** structure element of the command tag is increased. The name of the command tag is used as transfer parameter.

The tag can be any structure element (Value, Cause, Valuetype, CmdCounter).

The Command Execute function is used as second step of a command execution.

As the first step, you can e.g. use the SICAM command output function. In this case, however, the rows for the command execution must be commented in the C script! (See comments in the SCC_Command and SCC_Command_analog script)

To comment the script lines:

♦ Open the C script using the C editor.



[pascc702, 1, en_US]

Figure 7-24 Commenting command lines

- To comment the command execution lines (selected lines), add two slashes at the beginning of each line.
- ♦ Save the modified script.

#### Suggested trigger

Suggested trigger for the **Command Execute** function: As trigger for this function, you can use any action of an object, e.g. a click a button.

# 7.6.2 Substituting Values

#### 7.6.2.1 Overview

Via SICAM SCC, values in SICAM PAS/PQS and in IEC 61850 devices that support substitution (z.B. SIPROTEC 5), can be manually updated/substituted. For example, a substitution is required if there is no connection to the device/primary technology level although values are required in SICAM PAS/PQS or SICAM SCC. SICAM functions are available for the substitution of values.

The following values can be substituted:

- Bit pattern values
- Measured values (floating point values), metered values (integer values)
- Switch positions (signed integer values) For more detailed information, refer to chapter 4.4.6 *Runtime Dialogs of SICAM Switch Controls*.

Values are substituted by means of the following 2 subfunctions:

- Setting the value of the message to the substituted value and setting the status (validity) of the message to substituted.
- Incrementing the value of the WBCounter (Write-Back-Counter) structure element in order to ensure that the value is substituted in SICAM PAS/PQS.

For more detailed information on the structure of the indication tags, refer to appendix A.

A substitution can be performed if the message fulfils one or two of the following status criteria:

- Invalid
- Not topical
- Bay blocking set
- Substituted

The following functions are available:

Table 7-11	SICAM value s	substitution	functions
------------	---------------	--------------	-----------

Name	Meaning
SCC_PAS_SubstituteAnalog	Substitution of values in Float format
SCC_PAS_Substitute	Substitution of values in Integer format

Table 7-12 Additional functions for IEC Communication Suite (at present only for IEC 61850)

Name	Bedeutung
SCC_IEC_SubstituteAnalog	Nachführen mit dem Zahlenformat Float
SCC_IEC_Substitute	Nachführen mit dem Zahlenformat Integer
SCC_IEC_SubstituteReset	Rücksetzen des nachgeführten Wertes

The SICAM substitution functions are available in the WinCC Explorer under **Global Script/C Editor/Project Functions/SICAMSCC/misc**.

Various SICAM substitution functions can be used depending on the individual number format.

#### 7.6.2.2 Substituting Floating Point Values

#### Format

The SICAM substitution function for values in Float number format has the following structure: void SCC_PAS_SubstituteAnalog(char* p_cTagName, float p_fValue)

#### Description

Use this function to substitute a value in **Float** format. Therfor the tag name and the substitute value must be transferred to the function.

The tag can be any structure element of a SICAM structure tag (Value, Cause, Valuetype, CmdCounter). For more detailed information on number formats, refer to appendix A.1.3.

#### Suggested trigger

Suggested trigger for the **PAS_Substitute_Float** function: As trigger for this function you can use any action of an object, e.g. a click on a button.

#### 7.6.2.3 Substituting Digital Values

#### Format

The SICAM substitution function for values in the **Signed Integer** number format has the following structure: void SCC_PAS_Substitute(char* p_cTagName, int p_iValue)

#### Description

Use this function to substitute a value in the **Signed Integer** format. Therefor the tag name and the substitute value must be transferred to the function.

The tag can be any structure element (Value, Cause, Valuetype, CmdCounter).

For more detailed information on number formats, refer to appendix A.1.3.

#### Suggested trigger

Suggested trigger for the **Substitution with Integer number format** function: As trigger for this function, you can use any action of an object, e. g. a click a button. For more detailed information on the substitution of switch positions, refer to chapter *4.4.6 Runtime Dialogs* of *SICAM Switch Controls*.

The Switch position substitution function is also integrated in the ActiveX Controls.

# 7.6.3 Object-Specific Blocking

When using SICAM PAS/PQS, V8.01 or later, an information-specific blocking can be defined for information from the SICAM PAS target system. A C script is available for this function.

#### Format

The **object-specific blocking** has the following format:

```
void SCC_PAS_SetBlockState(char* p_cTagName, int p_iBayBlocked,
int p_iTelecontrolBlocked)
```

#### Description

You can use this function in order to set or undo blocking for an individual item of process information. When using SICAM SCC switching device objects this function is integrated in the status dialog, see chapter 4.4.6 Runtime Dialogs of SICAM Switch Controls.

The parameters for the function are as follows:

- Tag name (p_cTagName)
- Bay blocking value (p_iBayBlock)
- Telecontrol blocking value (p_iTelecontrolBlock).

The following values are possible:

- 0 No change
- 1 Undo blocking
- 2 Set blocking

After activating bay blocking the value of the object can be substituted using the functions described in chapter 7.6.2 Substituting Values.

# 7.6.4 Functions for Processing of Messages

#### 7.6.4.1 Overview

Use the SICAM functions described in this paragraph for the processing of alarm messages. The following functions are available:

Table 7-13 General SICAM function
-----------------------------------

Name	Meaning
PAS_CreateMessage_V500	Create a message with text from the text library
PAS_CreateMessageStr_V500	Create a message with text transfer
PAS_CreateMessageStr2_V500	Create a message with transfer to 2 texts
SCC_AcknowledgeAlarm	Acknowledge message in warning message list

The SICAM functions for the processing of messages and measured values are available in the WinCC Explorer under Global Script/C Editor/Project Functions/SICAMSCC/misc.

#### 7.6.4.2 Creating a Message - Text from the Text Library

#### Format

The Create message function has the following structure:

void PAS_CreateMessage_V500(DWORD dwMsgNr, DWORD dwState, DWORD dwTextID)

#### Description

This function creates a message in the SIMATIC WinCC Alarm Logging system.

It requires the message number, the SIMATIC WinCC message status (1 = Raised, 2 = Cleared) and the ID of the text to be shown in the **Value** column.

# NOTE

The new message must be created with this ID in the Alarm Logging system first.

## 7.6.4.3 Creating a Message - with Text Transfer

#### Format

The **Create message** function has the following structure: void PAS CreateMessageStr V500 (DWORD dwMsgNr, DWORD dwState, char* lpszMsgText)

#### Description

This function creates a message in the SIMATIC WinCC Alarm Logging system.

It requires the message number, the SIMATIC WinCC message status (1 = Raised, 2 = Cleared) and the text to be shown in the **Value** column.



#### NOTE

The new message must be created in the Alarm Logging system first.

#### 7.6.4.4 Acknowledging A Message in the Warning Message List

#### Format

The Acknowledge message in warning message list function has the following format:

void SCC_AcknowledgeAlarm(char* p_cMsgAckTagName, DWORD MsgNumber)

#### Description

This function creates Acknowledged messages in the warning message list via the message number. For this function you transfer the name of the raw data tag (MSG_Ack_... for acknowledgment) of the communication channel via which the message is received, as well as the message number.

# 7.6.5 Function for Copying Tag Values

#### Format

The Copy tag values function has the following format:

```
SCC_CopyTagValueRT(char* p_cSourceTagName, char* p_cDestinationIntTagName,
BOOL p bDigitalValue)
```

#### Description

This function copies the current runtime data of a tag of the **PAS Information** type into an internal tag structure of the same type. This is mainly required in order to use a switch several times for topological coloring, which the topological coloring plausibility check would not allow (e.g. use of switchgear trucks: the disconnector is drawn twice).

The transfer parameters are the structure tags of the source and target tags as well as the information whether it is a digital or analog value.

The names can be transferred with an extension (e.g. .RTInfo) or without an extension.

p bDigitalValue is transferred with **0** for analog and **1** for digital values.

# 7.6.6 Using SICAM Functions

The SICAM functions can be used to assign dynamic display properties to graphic objects in SIMATIC WinCC station diagrams.

#### Dynamic display properties

With the dynamic display properties, you can visualize a station's status in the control and monitoring direction.

#### C action

Via the C action, you can use all functions provided by SIMATIC WinCC. These also include the SICAM functions.

#### Commands

Use the **Commands** SICAM functions for the assignment of dynamic display properties in the command direction.

#### **General SICAM functions**

The general SICAM functions allow you to visualize the different states of a station in the monitoring direction.

# 7.6.7 Global Actions

The currently necessary global actions are copied into the project when importing the SICAM graphic object library.

They are available in the WinCC Explorer under Global Script/C Editor/Actions/Global Actions.

For optional global actions and global actions originating from previous versions refer to the installation directory in the **PAS** subfolder. You can copy them into your project if required.

#### SicamPAS_Compkey

This global action is created dynamically during the import process. During runtime, it checks whether the **compatibility keys** of the SICAM SCC project and the SICAM PAS project are identical. If this is not the case, a message is shown when the runtime is terminated.

No compatibility check is performed for SICAM RTUs, IEC 61850 and IEC 60870-5-104 devices.

#### Sicam_AsyncTicks

The **Sicam_AsyncTicks** global action writes into the **@AsyncTick** internal administrative tags (see 7.7.1 Administrative Tags). These tags are used to initiate topological coloring or a change in colors.

#### SicamPas_AlarmListFilter

The SicamPas_AlarmListFilter.pas C script distributes the settings performed via the Message List Filter checkbox to the external administrative tags of the connected communication channels. When the runtime is terminated, the filter setting can be saved for the next start:

- From SIMATIC WinCC V7.0 SP1, the **Runtime Persistence** option of the internal **@AlarmList-Filter_ValueInt** tag can be set.
- With older versions of SIMATIC WinCC (earlier than V7.0 SP1), the AlarmListFilter_WriteExt tag must be set to 1. This functionality is integrated in the Button End graphic object.

# i

NOTE

The **AlarmListFilter_WriteExt** tag can only be used when terminating the runtime (consistency of the tag management).

#### SICAM_FlashSyn

The **SICAM_FlashSyn** global action writes into the **@Flashxxx** internal administrative tags (see chapter 7.7.1 Administrative Tags).

This synchronizes the blinking of the IndustrialX Controls (SICAM PAS CC Version 5.10 or earlier).

#### Sicam1703_RedundancyMaster

The **Sicam1703_RedundancyMaster.pas** C script is created dynamically during the import process. It mirrors the **@RM_Master** administrative tag to the **RedundancyMaster_xx** external tag.

# 7.6.8 Testing SICAM Functions

The progress of the SICAM functions can be viewed during the runtime. To do this, add an application window and a checkbox from the project library to your diagram.

#### Inserting an application window

- ♦ Select the Application window object under Smart Objects in the Graphics Designer.
- Arrange the object in your diagram. The **Window Contents** dialog opens.



[pascc704, 1, en_US]

Figure 7-25 Inserting an Application Window

♦ Select **Global Script** and click **OK** to confirm. The **Template** window opens.

Template		×
GSC - Diagnose GSC - Runtime		
	ОК	Cancel



Figure 7-26 Selecting a Template

♦ Select **GSC Diagnostics** and click OK to confirm.

#### Inserting a checkbox

Insert the graphic object to be used for enabling/disabling the output of debug information.

♦ Insert the

CheckBox enable script output graphic object from the library into your diagram.

Library					<b>▼</b> ₽ ×
📸   🐰 🗈 🛍 🗙   🖭 🔚 🏥 🗰   6	6				
Graphic objects for SICAM SAS>	^	Name	Size 3505	Last Change 30.11.16 15:44	^
Control elements	l	Button quit RT	2550	30.11.16 15:42	
Switching device objects     Graphic objects of previous versions	;	Button switching authority (simple)	21285	30.11.16 15:45	- 1
Alarm Logging templates		Checkbox bay/telecontrol blocking	29628	30.11.16 15:46	
		CheckBox enable script debug outp	3219 8074	30.11.16 15:49 30.11.16 15:47	
		CheckBox switching authority	26765 10979	30.11.16 15:48 30.11.16 15:39	
< >	~	HelperObject WebNavCompKeyPic	3421	30.11.16 15:49	*
📳 Object Properties 🕒 Library 🤻 Dynam	nic V	Vizard			

[pascc706, 1, en_US]

Figure 7-27 Inserting the CheckBox enable script output graphic object



[pascc707, 1, en_US]

This checkbox allows you to enable/disable the output of debug information during runtime.

# 7.6.9 Calling the SICAM PQ Analyzer

#### Overview

You can call up the **SICAM PQ Analyzer** (Incident Explorer) from within SICAM SCC. This is possible from:

- A diagram
- The event list

In SICAM SCC you create a parameter file for the SICAM PQ Analyzer. In the opened Incident Explorer, the fault records are displayed according to the parameters for topology and time period, as defined in SICAM SCC.

#### Prerequisites

To be able to call up the SICAM PQ Analyzer from within SICAM SCC, the following prerequisites have to be fulfilled:

- The SICAM PQ Analyzer V3.03 or higher is installed on the SICAM SCC computer with the required licenses.
- A SICAM PQ Analyzer archive is configured according to the specifications, see Manual /11/ SICAM PQ Analyzer, Incident Explorer.
- Fault records are available in the SICAM PQ Analyzer archive.

#### 7.6.9.1 Call from a Diagram

#### Configuration in SICAM SCC

To configure the call in SICAM SCC:

- ♦ Create a new diagram in the Graphics Designer.
- ♦ To open the Library, click View > Library.
- ♦ Under Controls, select the Button PQA current time object.
- $\diamond$  Draw the graphics object to the desired position within the diagram.
- Right-click the button and select **Properties** from the context menu.
   The **Object properties** dialog opens.
- ♦ Open the Event tab.
- Under Button > Mouse, double-click Mouse Action.
   The Action Editor opens and the C script is displayed.





Figure 7-28 Editing the C Script

Adjust the following parameters for the display of your SICAM PQ Analyzer archive:

#### • char *cIPAddress

The IP address of the computer where the archive is located. The IP address of the local computer is the default address.

#### • char *cTopology

The topology to be displayed in the SICAM PQ Analyzer. Be aware of the double notation of the backslash.



# NOTE

Consider the correct upper and lower case. Otherwise the SICAM PQ Analyzer cannot display the topology properly.

#### • DWORD dwMinutes, DWORD dwHours, DWORD dwDays

The period when the fault records are to be displayed in the SICAM PQ Analyzer. You can set the period in minutes, hours, and/or days, see example below.

In the following example the **Incident Explorer** of the SICAM PQ Analyzer shows all fault records of the past 30 minutes up to now.

Example:

DWORD dwMinutes	= 30;
DWORD dwHours	= 0;
DWORD dwDays	= 0;

♦ Compile the adjusted script.



## NOTE

To get hints on configuration you can insert a **GSC Diagnostics** window. Therefor proceed as described in chapter 7.6.8 Testing SICAM Functions.

♦ Save the diagram and start SIMATIC WinCC Runtime.



[pq_analyzer_aufrufen_01, 1, en_US]

Figure 7-29 WinCC Runtime with Button for Calling the SICAM PQ Analyzer

To generate the parameter file for the SICAM PQ Analyzer, click PQA call current time. In the GSC Diagnostics window, the storage location of the generated parameter file is displayed.
 The Incident Explorer opens. The fault records are displayed within the configured time period and with the correct topology.

	SICAM PQ Analyz	er - nbesxcl8	0											siemei S	NS ICAM PQ	_ I Analyz	∃× zer
1	ncident Explorer	PQ Inspec	tor	Р	Q Ex	plorer		Report Browser	Gr	id Code '	Viewer						
•			Tim	e range	3		_										
ew	▼ Segion ▼ Region ▼ RACK_W_IECE	1850_station	Select tin	ne segmer	nt					From: 0	7/14/2014	÷ 11	:37:05 🛨	31 To: 03/17	/2015 🕂 12:0	7:05 🕂 31	
n vi	Voltage leve	1	Undefin	ed	•	•			20	D14			-		2015		
atio	PQ Dev	ice				Inf In	Aug	Sep	Od	t	Nov		Dec	Jan	Feb	Mar	
dur	,		Inc	idonte													
onfi			Chou	All		-											
0			SHUW	Colort		Tuna		Data/Tima		Enultin	Triagar	Causa		1.1	ararchu nath		
×	1		-	Derect		type	-	Dater mile		i duit ii	- mgger	Couse			erarchy pach		
vie			3		Fau	It record	-	09/10/2014 16:27:40	369	201	_	_	Region\RA	CK_W_IEC61	1850_station\V	oltage level	\753
NB O	3		2		Fau	lt record		08/28/2014 10:21:02	382	200			Region\RA	CK_W_IEC61	1850_station\V	oltage level	\ <b>7</b> 5J
100			1		Fau	ilt record		08/28/2014 10:20:57	856	199			Region\RA	CK_W_IEC61	1850_station\V	oltage level	\ <b>75</b> J
To																	
														Ope <u>n</u>	Ac <u>k</u> nowledge	<u>D</u> elet	te
															0 📃	% 著 nbesxo	:180

[pq_analyzer_aufrufen_02, 1, en_US]

Figure 7-30 Incident Explorer with Displayed Fault Records

♦ Click PQA call current time to open the Incident Explorer in the foreground. The display of the Incident Explorer is updated with the content of the SICAM PQ Analyzer fault record archive.

You can place and configure several buttons with different time parameters in the same diagram.



## NOTE

An incorrect configuration results in a corresponding message within SICAM PQ Analyzer or in the SICAM SCC GSC Diagnostics window.

If the Incident Explorer cannot be opened:

• Check the installation path of your SICAM PQ Analyzer as well as the path name in the C script **SCC_PQA_CreateParFile.fct**.

You can open, change, re-compile, and save the C script in the WinCC Explorer under Global Script > C-Editor > Project functions > SicamPAS > misc.

The following figure shows the meaning of the parameters of the C script for the **PQA call current time** button in conjunction with the display in the **Incident Explorer**.

c B	SICAM PQ Analyzer Options View Help	- nbesxcl8(	D											siemens SICAM	PQ Analy	_ ⊟ × yzer
h	ncident Explorer	PQ Inspect	tor	PC	) Explorer	Repor	t Browser	Grid Code	Viewer							
•			Tim	e range												_
X	Region	0 station	Select tim	e segment							From: 07	/14/2014 ÷	11:37:05 🛨	11 Td: 03/17/2015 🕂	12:07:05 ÷	31
i,	Voltage level		Undefine	d					2014					2015		Þ
tion					Line 🕨	Aug	S	ер	Oct	Nov	Dec		Jan	Feb	Mar	
igura	, d halpevice		Inci	dents						/						
Cont			Show	All	-											
	-		-	Select	Туре		Date	/Time	Fault number	Trigger	Caus	e		Hierarchy path		
/iew					5 . H	-		27.40.200	20		-	-		rectore to the bulk	1 0.767	
1 S	3		3		Fault record		09/10/2014 16	-21-02 392	20.	/		Reg	ion\RACK_W_I	EC61850_station\Volta	ge level\75J	
8			1		Fault record		08/28/2014 10	:20:57.856	19	,		Reg	ion\RACK_W_I	EC61850_station\Volta	ge level\751	_
Tol					DWO DWO	RD dwMin RD dwHou RD dwDay	utes = 30; rs = 0; rs = 100;									
			<						strncpy (	cTopology, "Reg	ion\\RACK_W_IE	C61850_sta	tion\\Voltag	e level\\75J*, STRI	NG_LENGTH )	;
														Ope <u>n</u> Ac <u>k</u> now	edge De	elete esxel80

[pq_analyzer_aufrufen_03, 1, en_US]

Figure 7-31 Incident Explorer and Parameters in the C Script

#### 7.6.9.2 Call from the Event List

#### **Configuration in SICAM SCC**

To configure the call in SICAM SCC:

- ♦ Create a new diagram in the Graphics Designer.
- ♦ To open the Library, click View > Library.
- Under Alarm Logging templates > WinCC V7.x, select the SICAM SCC Event list for PQ Analyzer object.
- $\diamond$  Draw the graphics object to the desired position within the diagram.
- ♦ Under Control elements, select the Button PQA message time object.
- $\diamond$  Draw the graphics object to the desired position within the diagram.



#### NOTE

To get hints on configuration you can insert a **GSC Diagnostics** window. Therefor proceed as described in chapter 7.6.8 Testing SICAM Functions.

♦ Save the diagram and start SIMATIC WinCC Runtime.

(							
III SICAM SCC Event list for PQ Analyzer							23
0 🗟 🎦 🔓 🕰 🖬 🚰 😫 🙆 🍃 🦆	) 🔁 🚺 🏹 🚺	🛎 🛃 🛐 🙇					
T.st. Date Time Message Group Message	fext Value	Unit Cause	Status (Validity)	Additional cause	ID number	Suplementary Infor	
977 S   VS 17/04/2015 10.36.38,069 HeidelbergNord\12V\University_103_1 sw-auth	OFF	spontaneous	valid	no error	identification number	irrelevant	
978 S   VS 17/04/2015 10.36.38,069 HeidelbergNord\12V\University_103_1 I_gt_bloc	OFF	spontaneous	valid	no error	identification number	irrelevant	
979 S VS 17/04/2015 10.36.38,069 HeidelbergNord\12V\University_103_1 q0_OnOf	OFF	spontaneous	valid	no error	identification number	irrelevant	
980 S VS 17/04/2015 10.36.38,069 HeidelbergNord\12V\University_103_1 g1_OnOf	OFF	spontaneous	valid	no error	identification number	irrelevant	
981 S VS 17/04/2015 10.36.38,009 HeidelbergNord/12/Voniversity_103_1 d2_OnOF	OFF double I	spontaneous	valid	no error	Identification number	irrelevant	
983 STVS 17/04/2015 10.36.38.069 HeidelberoNord/12//University_103_1_08_Op0f	OFF double i	i spontaneous	valid	no error	identification number	irrelevant	
984 STVS 17/04/2015 10.36.38.069 HeidelbergNord\12VUniversity 103_1 ventilator	OFF double i	i spontaneous	valid	no error	identification number	irrelevant	
985 SIVS 17/04/2015 10.36.56.400 HeidelbergNord\12V\University 103 1 sw-auth	ON	spontaneous	valid	no error	identification number	irrelevant	
986 S VS 17/04/2015 10.36.56,400 HeidelbergNord\12V\University_103_1 Lgt_bloc	ON	spontaneous	valid	no error	identification number	irrelevant	
987 S VS 17/04/2015 10.36.56,400 HeidelbergNord\12V\University_103_1 q0_OnOf	ON	spontaneous	valid	no error	identification number	irrelevant	
988 S   VS 17/04/2015 10.36.56,400 HeidelbergNord\12V\University_103_1 q1_OnOf	ON	spontaneous	valid	no error	identification number	irrelevant	
989 S   VS 17/04/2015 10.36.56,400 HeidelbergNord\12V\University_103_1 q2_OnOf	ON double in	n spontaneous	valid	no error	identification number	irrelevant	
990 S VS 17/04/2015 10.36.56.400 HerdelbergNord\12V/University_103_1 q9_OnOf	ON double in	spontaneous	valid	no error	identification number	irrelevant	
991 S VS 17/04/2015 10.38.56,400 HeidelbergNord\12V\University_103_1 q8_OnOf	ON double in	n spontaneous	valid	no error	identification number	irrelevant	
992 S VS 17/04/2015 10.36.56,400 HeidelbergNord\12V\University_103_1 ventilator	ON double in	n spontaneous	valid	no error	identification number	irrelevant	
993 S VS 17/04/2015 10.38.57,401 HeidelbergNord\12VUniversity_103_1 sw-auth	OFF	spontaneous	valid	no error	identification number	irrelevant	
994 S VS 17/04/2015 10.30.57,401 HeidelbergNord/12//University_103_1 gt_bloc	OFF	spontaneous	valid	no error	identification number	irrelevant	
996 STVS 17/04/2015 10:30:57:401 HeidelbergNord/12/Vichiversity_103_1 of OnOf	OFF	spontaneous	valid		identification number	irrelevant	
997 SIVS 17/04/2015 10.36.57.401 HeidelbergNord\12V\University 103 1 g2 OnOf	OFF double i	i spontaneous	valid	no error	identification number	irrelevant	
998 STVS 17/04/2015 10.38.57.401 HeidelbergNord/12V/University 103 1 g9 OnOf	OFF double i	i spontaneous	valid	no error	identification number	irrelevant	
999 S VS 17/04/2015 10.38.57,401 HeidelbergNord\12V\University_103_1 g8_OnOf	OFF double i	i spontaneous	valid	no error	identification number	irrelevant	=
1000 S   VS 17/04/2015 10.36.57,401 HeidelbergNord\12V\University_103_1 ventilator	OFF double i	i spontaneous	valid	no error	identification number	irrelevant	· ·
Ready		Pendi	ng: 26 To ackno	Wedge: 2 Hidd	on 0 List 1000	A/17/2015	10:44:36 AM
Tready		r chu	ing. 20 To delato	meage. 2 maa		En Annizona	10.44.5074
	Enable script debu	ud outout					
Call PQA message time	Global Script - Diago	ostics					
	Sideal Script Blaght	ostics					
	X I I 📾 🖬 é	5					
Call POA current time							
Gairr un current une	SICAM corint debug	aina io actival					
	Date: 17/04/2015	ging is active:					i i i i i i i i i i i i i i i i i i i
	Time: 10.26 E7.401						
	Time. 10.36.57,401		U-1-1	10.1			
	Message Group. ne	aeibergivora(12v	ioniversity_10	12_1			
	AnalyzerCallControl						E
	Start Script - Sicams	SCC_PUA_SetTime	eRange_MsgLi	ist.			
	TriggerVar: PQA_Ca	II_AlarmControl1ri	gger - dwState	: U, dwQuality	Code: 80		
	Start time: 2015-04-	1/107:36:57.0000	2				
	End time: 2015-04-1	7T11:36:57.00002	<u></u>				
1,000	Start Script - SCC_P	QA_CreateParFile	_V803.				
	The current Runtime	e Project name is:	WNBESXCL80	WinCC_Project	t_PQA_Systemtes	hPQA_Systemtes	st.mcp.
	cPQFile \\NBESXCL	80\WinCC_Project	_PQA_System	test, cszProje	ctName \\NBESXC	L80\WinCC_Proj	ect_PQA_Sys
	cPQFile \\NBESXCL	80\WinCC_Project	PQA_System	test(Export)PQ	Analyzer		-
	•		III.				F.

[pq_analyzer_aufrufen_04, 1, en_US]

Figure 7-32 WinCC Runtime with Button for Calling the SICAM PQ Analyzer

- Select the **AutoScroll** icon in the event list for the SICAM PQ Analyzer.
- Select the message from the event list for which you want to display fault records in your SICAM PQ Analyzer archive.
- To generate the parameter file for the SICAM PQ Analyzer, click Call PQA message time.
   As an alternative, you can generate the parameter file for the SICAM PQ Analyzer by clicking the icon for the SICAM PQ Analyzer (magnifier) in the toolbar of the event list.

The **Incident Explorer** opens and the fault records of the SICAM PQ Analyzer archive are displayed for the time of the message +/- 2 hours.

In the **GSC Diagnostics** window, the storage location of the new generated parameter file for the SICAM PQ Analyzer is displayed.

Clicking **Call PQA message time** again updates the display of the **SICAM PQ Analyzer**. The SICAM PQ Analyzer gets opened in the foreground.



## NOTE

If the Incident Explorer cannot be opened or the fault records are not displayed:

• Check the installation path of your SICAM PQ Analyzer and change it in the SCC_PQA_CreateParFile C script, if required.

You can find the C scripts in the **WinCC Explorer** under **Global Script > C-Editor > Project functions > SicamPAS > misc**.

In the C script, search for **cPQ_DEFAULT_PATH1** and change the path there. Then compile and save the changed C script.

If the SICAM PQ Analyzer archive is not located on the SICAM SCC computer, you have to adjust the global C script SicamSCC_PQA_SetTimeRange_MsgList.pas.
 You can find the C script in the WinCC Explorer under Global Script > C-Editor > Actions > Global actions.

In the C script, search for **cIPAddress** and replace the local IP address **127.0.0.1** with the IP address of your computer where the SICAM PQ Analyzer archive is located.

Then compile and save the changed C script.
# 7.7 System Control

#### Overview

When importing the SICAM graphic object library, internal and external **administrative tags** and several **global actions** are additionally created in the project. They serve for system control only.

# i

NOTE

Additional templates for global actions which you can use in your project are available in the installation directory of SICAM SCC, **PAS** subdirectory. Be aware of the configuration notes within the corresponding function.



#### NOTE

The functionality described in this section (e.g. bay/telecontrol blocking) depends on the support of the destination system - refer to the documentation of the destination system.

# 7.7.1 Administrative Tags

#### Internal administrative tags

Internal administrative tags are available in the WinCC Explorer under Internal Tags in the SICAMAdmin group. Tags starting with an @ character are required for the internal management of SICAM SCC and are not intended for the user.

Name	Туре
TextIDOffset	Unsigned 32-bit value
AckFlashing/QuitBlinking	Binary tag
@FlashFast	Signed 32-bit value
@FlashMedium	Signed 32-bit value
@FlashSlow	Signed 32-bit value
@Language	Unsigned 32-bit value
@AsyncTickx	Binary tag
@AlarmListFilter_WriteExt	Binary tag
@AlarmListFilter_ValueInt	Unsigned 32-bit value
ActivateControls	Binary tag
SubstVal_Float	Floating-point value
SICAMPASCCSynchState	8-bit character set text variable

#### Table 7-14 Required internal administrative tags

#### External administrative tags

External administrative tags are available in the WinCC Explorer under SICAM PAS PROTOCOL SUITE/ PAS Data Server/Project Name in the SicamAdmin_xxx group. They must be assigned as described below. The following applies to SICAM PAS:

The tag name of all external administrative tags is composed of 2 sections, i.e. a designation such as **Alarm-ListFilter** and a string of digits such as **107**. The string of digits is determined by the individual station and is generated by the SICAM PAS Wizard. The string of digits consists of 2 sections and a 0 as separator. The first section (e.g. 1) indicates the PAS project ID, and the second section (e.g. 7) indicates the HMI interface ID. The following applies to **SICAM RTUS**, **IEC 61850** and **IEC 60870-5-104 devices**:

The tag name of all external administrative tags is composed of 2 sections, i.e. a designation such as **Alarm-ListFilter** and a string of digits such as **1002**. The string of digits is station-specific and is generated by the SICAM IEC Wizard. The first digit (e.g. 10) represents the SICAM RTU project ID. A zero (0) serves as delimiter. The second digit (e.g. 2) identifies the communication protocol:

1 = IEC 60870-5-104 2 = IEC 61850

Table 7-15	Required	external	administrative	tags
				. J.

Name	Туре	Meaning
AlarmListFilter	Unsigned 32-bit value	for the definition of the filter function for the message/alarm list (see chapter 7.7.3 Message List Filter)
InitiatorCategory	Unsigned 32-bit value	for the cause ID
ConnectionState ⁶	Unsigned 32-bit value	status of the connection to the SICAM PAS system
ForceConnectionState ⁶	Unsigned 32-bit value	for controlling the connection to the SICAM PAS system
RedundancyMaster	Unsigned 32-bit	for distinguishing the servers in case of a redundant SICAM
(SICAM RTUs only)	value	SCC system
		1 = Master server
		0 = Redundant partner server

Additional tags are available for system-internal use.

#### NOTE

After any change of the **SICAM PAS project ID** or the **HMI interface ID**, check the assignment of the external administrative tags to the objects in the diagrams.

The **project ID** can be modified e.g. in SICAM PAS UI - Configuration.

The **HMI interface ID** can change after the deletion or re-creation of the SICAM SCC interface in SICAM PAS UI - Configuration and also after the creation of redundant WinCC connections in a SICAM PAS project. The **project ID** is assigned after the initial creation of a **SICAM TOOLBOX II/SCDSCD/IEC 60870-5-104 project** (import in the wizard). The project ID begins with the value **10**. It remains unchanged during an additional import using the wizard.

For the combined connection of SICAM PAS, SICAM RTUs, IEC 61850 and IEC 60870-5-104 devices in a SICAM SCC project, be aware to use unique project IDs for each station.

# 7.7.2 Initiator Category

The initiator category is defined in the **InitiatorCategory_xxx** external administrative tag. The tag is included in the command output to the automation system⁷. The content of the tag has the following significance:

2 = NEAR (default value)

3 = REMOTE

The contents of the tag must be changed to the value 3 if SICAM SCC is to act as the control center. To modify the value of the **InitiatorCategory_xxx** tag:

⁶ If connected to SICAM PAS V5 or V6

⁷ Connection to SICAM PAS/PQS

The tag is available in the WinCC Explorer under Tag Management/SICAM PAS PROTOCOL SUITE/ PAS Data Server/Project Name/SICAMAdmin_xxx.

- $\diamond$  Right-click the tag.
- Select Properties from the context menu.
   The Tag properties dialog opens.

	Tags Find 👂	•	📦 Properties - Tag		»
	Name	^	Name	InitiatorCategory_209	^
1	ActivateOnlineConfig_209		Comment		
2	AlarmListFilter_209		ID	1424	
3	CompKey Ext 209		Data type	Unsigned 32-bit value	
4	ConnectionName 209		Length	4	
5	ConnectionState 209		Format adaptation	DwordToUnsignedDword	
6	Exercit 209		AS Length	4	
7	EnceConnectionState 209		Address	VID0000000009,TID52,V50001,A00,C00,P0000000000,PN<>	
8	InitiatorCategory 209		AS tag name		
0	MSC Ack 200		Name space		
10	MSG_ACK_209		Assignment		
10	MISG_QUEUE_209		Communication driver	SICAM PAS Protocol Suite	
11	Projectio_Ext_209		Channel unit	PAS Data Server	
12	RedundancyMaster_209		Connection	newStation	
13			Group	SicamAdmin_209	
14			Linear scaling		
15			Linear scaling		
16			AS value range from		
17			AS value range to		
18			OS value range from		
19			OS value range to		
20			Limit Values		
21			Low limit		
22			High limit		
23			Start value	2	
24			Substitute value		_
25			Use Substitute Value		
26			Substitute value at low limit		
27			Substitute value at high limit		
29			Substitute value as start value		$\checkmark$
20					
29					
21		$\mathbf{v}$			
N.	Tags C >	.::			

[pascc610, 1, en_US] Figure 7-33 Tag properties

- ♦ Click to open the Limits/Reporting tab and define 3 as start value.
- ♦ Click **OK** to confirm your setting.

# 7.7.3 Message List Filter

Via the **Checkbox message list filter** graphic object, you can control for which changes of process data alarms must be entered in the alarm/event list. In the **SicamPas_AlarmListFilter.pas** C script, assign the **AlarmListFilter_xxx** external administrative tag.



## NOTE

If you do not use the **Checkbox message list filter** graphic object, the default settings (all options selected, time status deselected) are used.

To add the **Checkbox message list filter** graphic object to your diagram and to assign a tag:

 In the Graphics Designer, add the Checkbox message list filter object from the Project Library \Controls library directory to your diagram. 7.7 System Control

U) lis	Update SICAM message list entries on change of:		
-			
✓	status (validity)		
✓	location		
✓	cause		
✓	ID number		
✓	suplementary info.		
	time status		
✓	additional cause		

[pascc604, 1, en_US]

Figure 7-34	Checkbox	message	list filter	object
i igule / JT	CHECKDOX	message	inst inter	object



#### NOTE

The message list filter is neither effective for SICAM RTUs nor for the direct connection of IEC 61850-/IEC 60870-5-104 devices.

Messages referring to a value change cannot be deselected. They are always entered in the list. Apart from the **Time status**, all options are set by default.

♦ Under Global Actions, open the SicamPas_AlarmListFilter.pas C script.



[pascc605, 1, en_US]

Figure 7-35 C Script SicamPAS_AlarmListFilter.pas

The AlarmListFilter_xxx entry must be replaced by the corresponding alarm list filter tag.

- ♦ Select AlarmListFilter_xxx.
- ♦ Select Edit > Tag selection.

The tag selection dialog opens.

III Tag Management - WinCC Configuration	Studio				– 🗆 X
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp					
Tag Management «	📦 Tags [ SicamAdmin_109 ]	Find 🖌	<b>-</b> C	📦 Properties - Tag	»
Tag Management	Name		^	Selection	^
🗄 🍄 Internal tags	1 ActivateOnlineConfig_109			Object type	Tag
- L SICAM PAS PROTOCOL SUITE	2 AlarmListFilter_109			Object name	AlarmListFilter_109
PAS Data Server	3 AuthVID_109			General	
Substation South	4 ComFaultVID 109			Name	AlarmListFilter_109
	5 CompKey Ext 109			Comment	
	6 ConnectionName 109			ID	4411
SICAM_PAS_Demo_A	7 ConnectionState 109			Data type	Unsigned 32-bit value
SICAM_PAS_Demo_IE	8 ExecCI 109			Length	4
SicamAdmin_109	9 EnrceConnectionState 109			Format adaptation	DwordToUnsignedDwo
Station_South_10kV_E	10 InitiatorCatogony 100			AS Length	4
🔄 📙 System Info 🛛 👻	11 Interface Admin VID 100			Address	VID0000000009, TID
< >	11 InterfaceAdminVID_109			AS tag name	
	12 InterraceOperVID_109			Name space	
Tag Management	13 MSG_ACK_109			Assignment	
Alarm logging	14 MSG_Queue_109			Communication driver	SICAM PAS PROTOCO
Alarm logging	15 OprReadyVID_109			Channel unit	PAS Data Server
Tag Logging	16 ProjectID_Ext_109			Connection	SubstationSouth
	17 RedundancyMaster_109			Group	SicamAdmin_109
Text Library	18 ServiceAdminVID_109			Linear scaling	
	19 ServiceOperVID_109			Linear scaling	
User Administrator	20 💥			AS value range from	
	21			AS value range to	
User Archive	22			OS value range from	
40	23			OS value range to	
Norn	24			Limit Values	
Disturg Tree	25			Low limit	v
	26			I II a la la cara	
2:2: Text and graphics lists	27				
	28		~		
	H + H Tags		> .::		
Ready NUM		German (Germany)		Table: 19 Tags 10	0% ⊝



Tag Selection dialog

 Select the tag (e. g. AlarmListFilter_1011) and click OK to confirm. The tag is inserted into the C script.

The AlarmListFilter_1011 tag must now be entered as trigger.

 In the C script, right-click the AlarmListFilter_1011 tag and select Info/Trigger from the context menu. The Properties dialog opens.

Properties	?	×
Info Trigger		
Timer Tag @AlamListFilter_ValueInt @AlamListFilter_WriteEx AlamListFilter_xx	Add Delete Change	
< >		
OK Cancel A	\pply	Help



Figure 7-37 Inserting a Trigger

- ♦ Select the **Trigger** tab.
- ♦ Delete the AlarmListFilter_xxx tag and add the AlarmListFilter_1011 tag.
- ♦ Click **OK** to close the dialog.
- ♦ Compile and save the C script.

#### Structure of the AlarmListFilter tag



#### NOTE

In order to define a specific filter, you do not need to use the Message list filter checkbox and the global action. You can set the start value of the **AlarmListFilter_xxx** tag directly to the desired value.

The value is a bit combination as illustrated in figure 6-36. If the bits have been set, a new message is entered in the message lists when the corresponding property of an item of information changes.

Value (decimal)	Value (hex)	Meaning	Selected by default
0	0x0000000	Value (cannot be discon- nected)	x
1	0x0000001	Status	х
2	0x0000002	Location	х
4	0x0000004	Cause	х
8	0x0000008	ID number	х
16	0x0000010	Additional information	x

Table 7-16 Value of the AlarmListFilter tag
---------------------------------------------

Value (decimal)	Value (hex)	Meaning	Selected by default
32	0x0000020	Time status	
64	0x00000040	Additional cause	x

The options marked with an x are predefined by default.

# 7.7.4 Switching Authority

For the control of switching authorities, use the switching authority tags mapped in SICAM PAS UI – Configuration. These tags are stored among the status tags of the SICAM SCC interface. The control of the switching authority is only supported for the SICAM PAS target system, but neither for

SICAM RTUs nor for directly connected IEC 61850/IEC 60870-5-104 devices.

Only map the switching authority tags in the **monitoring direction**.



## NOTE

In order to be able to control the switching authority, switching authority groups for the SICAM SCC interface must have been assigned in SICAM PAS.

The following 2 graphic objects are available for implementing the switching authority:

- PAS switching authority (Authority checkbox) All states can be controlled via this checkbox.
- PAS switching authority (Switching authority button) This button only controls the Near 1/Remote 1 switching.

#### Switching authority checkbox

This dialog provides the Read and Write buttons. During runtime,

- the contents of the corresponding switching authority tag can be read in and shown by clicking **Read**.
- the contents of the checkbox can be written into the corresponding switching authority tag by clicking Write.

PAS Switching Authority		
	remote 1	
🔲 near 1	remote 2	
near 2	remote 3	
near 3	remote 4	
	remote 5	
Read	Write	

[pascc601, 1, en_US]

Figure 7-38 Switching Authority Checkbox

#### Switching authority button

This dialog provides a button for switching between **Near** and **Remote** during runtime. The button text changes depending on the current switching authority.

Near and Remote in this dialog correspond to Near 1 and Remote 1 in the Switching Authority checkbox.

PAS Switching authority						
Text						

[pascc607, 1, en_US]

Figure 7-39 Switching Authority Button

To add the **PAS Switching authority** graphic object to your diagram and assign a tag:

- ♦ In the **Graphics Designer**, add the **PAS switching authority** object from the library to your diagram.
- ♦ Assign the **PAS switching authority** object the corresponding switching authority tag. To do this, rightclick the object.
- ♦ Select Properties in the context menu. The Object properties dialog opens.

Properties Events					
Customized object Geometry Miscellaneous Group0_15 Group16_32 SICAM Color Buttons Effects	Attribute Ausgabewert	Static 0,000000e+000	Dynamic SICAMPAS_110kv_BayAuthorityValue	Update Cycle 2 s	Indir

[pascc602, 1, en_US]

Figure 7-40 Properties of the PAS Switching Authority Object

- ♦ Select Tags from the Properties tab.
- ♦ Right-click the **Dynamic** column in the **OutputValue** row.
- Select Tag from the context menu.
   The tag selection dialog opens.

III Tag Management - WinCC Configuration	Studio					- 1		×
File Edit View Tools Help								
Tag Management	Game Tags [ SICAM PAS ]	Find	Q -		Properties - Grou	n		>>
	Name	_ mu			Foloction	·P		
	1 CICAM DAG Authorita/jolua		^		Dhiect type	Group		
Internal tags	2 SICAM_PAS_Authonityvalue				Object type	SICAM PAS		
E- SICAM PAS PROTOCOL SUITE	2 215				Seneral	bionin_1715		
□- PAS Data Server	3				Vame	SICAM PAS		
SubstationSouth	4			I	D	53		
SICAM_PAS	5			EA	Assianment			
🥞 SICAM_PAS_Demo_A	0			C	Communication driver	SICAM PAS PROTOCOL S	UITE	
				C	Channel unit	PAS Data Server		
😤 SicamAdmin_109	8			C	Connection	SubstationSouth		
Station_South_10kV_E	9			ΞV	/arious			
- System Info	10			C	Creator ID	0		
< >	11			L	last Change	09.01.2017 15:54:52		
	12							
Tag Management	13							
	14							
Alarm logging	15							
Tag Logging	16							
ing cogging	17							
Text Library	18							
	19							
User Administrator	20							
	21							
User Archive	22							
- 1 Jan 19	23							
	24							
Picture Tree	25							
n	26							
22 Text and graphics lists	27							
	28		~					
-	HIFH Tags	1 <	بر					
Ready NUM		German (Germany)			Table: 1 Tag	100 % 🕞 🗸 🗸		÷.,

[pascc603, 1, en_US]

Figure 7-41 Tag Selection

♦ Select the desired switching authority tag and click **OK**.

While the WinCC project is active, the current setting of the switching authority is shown via the **PAS** switching authority (PAS switching authority (complete)) object.

You can now request a change of the switching authority from SICAM PAS.

Change the settings in the PAS switching authority object and then click Write to transmit them to SICAM PAS.

The settings are transmitted to SICAM PAS and checked for reliability. If the requested switching authority is not permissible, it is reset to the previous value.



#### NOTE

To log the current switching authority setting in the message lists, the switching authority tag in SICAM PAS UI – Configuration must be mapped to the SICAM SCC Alarm Logging system within the **SICAM SCC status messages**.

# 7.7.5 Bay/Telecontrol Blocking



#### NOTE

The functions described in this section cannot be used for connections via IEC 60870-5-104 and IEC 61850.

#### 7.7.5.1 Device-Specific Blocking

The functions described in this section are used to block all the information of a device, an interface or an application in case of a connection to SICAM PAS/PQS.

The following graphic objects are available for controlling the bay/telecontrol blocking:

- Set bay blocking: Click this button to set/reset the bay blocking.
- Set telecontrol blocking: Click this button to set/reset the telecontrol blocking.
- **Ignore telecontrol blocking**: Click this button to ignore/obey the telecontrol blocking for a control center.

÷	÷	÷	Г	•	•	•		•					•	•	•	•	•	1	÷	÷	÷	:
							B	ay	B	01	c	cin	١g					ł				
•	·	·	-	•	•	•	•	•	•	•	•	•	•	•	•	•	-	÷.	·	·	·	•
•	·	·	• •	·	·	·	·	·	·	·	·	·	·	·	·	·	·	·	·	·	·	•
•	·	·	-		•	•	•	•			•	•	•	•	•	•		1	·	·	·	•
•	·	·		-	Го	de	0	or	hte	ol	P	lo	ck	cin	0			÷	·	·	·	•
•	·	·				10	-0		IU	U	-	10	u	AII.	'y			÷	·	·	·	•
•	·	·	-	•	•	•	•	•	•	•	•	•	•	•	•	•	•	1	·	·	·	•
•	·	·	• •	·	·	·	·	·	•	•	·	·	·	·	·	·	·	·	•	·	·	•
1					•				•	•			•	•	•				•	-	1	•
				Te	ale	ec	0	nt	ro	I F	31c	C	kir	no	2	2					1	•
														.9							1	•
								•					•									

[pascc611, 1, en_US]

Figure 7-42 Bay/Telecontrol Blocking Graphic Object, Buttons

Depending on the status of the bay/telecontrol blocking, the texts shown on the buttons change during runtime.

The buttons (graphic objects) must be assigned the corresponding device tags.

To add the Set bay blocking to your diagram and assign the tags:

- ♦ In the **Graphics Designer**, add the **Insert bay blocking** button object from the library to your display.
- $\diamond$  Right-click the object.
- Select Properties in the context menu.
   The Object properties dialog opens.



[pascc612, 1, en_US]

Figure 7-43 Properties of the BayBlockingButton Object

- ♦ Select SICAM from the Properties tab.
- Right-click the Dynamic column in the Master BlockOper (*.Value) row.
- Select Tag from the context menu.
   The tag selection dialog opens.

2 ≥ 33 🗰 🛛 🖂 WinCC Taos		- <b>-</b>	f	
er: Data source:				
SICAM IEC Communication Suite     SICAM PAS Protocol Suite     SICAM PAS Protocol Suite     SICAM PAS Protocol Suite     SICAM PAS Protocol Suite     SICAM PAS     SICAM PAS     SICAM PasV808_IEC61850_61850IF_SIP_7SL87     SICAM PasV808_IEC61850     SICAM PasV808_IEC61850     SICAM PasV808_IEC61850     SICAM PasV808_IEC61850     SICAM PasV808_CFC_SoftPLC_Info2PLC     SICAM PasV808_CFC_SoftPLC_Info2PLC     SICAM PasV808_CFC_SoftPLC_Cmd2PLC     SICAM PasV808_CFC_SCC_IF_SCC_CC     SICAM PasV808_T104M_T104IF_T104Device     SICAM PasV808_T104M_T104IF_SI63     SICAM PasV808_T104M     SICAM PasV808_T1	~	Name           SICAM_PasV808_T103M_T103IF_BIkAdm           Ei         SICAM_PasV808_T103M_T103IF_BIkOpr           Ei         SICAM_PasV808_T103M_T103IF_Opr	Ty UI P2 P2	/pe nsig AS_I AS_I

[pascc613, 1, en_US] Figure 7-44 Tag Selection

- ♦ Select the desired **BlkOpr.Value** tag and click **OK**.
- ♦ Link the **BlockAdminXXX** attribute to the **BlkAdm** tag.

Provided that a WinCC project is active, you can now set or reset the bay blocking by means of the **Bay blocking** button.

You can insert the **Telecontrol blocking** button and **Ignore telecontrol blocking** button graphic objects in the same way and assign them the same tags. The **BlkOpr.Value** and **BlkAdm** tags include information for all 3 graphic objects.

As an alternative to the buttons, you can use the CheckboxBay/Telecontrol Blocking graphic object.

bay blocking	Set
telecontrol blocking	Set

[pascc614, 1, en_US]

Figure 7-45 Bay/Telecontrol Blocking Checkbox Graphic Object

#### 7.7.5.2 Object-Specific Blocking

To block individual items of process information, you can set/undo a bay blocking/telecontrol blocking on a switching device object via a status dialog. After setting a bay block this information can also be substituted, see chapter 4.4.6 Runtime Dialogs of SICAM Switch Controls.

The **PAS_SetBlockState_V801** function is available as a C script for the object-specific blocking of other objects, see chapter 7.6.3 Object-Specific Blocking.

#### 7.7.5.3 Ignoring Bay Blocking

You can use the **Button Ignore Telecontrol Blocking** graphic object in order to inform a control center connection on the interface level that this connection may ignore the telecontrol block.

# 7.7.6 Triggering a General Interrogation in Case of IEC 61850 Connection

A template for the global action **Sicam_IEC61850_DeviceGI.pas** for triggering a general interrogation to directly connected IEC 61850 devices is available in the installation directory of SICAM SCC, **PAS** subdirectory. This template is used per device and enables a general interrogation for selected devices.

Use this script if a message/measured value blocking, e.g. on a SIPROTEC device, is undone. In this case the device does not transmit an up to date image, which means that SICAM SCC must perform a general interrogation.

Be aware of the configuration notes within the function.

# 7.7.7 Changing Device Parameters via IEC 61850

#### 7.7.7.1 Switching the Parameter Groups

#### Prerequisites

In DIGSI 5 the **Via controller** setting must be selected as **Active parameter group** in the corresponding device settings.

#### SICAM SCC functionality

Tags are available for switching the parameter groups. These tags must be imported via the SICAM IEC 61850 Wizard and the SICAM SCC - IEC61850 data mapping Editor and used accordingly.

Table 7-17Tags for switching the parameter groups

Tags	Meaning
Tag extension:	This information tag indicates the number of existing/
• *.SettingGroup.NumberOfSG	possible parameter groups in the device.
Or as IEC61850 address:	
• *.SGCB.NumOfSG	
Tag extension:	This tag exists in:
• *.SettingGroup.ActiveSG	Information direction (indicates which param-
Or as IEC61850 address:	eter group is currently active)
• *.SGCB.ActiveSG	<ul> <li>Command direction (activates one/this specific parameter group)</li> </ul>

#### Switching the parameter group

To switch the active parameter group, you must set the ***.ActiveSG** command tag to the value of the desired parameter group:

♦ To modify the value of the *.ActiveSG command tag, use a SICAM function, see chapter 7.6.1 Commands, or the SICAM measured value with operating script object.

#### 7.7.7.2 Modifying Individual Device Parameters/Settings Online

#### Prerequisites

The **Block IEC61850 parameter changes** option must not be activated in the corresponding device settings in DIGSI 5.

#### SICAM SCC functionality

The tags available for online configuration must be imported using the SICAM IEC 61850 Wizard and the SICAM SCC - IEC61850 data mapping Editor and used accordingly.

Table 7-18	Tags for onli	ne configuration
------------	---------------	------------------

Tags	Meaning						
Tag extension:	This command tag is used to select/set the paramet						
• *.SettingGroup.EditSG	group to be edited.						
Or as IEC61850 address:	rejected.						
• *.SGCB.EditSG							
Tag extension:	With this command tag and the value 1 all the						
• *.SettingGroup.ConfirmEdit	changes performed in the selected parameter group						
Or as IEC61850 address:							
• *.SGCB.ConfirmEdit							

Every parameter has an information tag and a command tag assigned.

#### Modifying device parameters/settings online

To modify device parameters/settings online:

- ✤ To activate the change process, set the *.EditSG command tag to the value of the desired parameter group.
- ♦ To modify one or several parameters, set the corresponding command tag to the desired value.
- ♦ To confirm the change, set the *.ConfirmEdit command tag to the value 1.

- or -

♦ To reject the change, set the *.EditSG command tag to the value 0.

Use a SICAM function to set the ***.EditSG** and ***.ConfirmEdit** command tags, see chapter **7.6.1** *Commands*. You cannot use the **SICAM measured value with operating script** object for setting the ***.EditSG** and ***.ConfirmEdit** command tags.

You can use a SICAM function to define individual parameters, see chapter 7.6.1 Commands, or the SICAM measured value with operating script object.

# 7.8 SICAM SCC Runtime Data Server

To increase the quantity scopes supported by SICAM SCC, the **SICAM SCC Runtime Data Server** component was introduced with Version 8.00. With SICAM SCC V8.00 or higher, up to 20,000 switching device objects per WinCC project and up to 2,000 controls per picture can be managed with the aid of this component.

The **SICAM SCC Runtime Data Server** component processes all process data of the SICAM SCC project independently of whether they are being shown in the picture or not.

SIMATIC WinCC, Version 7.0 SP3 or higher, is a prerequisite for the SICAM SCC Runtime Data Server component.



[Runtime_Data_Server, 1, en_US]

Figure 7-46 SICAM SCC Runtime Data Server

The SICAM SCC Runtime Data Server supplies the controls with the relevant, calculated process data required for display. The SICAM SCC Runtime Data Server is automatically started and stopped with the WinCC Runtime. The blinking states between the redundant WinCC servers are compared in redundant SICAM SCC systems.

# 1

#### NOTE

You can continue to operate existing SICAM SCC projects of version 7.xx with the current **IndustrialX Controls** without using the SICAM SCC Runtime Data Server. In order to continue to use current IndustrialX Controls (switching device objects) the IX State Sync must also be continue to be used.

The optionally installable **IX State Sync** redundancy component is entirely replaced by the SICAM SCC Runtime Data Server and no longer is required when using the ActiveX Controls of V8.0 or higher.

In order to be able to use the SICAM SCC Runtime Data Server for existing SICAM SCC projects, the IndustrialX Controls (Switch and Bay Overview) must be replaced with the SICAM Switch Controls and SICAM Bay Overview Controls.

Using a task available in the SICAM Toolbar you can replace all IndustrialX Controls of a picture at the same time, see chapter 6.5 Predefined Tasks.



#### NOTE

Be aware that pictures and settings configured under the **Bitmap** option are not applied for **Send QoC in command value**.

Scripts or actions configured for properties or events of the switching device objects are not applied during conversion. They cannot be applied because the property types and events are not fully compatible. The scripts and actions must be created again after the conversion.

All further object settings are applied during conversion.

# 7.9 Language Settings

#### Overview

When defining the language for SIMATIC WinCC/SICAM SCC, several system levels are distinguished. The language must be switched at different locations.

#### • Language of the WinCC user interface

The language of the WinCC user interface is set in the WinCC Explorer. Any language enabled during the installation of WinCC can be set for the WinCC user interface.

#### • Configuration language

The configuration language is set directly in the editor which you are using for configuration, e. g. the Graphics Designer. You can select further languages as configuration languages in addition to the languages installed with WinCC.

#### Runtime language

The runtime language and the runtime default language are defined via the start configuration of the runtime computer. You can select further languages as runtime language in addition to the languages installed with WinCC.

More detailed information on the language setting is available in the WinCC Information System under **Start > SIMATIC > WinCC > WinCC Information System**.

Specific graphic objects of SIMATIC WinCC are added to SICAM SCC. The distinction with regard to the language setting also refers to these additional graphic objects.



#### NOTE

Before the first data import, define the runtime language required for the runtime texts. The configuration data must be updated with the same language setting in order to ensure that the texts are stored in the correct language in the SIMATIC WinCC text library.

To use additional runtime languages, the texts in the SIMATIC WinCC text library can be translated into the corresponding language.

If you switch the runtime language in SIMATIC WinCC, you have to close and re-open the WinCC project before import/update, in order to get the texts of the import data for the Alarm Logging System to be written into the text library in the correct language.

# 7.9.1 Language Setting for SICAM Graphic Objects

Several languages (e. g. English, German) are available by default for the SICAM graphic objects. You can switch between these languages without any preliminary steps.

It is also possible to use additional languages. To do this, some preliminary steps have to be performed (as described below).

#### • SICAM Switch Controls

The texts for the Runtime dialogs of switching device objects, SICAM SCC V8.00 or later (SICAM Switch Controls), are stored in the **SICAMSwitch.xml** file. This file includes a block for each language.

#### • Other SICAM graphic objects

The dialog/menu texts are stored in several text files for the individual languages. For the SICAM add-in within the Graphics Designer, the **SICAMToolbar_xxx.txt** file is used. The **xxx** wildcard is used for the language code, e. g. **409** for English. During the start-up, SICAM SCC loads these text files and shows the included texts on the user interface.

The text files consist of individual rows. Each row includes the text ID, one or several space characters and the text string. The text string is placed between quotation marks; this text is displayed.

The following table indicates for which program interfaces the described language settings are valid and which text files are available.

#### Table 7-19 Language setting - SICAM graphic objects

Program's User Interface	Text File
Runtime dialogs of circuit breakers and disconnectors, SICAM SCC V8.00	SICAMSwitch.xml
or later	
Properties dialog for circuit breakers and disconnectors	PCCIX_xxx.txt
Runtime dialogs for circuit breakers and disconnectors	
Error messages/information regarding circuit breakers and disconnectors	]
Dialog for defining the properties of the bay overview	PASCC_BO_xxx.txt
Error messages/information regarding the bay overview	]
Toolbar for topological coloring	SICAMToolbar1_xxx.txt
(in the Graphics Designer)	
Upgrade Controls dialog	
to be opened via SICAM > Upgrade Controls in the Graphics Designer	

All languages which can be set as runtime language can be used for texts shown during runtime (e. g. texts in the runtime dialogs).

All other texts (e. g. texts of the properties dialogs for circuit breakers and disconnectors) can only be shown in the languages defined for the WinCC user interface.

The texts of the properties dialogs for SICAM graphic objects, SICAM SCC V8.00 or later (SICAM Switch Controls and SICAM Bay Overview Controls), are not included in the **SICAMSwitch.xml** file. They are stored in the **SICAMSwitchxxx.Ing** and **SICAMBOxxx.Ing** language DLLs.

#### Preparing the language setting

To prepare the language setting:

First, determine the code of the desired language. All available languages are listed in the information system of SIMATIC WinCC.

- ♦ To open the information system, click **Start > SIMATIC > WinCC > WinCC Information System**.
- Browse for the term Language code and open the Language code window.
   The list shows all available languages with their code (e. g. 0x040A/1034 for Spanish).

#### Adding the language for Runtime dialogs of switching device objects, SICAM SCC V8.00 or later

The SICAMSwitch.xml file is stored in the following directory: ...\Siemens Energy\SICAM\SCC\bin.

- ♦ Open the **SICAMSwitch.xml** file using an XML Editor.
- ♦ Copy an existing language block.
- ♦ Enter the language ID of the new language, e.g. 1034 for Spanish.
- ♦ Enter the texts for the new language.
- ♦ Save and close the XML file.

#### Creating language-dependent text files for other SICAM graphic objects

The text files are located in the following directory: ...\Siemens Energy\SICAM\SCC\bin or ..\Siemens\WinCC \bin.

- ♦ Copy the **SICAMToolbar_409.txt** file. 409 is the language code for English.
- ♦ Rename the file (e. g. to SICAMToolbar_40A.txt for Spanish).
- ♦ Open the SICAMToolbar_40A.txt file using a text editor.
- ♦ All texts placed between quotation marks can now be adjusted to the desired language.
- ♦ Save and close the text file.
- ♦ Create all other text files, too.

#### Language of the WinCC user interface

To define the language of the WinCC user interface, click **Tools > Language** in the WinCC Explorer. You can select any language which has been enabled during the installation of WinCC. As soon as you have defined the desired language, all SICAM graphic objects can be configured in this language.

#### Switching the runtime language

The runtime language can be selected in the **Computer Properties** dialog, **Parameters** tab (see chapter *3.2.3 Defining Computer Properties*). The language you select in this tab is used during the start of the runtime. Alternatively, you can switch the runtime language during runtime (see chapter *7.9.2 Switching the Language During Runtime*).

# 7.9.2 Switching the Language During Runtime

If you have defined several languages during the configuration of a project, you need to configure a control element via which the operator can set the desired language during runtime. SICAM SCC includes a pre-configured control element which you can use in your project.

This paragraph explains how to define the switchover to the Spanish language.

For the language switching to function properly, the text files must be available in the **...\Siemens Energy \SICAM\SCC\bin** Spanish directory with the **40A** language ID.

Proceed as follows to configure the switching of the runtime language:

#### Adding a control element to a display

- In the Graphics Designer, open the display to which you want to add the control element required for switching the language.
- ♦ Insert the **Button select language** object from the SICAM graphic object library into your display.

Image: Second secon	Size	Last Change
Project Library Name	Size	Last Change
- Craphic objects for SICAM SAS>		
i 🚔 📩 Complia chierte ef annuisceancien 🛛 👘 👘	22878	30.11.16 15:43
Button POA current time	4330	30.11.16 15:44
Alarm Logging templates	3505	30.11.16 15:44
Bay overview objects	2550	30.11.16 15:42
Measured/Metered values	4729	30.11.16 15:46
Button switching authority (simple)	21285	30.11.16 15:45
Enclosed a second secon	19330	30.11.16 15:41
Checkbox bay/telecontrol blocking	29628	30.11.16 15:46
ChackPay apphla corint dahura outp	2210	20 11 16 15.40

[pascc423, 1, en_US]



Using the default control element, you can switch between the German and the English language. In order to be able to define e. g. the Spanish language during runtime, this language must be configured accordingly.

#### Configuring language switchover

To define an additional option for switching to the Spanish language:

- $\diamond$  Copy a button.
- ♦ Open the **Object properties** of the new button.
- ♦ Enter the new language for the attribute **Text** in the **Properties** tab.

- ♦ Modify the **Tooltip Text** attribute.
- Customize the **Text** and **Tooltip Text** attributes also for the other configuration languages used.
- In the Events tab, double-click Mouse Action.
   The Action Editor opens.

Edit Action		?	×	<
🗏 🛃   🐰 💷 🕮 🖏   🗙   🄊	ĈB   🛗 🎯 🕅 🗃 🕞   💽 💽 👔			
Project functions Standard functions	<pre>tinclude "apdetap.h" void OnClick(char* [pszPictureName, char* lpszDbjectName, char* [pszPropertyName) {     //###############################</pre>			
<b>D</b>	OK		Cancel	
Ready	Line:	18 Co	lumn: 3	к., "

[pascc424, 1, en_US]

Figure 7-48 Editing the Action for Switching the Language

- ♦ Change the language code to **0x040A** for Spanish at two different locations.
- ♦ Compile the action and close the editor.
- $\diamond$  Save your display.

The configuration of the language switchover is now completed, and you can switch between 3 different languages during runtime.



[pascc425, 1, en_US]

Figure 7-49 Switching the Language During Runtime

# 7.10 Communication with SICAM DISTO

#### **TCP/IP** Connection

The TCP/IP connection is always set up by SICAM DISTO, i.e. the IEC 61850-Client waits until the connection has been set up. The Port 5335 used is determined via the service name **DISTO61850**. This service name must be entered in the **Services** file located in the following directory: <WINDIR>\system32\drivers\etc\services.

 Insert the following line into the Services file: DISTO61850 5335/tcp #Disto



#### NOTE

If SICAM DISTO is used on a separate computer, open the DISTO port via firewall rules.

#### IEC 61850 file transfer mode

The **file transfer services** are used in order to transmit the fault records from IEC 61850 servers. The protection line of devices from which fault records are to be requested must be defined as **IEC=61850-FT**. The **StatNo** parameter corresponds to the subsequent calculation of the LAN station number.

#### Calculation of the LAN station number

The LAN station number to be entered in SICAM DISTO is calculated via the number of the IEC 61850 Data Server Station and the LAN number of the device to be connected.

StatNo = StatIndex * 512 + LANNo

Significance of the individual elements of the formula:

- StatNo = LAN station number to be entered
- **StatIndex** = Number of the station in the station list in the IEC 61850 Data Server (SIMATIC WinCC), starting with 0
- LANNo = LAN number defined for the device, e.g. in the SICAM Toolbox II or in the SICAM IEC 61850 Wizard with direct connection to a IEC 61850 device.

You can view the LAN station number in the parameters of a tag of the corresponding device.

7.10 Communication with SICAM DISTO

arameter string			
and inclusion stilling			
Variable spezific pa	rameter string:		-
D12,V50001,A03,0	00,P0000002221,PN <q0cswi1_mod_stval></q0cswi1_mod_stval>		Туре
			Unsigned 32-bit value
/alue ID	0000002220		Unsigned 32-bit value
Tag ID	12	84_IED_000a_CTRL_Q0CSWIT_Mod_ctiva	Unsigned 32-bit value
		d 32-bit value 🔻	Unsigned 32-bit value
Command model	100		Unsigned 32-bit value
ALG entry	03	00002220,TID12,V50001,A0 Select	Unsigned 32-bit value
Partner value ID	0000002221		Unsigned 32-bit value
		ounsignedDword	Signed 32-bit value
'artner name	Q0CSWI1_Mod_stVal	Computer-local update	Unsigned 32-bit value
² artner name Additional paramete	QOCSWI1_Mod_stVal	Computer-local update	Unsigned 32-bit value Unsigned 32-bit value
^J artner name Additional paramete	Q0CSWI1_Mod_stVal er:	Computer-local update	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value
Partner name Additional paramete Property	QOCSWI1_Mod_stVal	Computer-local update	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value
Partner name Additional paramete Property MsgName	Q0CSWI1_Mod_stVal	Computer-local update	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value
² artner name Additional paramete Property MsgName ValueTextGroup Taol occion	Q0CSWI1_Mod_stVal	Computer-local update	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag
² artner name Additional paramete <u>Property</u> MsgName Value TextGroup TagLogging TagLogging	Q0CSWI1_Mod_stVal	Computer-local update	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value
² artner name Additional paramete <u>Property</u> MsgName Value TextGroup TagLogging TagLoggingInfo	Q0CSWI1_Mod_stVal           er:           Value           Q0CSWI1_Mod_ctIVal           0           false	Computer-local update	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value
Partner name Additional paramete Property MsgName Value TextGroup TagLogging TagLoggingInfo 161850 ADR	Value	Computer-local update Tag Value Range Value1 Ualue2 0	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value Signed 32-bit value
Partner name Additional paramete Property MsgName Value TextGroup TagLogging TagLoggingInfo I61850 ADR (61850 LAN Case Dual	Q0CSWI1_Mod_stVal           value           Q0CSWI1_Mod_ctlVal           0           false              IED_0004CTRL/Q0CSWI1.Mod.ctlVal	Computer-local update	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value Signed 32-bit value Unsigned 32-bit value
Partner name Additional paramete MsgName Value TextGroup TagLogging TagLoggingHierar TagLoggingHierar TagLoggingInfo IG1850_LAN IG1850_LAN IG1850_LAL IG1850_LCAL IG1850_LCAL	Q0CSWI1_Mod_stVal           er:           Value           Q0CSWI1_Mod_ctIVal           0           false              IED_0004CTRL/Q0CSWI1.Mod.ctIVal           1           0           14	Computer-local update Tag Value Range Value1 Value2 0 alog, please make certain that the name of the	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value Signed 32-bit value Unsigned 32-bit value Unsigned 32-bit value
Partner name Additional paramete Property MsgName Value TextGroup TagLogging TagLoggingHierar TagLoggingIhro 161850_ADR 161850_CDC FW FW	Q0CSWI1_Mod_stVal           er:           Value           Q0CSWI1_Mod_ctIVal           0           false              IED_0004CTRL/Q0CSWI1.Mod.ctIVal           1           0           14	Computer-local update Tag Value Range Value1 Value2 0 alog, please make certain that the name of the	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value Signed 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value
² artner name <u>Property</u> MsgName Value TextGroup TagLogging TagLoggingHierar TagLoggingIhierar TagLoggingIhierar (61850_LAN 161850_CDC EW EW EW EW	Q0CSWI1_Mod_stVal           er:           Value           Q0CSWI1_Mod_ctIVal           0           false           1           0           14           0           false	Computer-local update Tag Value Range Value1 Value2 0 alog, please make certain that the name of the	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value Signed 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value
Partner name Additional paramete Property MsgName Value TextGroup TagLogging TagLoggingHrfo I61850 ADR I61850_CDC EW FWR ≮	Q0CSWI1_Mod_stVal       er:       Value       Q0CSWI1_Mod_ctlVal       0       false       IED_0004CTRL/Q0CSWI1.Mod.ctlVal       1       0       14       0       false	Computer-local update Tag Value Range Value1 Value2 0 alog, please make certain that the name of the	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value Signed 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value
Property MsgName Value TextGroup TagLogging TagLoggingHierar TagLoggingInfo I61850_ADR (61850_LAN I61850_CDC EW FWR <	Q0CSWI1_Mod_stVal       ar:       Value       Q0CSWI1_Mod_ctlVal       0       false       1       0       14       0       false	Computer-local update Tag Value Range Value1 Value2 0 alog, please make certain that the name of the	Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Unsigned 32-bit value Binary Tag Unsigned 32-bit value Unsigned 32-bit value

[disto_01, 1, en_US]

Figure 7-50 Viewing the LAN station number

# 7.11 SNMP – SICAM Network Manager (NWM)

# 7.11.1 Introduction

SNMP objects are managed in a kind of database in each device (agent) to be managed. The database contains a number of objects which can be read and/or written via the network.



## NOTE

The SICAM Network Manager requires a separate license.

#### Management Information Base (MIB)

The **Management Information Base (MIB)** is most important because it contains all the objects to be managed for an agent. In order to be able to define SNMP objects, the MIB must be available in both the agent and the network management system.

The MIB tags are implemented in the agent software and uniquely addressable. All the objects in an agent are addressed based on a globally unique identification scheme designed as a number string. This number string is transmitted to the agent when querying an object. As a result of the query, the agent returns the object contents to the management station.

SICAM SCC also provides a collection of MIB files as a basis for defining the NWM parameters. You can extend this collection yourself.

The **Default_MIB** folder is located on the SICAM SCC DVD in the **ProductEnhancements** folder. Copy this folder to any drive.

#### **Basic Procedure**

The SNMP is configured with the following basic steps:

- Starting the SICAM Network Manager
- Finding and defining agents
- Loading the MIB container file MibSicamSCC.mcf
- Selecting and configuring MIB objects
- The report starts once the configuration has been completed; the parameters are processed and the Tag Management is updated in the background
- Defining the SNMP IP address in the Tag Management
- Starting the Runtime



#### NOTE

Consider the information in 7.1.3 Configuration for Improved Message Display in the Case of Redundancy.

### NOTE

To define that the SICAM SCC computer is monitored by a higher-level SICAM SCC using SNMP, open the SNMP ports via firewall rules.

# 7.11.2 SICAM Network Manager – Dialog

#### **SNMP** Agents

In this view you can find and define agents and specify the lined variables (identical with the MIB objects view).

To specify these linked variables, at least 1 MIB object must have been defined (in the MIB objects view).

MP agents MI	B objects									
Name	IP address	Active	Cycle	Time-out	Retries	Community	WR-Commu	SNMP-Version	Description	New
										Edit
										De/Activate
										Delete
										Clone
										Import
										Export
										Ping
-										Find
ked variables									>	
ame		Offset	Name	1			Object			New
										Edit
										Delete
										Delete all

[sc_snmp_network_manager, 1, en_US]

Figure 7-51 SICAM Network Manager Dialog, SNMP Agents View

Element	Explanation
New	Opens the <b>Edit agent</b> dialog for creating a new agent.
Edit	Opens the Edit agent dialog for editing the agent selected in the list.
De/Activate	Activates or deactivates the agent selected in the list. The entry in the <b>Active</b> column changes to <b>Yes</b> or <b>No</b> .
Delete	Deletes the agent selected in the list.
	The agent can only be deleted if no variable is linked any more.
Clone	Opens a dialog for cloning the variables of the agents selected in the list to the target agent.
Import	Opens the file manager for importing from the exported agent.
Export	Opens a dialog for exporting (and thus backing up) agents with variables and objects.
Ping	Sends a ping to the agent selected in the list and shows the result (status, response time). "Timeout" is shown if the agent cannot be contacted.
Find	Opens the <b>Find agent</b> dialog.

#### **MIB** objects

In this view you can define and edit MIB objects.

MP agents MIB objects						
Name	Object I	D	Т	ype	Access	New Edit
						Impo Expo
ked vanables lame	Offset	Name	Object	t		New
			,			Edit
						Dele
						Delete
						>

[sc_snmp_network_manager_mib, 1, en_US]

Figure 7-52 SICAM Network Manager Dialog, MIB Objects View

Element	Explanation
New	Opens the Create new MIB object dialog.
Edit	Opens the Edit MIB Object dialog for editing the MIB object selected in the list.
Delete	Deletes the MIB object selected in the list.
	The agent can only be deleted if no tag is linked any more.
Import	Opens the file manager for importing the exported objects.
Export	Opens a dialog where you can export objects.

#### Linked variables

In this window section you can link variables. This is possible in both the SNMP agents and the MIB objects view.

7.11 SNMP – SICAM Network Manager (NWM)

IMP agents I mb objects					
Name	Object I	D	Туре	Access	New
iso.3.6.1.2.1.1.3	{1.3.6.1	.2.1.1.3.0}	TimeTicks	Read-Only	Edit
					Delete
					Import
					Export
inked variables					
Name	Offset	Name	Object		New
MyAgent_iso,3,6,1,2,1,1,3	2	MyAgent	iso.3.6.1.2.1.1	.3	Edit
					Delete
					Delete all

[sc_snmp_mib_linked_vars, 1, en_US] Figure 7-53 Linked variables

Element	Explanation
New	Opens the <b>Create new variable</b> dialog.
	If you open this dialog from the <b>SNMP agents</b> view, you can only select objects from the agent selected.
	If you open this dialog from the <b>MIB objects</b> view, you can define from which agent the selected object is to be linked (the same object can exist in several agents).
Edit	Opens a dialog for editing the variable selected from the list. The dialog which opens depends on the variable type.
Delete	Deletes the variable selected from the list.
Delete all	Deletes all variables.

#### Create New Variable – Dialog

With this dialog you create new variables and select the variable type.

Create new variable	×
Variable type	
OBinary	
◯ 32-bit signed	
◯ 32-bit unsigned	
• Text tag 8-bit character set	
◯ SNMP counter	
◯ SNMP table	
◯ SNMP trap	
O ICMP echo	
ОК	Cancel

[sc_example_var_new_type, 1, en_US]

|--|

Variable Type	Explanation
Binary	Value range: 0 or 1
	Supports MIB object types Integer, Timeticks, Gauge, and Counter
32 bit, signed	Value range: -2 147 483 .48 to 2 147 483 647
	Supports MIB object types Integer, Timeticks, Gauge, and Counter
32 bit, unsigned	Value range: 0 to 4 294 967 295
	Supports MIB object types Integer, Timeticks, Gauge, and Counter
Text tag 8-bit char- acter set	Supports MIB object types OctetString, Integer, Timeticks, Gauge, and Counter
SNMP Counter	Value range: 0 to 4 294 967 295
	Provides the change of a MIB variable of MIB object type Integer, Timeticks, or Gauge.
	The counter computes the average deviation of 2 values at intervals of its cycle time
	and sends it to the runtime.
SNMP Table	Not supported in SICAM V9.06
SNMP Trap	Supports MIB object type Trap, provides 0->1->0 edges when the Trap arises.
	Traps are spontaneous events which only contain information when they arise. Thus, an incoming variable of type Trap provides 2 signal transitions that are treated like 1 binary variable: 0 -> 1, then immediately 1 -> 0, i.e. a "fleeting indication". To extract the actually essential information from the Trap (what status really occurred?), the variables coming along with the Trap should be created. For these variables to be decoded, the Trap variable has to be defined as described above, even if it is not displayed.
	Not supported in SICAM V9.06
ICMP Echo	Via the ICMP Echo components can be monitored that do not have an SNMP agent. In this case, the monitoring is realized via a cyclic ping. The cycle time is derived from the agent cycle. This variable type provides a result of 0 (echo/ping successful) or 1 (ping not successful = error).



#### NOTE

When a variable is created, only those variable types are provided which are supported by the MIB objects (e.g., for the MIB object "OctetString" only the variable type "Text tag 8-bit character set" can be selected).

#### **Find Agents Dialog**

Open this dialog to find an agent.

Find agents		-	
Name AGT001	IP address 172.17.16.104	Description	Find
AGT002	192.168.0.120		8 <u></u>
AGT003	172.17.17.3 172.17.17.4	Siemens, SIM4 Siemens, SIM4	☑ Host name ☑ as list
<		>	Close

[sc_snmp_find_agents, 1, en_US]

Figure 7-55 Find Agents Dialog

Element	Explanation
Find	Starts the search for available agents.
	The query can take some time depending on the number of agents. Whether agents can be contacted via routers depends on the multicast configuration of the routers.
	The bar under the button indicates the progress of the search.
Host name	If this checkbox is activated, the host name of the IP address found is also searched via the inverse Domain Name Service. If this checkbox is deactivated or no name server entry exists, the agent is automatically assigned a name in the following format: "AGTnnn".
	NOTE: Finding the host name can take several minutes depending on the system configuration.
as list	If this checkbox is activated, the agents found are shown as a list; otherwise, they are shown as icons.

## Edit Agent Dialog

Open this dialog to edit an agent.

Ament							
		IF address	IP address				
AG1004		172.17.17.4	1/2.1/.1/.4				
Read community		Write community	Write community				
C l'	T						
Sampling cycle	I ime-out	Hetries					
05			Agent active				
Agent description	(optional)						
Siemens, SIMATI	CINET, SCALANCE ×	(R526-8C 2PS L3, 6GK5	526-8GR00-				
ComEault:	TagManagement		Teal orging				
OprBeadu:	] TagManagement	AlarmLogging	TagLogging				
SNMP version: (	⊖ SNMP∨1	NMPv2c O SNMPv3	}				
SNMPv3 paramet	er						
SNMP engine ID (	as octet string)						
				Readout			
lleer name		Context name					
User name		Context name					
Username Secuitylevel:	laAuthNoPriv 🗠	Context name					
Username Secuitylevel:	JaAuthNoPriv →	Context name					
User name Secuity level:	laAuthNoPriv ∽	Context name					
Username Secuitylevel: M Authentication Algorithm	laAuthNoPriv → 1D5 →	Context name					
Username Secuitylevel: Authentication Algorithm Password	laAuthNoPriv ∨ 1D5 ∨	Context name		Visibility			
User name Secuity level: Authentication Algorithm Password Privacy (Encrupti	laAuthNoPriv ∨ 1D5 ∨ an)	Context name		Visibility			
User name Secuity level: Authentication Algorithm Password Privacy (Encrypti	laAuthNoPriv 1D5 ~ on) )ES ~	Context name		Visibility			
User name Secuity level: M Authentication Algorithm Password Privacy (Encrypti Algorithm:	laAuthNoPriv 1D5 on) )ES v	Context name		Visibility			
User name Secuity level: Authentication Algorithm Password Privacy (Encrypti Algorithm: Password:	laAuthNoPriv 1D5 ∼ on) )ES ∽	Context name		Visibility Visibility			
User name Secuity level: Authentication Algorithm Password Privacy (Encrypti Algorithm: Password:	NaAuthNoPriv 1D5 on) )ES	Context name		Visibility Visibility			
User name Secuity level: Authentication Algorithm Password Privacy (Encrypti Algorithm: Password:	NaAuthNoPriv 1D5 on) DES	Context name		Visibility Visibility			

[sc_snmp_edit_agent, 1, en_US] Figure 7-56 Edit Agent Dialog



# NOTE

Communication with an **IP address** ending with **.255** is not possible because it is a broadcast address. In this case, the Runtime uses the previously configured IP address of the agent.



# NOTE

For displaying the current status of a device with **ComFault** and **OprReady**, you have to configure at least 1 SNMP variable of this device.

Element	Explanation
Agent	Enter the name of the agent.
IP address	Enter the IP address of the agent.
Read community	Read access password, default: "public"
Write community	Write access password, default: "public"
Sampling cycle	You can either apply the default value (0s) or enter a different cycle value (comple- mented by s, m, h for seconds, minutes, hours) for querying the agent (e.g. $10s = 10$ seconds or $1m = 1$ minute). The recommended minimum time is $10s$ . Use the default value if possible.
Time-out	Time during which the system tries to contact the agent. If the connection could not be set up within this period, the attempt is aborted.
Retries	Number of retries to set up a connection with the agent.
Agent active	Activates or deactivates the agent.
Agent description (optional)	Enter a meaningful description of the agent if required.
ComFault, OprReady	Select here where you want the <b>ComFault</b> and <b>OprReady</b> information to be issued.
SNMP version	Select the encryption: SNMPv1, SNMPv2 or SNMPv3
SNMPv3 parameter	If you select the most secure SNMP version (v3), you can define the corresponding parameters here, such as <b>User name</b> and <b>Context name</b> for accessing the agent as well as <b>Security Level</b> , <b>Authentication</b> and <b>Privacy (Encryption)</b> .
Ping	Sends a ping to the agent and shows the result (status, response time). "Timeout" is shown if the agent cannot be contacted.

# 7.11.3 SNMPv3

#### Security

Since the SNMP versions 1 and 2 only provide reduced security mechanisms, the **SICAM Network Manager** also supports **SNMPv3**. This version provides significantly improved security. For this reason, Siemens always recommends that you use SNMPv3.

Set all the relevant parameters directly in the Edit agent dialog.

#### SNMPv3 parameter

Edit agent		×
Agent AGT004 Read community	IP address 172.17.17.4 Write community	
Sampling cycle Time-out Os 1000 Agent description (optional) Siemens, SIMATIC NET, SCALANCE XR52	Retries 5 Agent active 26-8C 2PS L3, 6GK5 526-8GR00-	
ComFault: TagManagement OprReady: TagManagement	AlarmLogging TagLogging	
SNMP version: O SNMPv1 O SNMP SNMPv3 parameter SNMP engine ID (as octet string)	VV2C () SNMPV3	
User name	Context name	Readout
Secuity level: NoAuthNoPriv V		
Algorithm MD5 Variable MD5 Vari		Visibility
Privacy (Encryption) Algorithm: DES V		Maibiltu
Password:		Cancel

[sc_snmp_edit_agent, 1, en_US] Figure 7-57 Edit agent dialog

Element	Explanation
SNMP Engine ID (as Octet string)	The <b>SNMP Engine ID</b> serves for the unique identification of the entity. Under SNMPv3, an entity is an SNMP instance which can serve as a manager, an agent, or as a combination of both. Click <b>Readout</b> in order to query this ID directly from the agent.
Readout	Queries the engine ID directly from the agent and enters it automatically in the <b>SNMP Engine ID (as Octet string)</b> field.
User name	The <b>User name</b> replaces the community strings of the versions v1 and v2c and is an integral part of the User-based Security Model (USM).
Context name	A context can be used in order to combine the management objects of an entity into logical groups. Several contexts per SNMP entity are possible and these contexts can also contain identical objects. The <b>Context name</b> serves for unique identification.
Security level	Shows the security level used:
	<ul> <li>NoAuthNoPriv         No authentication and no privacy (encryption). Corresponds to SNMPv1/ SNMPv2c security; the user name is used as a community string.     </li> </ul>
	AuthNoPriv
	Authentication is used
	• AuthPriv
	Both authentication and privacy are used
Authentication	
Algorithm	Authentication method (MD5, SH1)
	Used in the AuthNoPriv and AuthPriv security levels.
Password	Authentication password
Visibility	Provides the Show password and Hide password options
Privacy (Encryption)	
Algorithm	Encryption type
	Used with the <b>AuthPriv</b> security level.
Password	Encryption password
Visibility	Provides the Show password and Hide password options

# 7.11.4 Extending the MIB Container

You can complement the MIB file collection by additional MIB files.

♦ Copy the folder with your new MIBs into the **Default_MIB** folder (available under any path on your drive, see *Management Information Base (MIB)*, *Page 345*).

📙   🛃 🖛   Default_MIB					- 🗆 ×
File Home Share View					~ 🤇
← → × ↑ 📑 > This PC > DATEN (D:) > Default_MIB >			ٽ ~	Search Default_	MIB 🔎
👌 Music	^ Name	^	Date modified	Туре	Size
E Pictures	_structur	e	11/20/2018 10:52	File folder	
📕 Videos	avocent		11/20/2018 10:52	File folder	
🏪 Local Disk (C:)	broadco	m	11/20/2018 10:52	File folder	
DATEN (D:)	cisco		11/20/2018 10:52	File folder	
Default_MIB	dell		11/20/2018 10:52	File folder	
structure	dr_neuha	aus-gsmenterprise	11/20/2018 10:52	File folder	
avocant	equinox		11/20/2018 10:52	File folder	
bradam	foundry		11/20/2018 10:52	File folder	
broadcom	fujitsu		11/20/2018 10:52	File folder	
cisco	hirschma	ann-beldensolutions	11/20/2018 10:52	File folder	
Default_MIB	intel		11/20/2018 10:52	File folder	
dell	meinber	g	11/20/2018 10:52	File folder	
dr_neuhaus-gsmenterprise	panda		11/20/2018 10:52	File folder	
equinox	ruggedc	om	11/20/2018 10:52	File folder	
foundry	siemens/	AD	11/23/2018 3:46 PM	Filefolder	
fuiitsu	siprotec		11/20/2018 10:52	Filefolder	
hirschmann-heldensolutions	sni		11/20/2018 10:52	File folder	
intel	MibSicor	mgmi nSCC met	0/21/2010 10:32	MCE File	12 VP
		nace.mei	0/31/2010 4:21 PIVI	MCF File	12 KD
meinberg					
panda					
siemensAD 19 items 1 item selected	~				

[sc_snmp_add_mib1, 1, en_US]

The folder includes an .index file and at least one MIB file.

Default_MIB → sieme	nsAD
^	Name
	index snScalanceX300X400.mib

[sc_snmp_add_mib1b, 1, en_US]

- Click New... in the MIB objects view of the SICAM Network Manager.
- The Create new MIB object dialog opens.
- ♦ Click Edit.
- The MibSicamSCC.mcf container file is opened in the MIB File List Editor.
- Under [Directories] of the file, enter the name of the folder you have added previously and then click OK to confirm.

7.11 SNMP – SICAM Network Manager (NWM)

MIB file list editor	×
; All the paths are relative to this file	•
New RFC upper bounds: 2147483647 (not 4294967295)	
[Directories] ; Verzeichnisse die nach Mibs durchsucht werden (gefundene Mibs können bei Bed ;	
; Directories which will be searched for Mibs (found Mibs can be loaded on demand)	
_structure avocent broadcom	
cisco dell	
dr_neuhaus-gsmenterprise equinox foundry	
fujitsu hirschmann-beldensolutions intel	
meinberg panda	
ruggedcom siprotec	
sni wiredformgmt siemensAD	
[Modules]	
OK Cancel	

[sc_snmp_add_mib2, 1, en_US]

#### ♦ In the **Loaded** column, double-click **no** in order to load the MIB file.

Create new MIB object					×
	MIB colle	ction			
	MIB colle Loaded yes yes yes yes yes yes no	Module SipGoose SipOptical SipTIDEC5MIB SipTID4 FSC-AC-MIB FSC-HPI-MIB DELL_ASF-MIB SN-SCALANCEX300X400	File //siprotec/SipDiose.txt //siprotec/SipDitical.txt //siprotec/SipT104.txt //siprotec/SipT104.txt //sin/FSCAC-MIBV1.txt //sin/FHI-MIBV1.txt //simmersAD/snScalanceX300X400.mib	· ·	File Edit
	Addition	nal information			Add
Search	riap o	nead agent			Close

[sc_snmp_add_mib3, 1, en_US]

9-siemens&D (4196) ⊖-adProductNibs (1) ⊕-simaticNet (1)	Loaded yes yes	Module SipGoose	File	^	File.
⊡-adProductMibs (1) ⊕- siməticNet (1)	yes yes	SipGoose	1.1.1.101.0		
⊛-simaticNet [1]	yes	- pareere	/sintotec/Sintsonse.txt		E da
	,	SinOntical	/sintotec/SinOntical.txt		EU
	ves	SIPBOTEC5-MIB	/siprotec/Siprotec5_V02_00.txt		
	ves	SinT104	/sinrotec/SinT104 txt		
	ves	FSC-AC-MIB	/sni/FSC-AC-MIBV1.txt		
	ves	FSC-HPI-MIB	./sni/HPI-MIBV1.txt		
	ves	DELL ASF-MIB	./wiredformamt/DcAsfSrv.txt		
	ves	SN-SCALANCEX300-X400	/siemensAD/snScalanceX300X400 mib		
	Syntax OTHER				
	Additio	nal information			

The entry now reads **yes** and the MIB file is available in the MIB collection.

[sc_snmp_add_mib4, 1, en_US]

# 7.11.5 Separate Network Card for SNMP

If your computer is equipped with several network cards, you can define a specific IP address for SNMP.

- ♦ In the WinCC Explorer, open the Tag Management.
- ♦ Right-click **SNMP** and select **Connection parameters** from the context menu.

Tag Management ~ □···· Tag Management ~ 🗄 🍄 Internal tags . SICAM PAS PROTOCOL SUITE PAS Data Server 🖮 📙 System Info 🖮 👖 System Info SystemInfo 🖮 📙 SICAM SNMP Suite SNMP Data Server 🗄 - 📂 SN New Group 🗄 🌆 Structure tags 🗄 🕀 Audit_Den 🗈 Copy 🗄 🕂 PAS_Com P. Paste Tag Manageme Delete Rename Alarm logging Export .... Tag Logging 6 **Connection Parameters** 

[sc_snmp_add_ip1, 1, en_US]

The Select IP addresses dialog opens.

#### ♦ Click New.

The default IP address (**<auto>**) of your computer is displayed. Via **Selected entry** you can select another IP address, if existing.

Select IP addresses		×
For computers with several network (	cards, the IP address to be used ca	an be set here
Computername	IP address	New
SCCCL49	<auto></auto>	Delete
		OK
selected entry:		UK
SCCCL49 172.17.16	.236 V Apply	Cancel

[sc_snmp_add_ip2, 1, en_US]

# 7.11.6 Configuring SNMP (Example)

#### 7.11.6.1 Defining Agents

♦ In the WinCC Explorer, open the SICAM Network Manager.



[sc_example_open_nwm, 1, en_US]

Click Find... in the SNMP agents view in order to open the Find agents dialog.
 Click Find in the dialog.

All available agents are displayed.

7.11 SNMP – SICAM Network Manager (NWM)

lame	IP address	Active	Cycle	Time-ou	t Retries	Community	WR-	Commu	SNMP-Version	Description	New
											Edit
											De/Activate
		Find agents					-		×		Delete
						<b>D</b>		Ei			Clone
		Name			IP address	Descri	otion	FI			Import
		AGT002			172.17.16.10	4					Export
		AGT003		172.17.17.4		Siemens, S	ns, SIM/	s, SIMA	tname		Pina
		AGT004			172.17.17.3	Siemer	ns, SIM/	⊡ as li	st		
											Find
										>	1110
ked variables											
lame											New
											Edit
							_	CL			Delete
							/		DSE		Delete all

[sc_example_find_agent, 1, en_US]

♦ Double-click the desired agent (here: AGT004).

The Edit agent dialog opens (see Edit Agent Dialog, Page 350).

- ♦ If desired, enter a different name in the Agent field.
- ♦ For **Read community** and **Write community**, enter the "public" default entry.
- Select where you want the ComFault and OprReady information to be issued, e.g. in the Tag Management.
- ♦ Change further parameter settings if required.
| lit agent                                                                                                                                            |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |                                 |                |                       |
|------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------|----------------|-----------------------|
| in ugent                                                                                                                                             |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |                                 |                |                       |
| Agent                                                                                                                                                |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 | IP address                      |                |                       |
| MyAgent01                                                                                                                                            |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 | 172.17.17.4                     |                |                       |
| Read commun                                                                                                                                          | ity                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             | Write community                 |                |                       |
| public                                                                                                                                               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 | public                          |                |                       |
| Sampling cycle                                                                                                                                       | Time-out                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | Retries                         |                | 4                     |
| Os                                                                                                                                                   | 1000                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            | 5                               | 🗹 Agent active |                       |
| Agent descript                                                                                                                                       | ion (optional)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |                                 |                |                       |
| Siemens, SIM/                                                                                                                                        | ATIC NET, SCALANCE >                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            | KR526-8C 2PS L3, 6GK5           | 526-8GR00-     |                       |
| ComFault                                                                                                                                             | 🖂 TagManagement                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 | AlarmLogging                    | 🗌 TagLogging   |                       |
| OprReady:                                                                                                                                            | ✓ TagManagement                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 | AlarmLogging                    | TagLogging     |                       |
| SNMP version<br>SNMPv3 para<br>SNMP engine                                                                                                           | : ○ SNMP∨1 ● Sf<br>meter<br>ID (as octet string)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | NMPv2c O SNMPv3                 |                |                       |
| SNMP version<br>SNMPv3 para<br>SNMP engine                                                                                                           | : ○ SNMP∨1 ● Sf<br>meter<br>ID (as octet string)                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | NMPv2c O SNMPv3                 |                | Readout               |
| SNMP version<br>SNMPv3 para<br>SNMP engine<br>User name                                                                                              | : ○ SNMP∨1                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      | NMPv2c O SNMPv3<br>Context name |                | Readout               |
| SNMP version<br>SNMPv3 para<br>SNMP engine<br>User name<br>Secuity level:                                                                            | : O SNMPv1                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      | NMPv2c O SNMPv3                 |                | Readout               |
| SNMP version<br>SNMPv3 para<br>SNMP engine<br>User name<br>Secuity level:<br>Authentication                                                          | : ○ SNMPv1                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      | NMPv2c O SNMPv3                 |                | Readout               |
| SNMP version<br>SNMPv3 para<br>SNMP engine<br>User name<br>Secuity level:<br>Authentication<br>Algorithm                                             | <ul> <li>∴ ○ SNMPv1</li></ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   | NMPv2c O SNMPv3                 |                | Readout               |
| SNMP version<br>SNMPv3 para<br>SNMP engine<br>User name<br>Secuity level:<br>Authentication<br>Algorithm<br>Password                                 | x ○ SNMPv1 ④ St<br>meter<br>ID (as octet string)<br>NoAuthNoPriv<br>MD5                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         | NMPv2c O SNMPv3                 |                | Readout<br>Visibility |
| SNMP version<br>SNMPv3 para<br>SNMP engine<br>User name<br>Secuity level:<br>Authentication<br>Algorithm<br>Password                                 | <ul> <li>SNMPv1 Standard</li> <li>Standard</li> <li>SNMPv1 Standard</li> <li>Standard</li> <li>Standard</li></ul> | NMPv2c O SNMPv3                 |                | Readout<br>Visibility |
| SNMP version<br>SNMPv3 para<br>SNMP engine<br>User name<br>Secuity level:<br>Authentication<br>Algorithm<br>Password                                 | <ul> <li>SNMPv1 State</li> <li>SNMPv1 State</li> <li>State</li> <li>State</li></ul>                                                    | NMPv2c O SNMPv3                 |                | Readout<br>Visibility |
| SNMP version<br>SNMPv3 para<br>SNMP engine<br>User name<br>Secuity level:<br>Authentication<br>Algorithm<br>Password<br>Privacy (Encr.<br>Algorithm: | <ul> <li>SNMPv1 Standard</li> <li>SNMPv1 Standard</li> <li>Standard</li> <li>Standard</li></ul> | NMPv2c O SNMPv3                 |                | Visibility            |

[sc_example_edit_agent, 1, en_US]

- ♦ Click OK to close the Edit agent dialog.
- ♦ Click Close to close the Find agents dialog.

The agent is now shown in the SICAM Network Manager, SNMP agents view.

7.11 SNMP – SICAM Network Manager (NWM)

lame	IP address	Active	Cycle	Time-out	Retries	Community	WR-Commu	SNMP-Version	Description	New
/lyAgent01	172.17.17.4	yes	0s	1000 ms	5	public	public	2	Siemens, SI	Edit
										De/Activate
										Delete
										Clone
										Import
										Export
										Ping
ked variables									>	Find
ame		Offset	Name				Object			New
										Edit
										Delete
										Delete all

[sc_example_nwm_with_agent, 1, en_US]

#### 7.11.6.2 Configuring MIB Objects

- ♦ In the WinCC Explorer, open the SICAM Network Manager.
- ♦ Open the **MIB objects** view and click **New...**.

The Create new MIB object dialog opens.

3 SICAM Network Manager × SNMP agents MIB objects New Name Object ID Туре Access SN Create new MIB object  $\times$ MIB collection 🖭- ccitt (0) File Loaded Module File ^ 🛨 iso (1) partial <all> <all> Edit - joint-iso-ccitt (2) Object .ccitt Object ID Link Na {0} MIB Type Object-type Syntax OTHER < Additional information Trap objects... Read agent... Search Close

[sc_example_mib_objects, 1, en_US]

- Click File, navigate to the MIB file folder and select the MIB container file MibSicamSCC.mcf. This file contains a collection of all the MIB files included.
- ♦ Click Open.

All available MIB files are read in and all MIB objects are shown in the Create new MIB object dialog.



#### NOTE

If you have several MIB files with different versions, activate only 1 of these MIB files. Select the desired objects from this file. Afterwards, you can open the dialog once again and load the other MIB file.

Click Read agents....

The Read all MIB variables dialog opens.

♦ Select your desired agent from the drop-down list box and then click Read agents.

Under **Objects** you can observe how the objects are read in.

5ject ID 3.6.1.2.1.1.1.0 3.6.1.2.1.1.2.0 3.6.1.2.1.1.3.0	Name SNMPv2-MIB::sysDescr	Туре	Value
3.6.1.2.1.1.1.0 3.6.1.2.1.1.2.0 3.6.1.2.1.1.3.0	SNMPv2-MIB::sysDescr		
.3.6.1.2.1.1.2.0 3.6.1.2.1.1.3.0		OctetString	Siemens, SIMATIC NET, SCALANCE XR526-8C 2PS L3,
3.6.1.2.1.1.3.0	SNMPv2-MIB::sysObjectID	ObjectIdentifier	.1.3.6.1.4.1.4329.6.1.2.1.5
	SNMPv2-MIB::sysUpTime	TimeTicks	362:22:50:49.98
.3.6.1.2.1.1.4.0	SNMPv2-MIB::sysContact	OctetString	Waltur Husling
.3.6.1.2.1.1.5.0	SNMPv2-MIB::sysName	OctetString	NB2NBGPD09
.3.6.1.2.1.1.6.0	SNMPv2-MIB::sysLocation	OctetString	ESX Server Schiesskeller
.3.6.1.2.1.1.7.0	SNMPv2-MIB::sysServices	Integer	72
.3.6.1.2.1.1.8.0	SNMPv2-MIB::sysORLastChange	TimeTicks	0:0:00:28.98
.3.6.1.2.1.1.9.1.2.1	SNMPv2-MIB::sysORID[1]	ObjectIdentifier	.1.3.6.1.4.1.4329.6.3.2
.3.6.1.2.1.1.9.1.2.2	SNMPv2-MIB::sysORID[2]	ObjectIdentifier	.1.3.6.1.4.1.4329.6.1.2.100.2
.3.6.1.2.1.1.9.1.2.3	SNMPv2-MIB::sysORID[3]	ObjectIdentifier	.1.3.6.1.2.1.2
.3.6.1.2.1.1.9.1.2.4	SNMPv2-MIB::sysORID[4]	ObjectIdentifier	.1.3.6.1.2.1.10.7.2
36.1.2.1.1.9.1.2.5	SNMPv2-MIB::sysORID[5]	ObjectIdentifier	.1.3.6.1.2.1.26
.3.6.1.2.1.1.9.1.2.6	SNMPv2-MIB::sysORID[6]	ObjectIdentifier	.1.0.8802.1.1.1
.3.6.1.2.1.1.9.1.2.7	SNMPv2-MIB::sysORID[7]	ObjectIdentifier	.1.2.840.10006.300.43
.3.6.1.2.1.1.9.1.2.8	SNMPv2-MIB::sysORID[8]	ObjectIdentifier	.1.3.6.1.2.1.17.7
.3.6.1.2.1.1.9.1.2.9	SNMPv2-MIB::sysORID[9]	ObjectIdentifier	.1.3.6.1.2.1.17.6
		and an or	10010117
		Search string	

[sc_example_mib_read_agent, 1, en_US]

♦ Select the desired object and click Add....

#### The Edit MIB Object dialog opens.

Agent	MyAgent01	Edit MIB Object				×	Objects:	so far: 8610
Object ID		Object ID						
.1.3.6.1.2.1	.1.1.0	{1.3.6.1.2.1.1.3	3.0}				ET, SCALANCE XR5	26-8C 2PS L3,
.1.3.6.1.2.1	.1.2.0	Object name	Assign name autom	atically			.2.1.5	
.1.3.6.1.2.1	.1.3.0	Object name	- Abaign name datom	addaily				
.1.3.6.1.2.1	.1.4.0	SNMPv2-MIB::sy	sUpTime					
.1.3.6.1.2.1	1.1.5.0	MIB information						
.1.3.6.1.2.1	1.1.6.0	Object					.eller	
.1.3.6.1.2.1	.1.7.0	.iso.org.dod.inter	net.mamt.mib-2.svstem	.svsUpTime		<u>^</u>		
.1.3.6.1.2.1	.1.8.0	Object ID						
.1.3.6.1.2.1	1.1.9.1.2.1	{1.3.6.1.2.1.1.3]	}				.2	
.1.3.6.1.2.1	1.1.9.1.2.2	SNMPy2-MIB_REF	C1213-MIR_REC1158-M	TB			.2.100.2	
.1.3.6.1.2.1	1.1.9.1.2.3	Type	C1215 MID, N C1150 M	10				
.1.3.6.1.2.1	1.1.9.1.2.4	OBJECT-TYPE						
.1.3.6.1.2.1	1.1.9.1.2.5	Syntax						
.1.3.6.1.2.1	1.1.9.1.2.6	Access						
.1.3.6.1.2.1	1.1.9.1.2.7	Read-Only					13	
.1.3.6.1.2.1	1.1.9.1.2.8	State						
.1.3.6.1.2.1	.1.9.1.2.9	Comment						
LID SCORE	101010	The time (in hund	redths of a second) sinc	e the network management	portion of the system was last re-			
MIB Informat	lion	initialized.				~		
Object .iso.org.dod Object ID	internet.mgmt.mib-2.system.sys	Index list			Read agent			
{1.3.6.1.2.1	.1.3}	Name	Type	Index	MyAgent01	~		
MIB					Deed			
	ID, NECT213-MID, NECT130-MI				Reau			
OBJECT TY	'PE							
Syntax								
Read-Only		<		>				
State								
Commont				Apply index	Add	Close		
comment								

[sc_example_mib_edit_object, 1, en_US]

- ♦ You can change the **Object name** here, if required. **Assign name automatically** is activated by default.
- ♦ Click Add and then click OK to confirm that you really want to add the object.

- ♦ Click Close to close the Edit MIB Object dialog.
- ♦ Repeat these steps to add additional MIB objects, if required.
- ♦ Click Close to close the Read all MIB variables dialog.
- ♦ Click Close to close the Create new MIB Object dialog.

The MIB object is now shown in the SICAM Network Manager, MIB objects view.

Name	Object I	D		Туре	Access	New
SNMPv2-MIB::sysUpTime	{1.3.6.1	.2.1.1.3.0}		TimeTicks	Read-Only	Edit
						Delete
						Import
						Export
						_
ked variables						
	Offset	Name	Obje	ect		New
lame						
lame						Edit
lame						Edit Delete
lame						Edit Delete Delete all
lame						Edit Delete Delete all
lame						Edit Delete Delete all
lame						Edit Delete Delete all

[sc_example_nwm_with_mib_object, 1, en_US]

#### 7.11.6.3 Creating Linked Variables

- ♦ In the WinCC Explorer, open the SICAM Network Manager.
- ♦ In the MIB objects view under Linked variables, click New....

The Create new variable dialog opens.

7.11 SNMP – SICAM Network Manager (NWM)

Create new variable	<
Variable type	
OBinary	
◯ 32-bit signed	
◯ 32-bit unsigned	
Text tag 8-bit character set	
◯ SNMP counter	
◯ SNMP table	
◯ SNMP trap	
O ICMP echo	
OK Cancel	

[sc_example_var_new_type, 1, en_US]

♦ For this example, select **Text 8-bit character set** and click **OK**.

The dialog for configuring the variable (here: Text variable 8-bit character set) opens.

Configure text tag 8-bit character set	×
Addressing	
Object	
SNMPv2-MIB::sysUpTime	~
Type TimeTicks Access Read-Only	
Agent	
	$\sim$
Offset	
General parameters	
Name Assign name automatically	
_SNMPv2-MIB;;sysUpTime	
TagManagement AlarmLogging TagLogging	
Write access use enum texts	
Add Clo	se

[sc_example_var_config, 1, en_US]

- Select the desired **Agent** from the drop-down list box.
- ♦ Click Add and then click OK to confirm that you really want to add the variable.

### ♦ Click Close.

The variable is now shown under Linked variables.

MP agents MIB objects					
Name	Object I	D	Туре	Access	New
SNMPv2-MIB::sysUpTime	{1.3.6.1	.2.1.1.3.0}	TimeTicks	s Read-Only	Edit
					Delete
					Import
					Export
nked variables					
Name	Offset	Name	Object		New
MyAgent01_SNMPv2-MIB;;sysUpTir	me 2	MyAgent01	SNMPv2-MIB	::sysUpTime	Edit
MyAgent01_SNMPv2-MIB;;sysUpTii	me 2	MyAgent01	SNMPv2-MIB	∷sysUpTime	Edit Delete
MyAgent01_SNMPv2-MIB;;sysUpTi	me 2	MyAgent01	SNMPv2-MIB	∷sysUpTime	Edit Delete Delete all
MyAgent01_SNMPv2-MIB;;sysUpTi	me 2	MyAgent01	SNMPv2-MIB	t∷sysUp Time	Edit Delete Delete all
MyAgent01_SNMPv2-MIB;;sysUpTi	me 2	MyAgent01	SNMPv2-MIB	k:sysUp Time	Edit Delete Delete all
MyAgent01_SNMPv2-MIB:;sysUpTi	me 2	MyAgent01	SNMPv2-MIB	k:sysUp Time	Edit Delete Delete all
MyAgent01_SNMPv2-MIB:;sysUpTi	me 2	MyAgent01	SNMPv2-MIB	t:sysUp Time	Edit Delete Delete all
MyAgent01_SNMPv2-MIB:;sysUpTi	me 2	MyAgent01	SNMPv2-MIB	::sysUp Time	Edit Delete Delete all

[sc_example_var_linked, 1, en_US]

- ♦ Click **Apply** to apply the parameters for the linked variable.
- ♦ Repeat these steps to add additional linked variables, if required.
- ♦ Click **OK** to close the **SICAM Network Manager**.

The parameters are processed in the background and the Tag Management is updated. The "NWCCM shutting down" message in the **Report** in the **SNMP-Config** view informs you that the update has been completed.

7.11 SNMP – SICAM Network Manager (NWM)

Keport		- 🗆	×
Export 🔮 Print preview 😽 Delete 🔖 Delete all			
verview SNMP-Config SICAM PAS Wizard SICAM SCC Importer SICAM SCC Runtime Data Server SICAM SCC	Runtime Data Se	erver-DAF_Plugi	n 4
Messages	Date	Time	1
D End: Updating alarm logging	11/21/2018	4:12:21 PM	
Begin: Updating tag logging	11/21/2018	4:12:21 PM	
Q	11/21/2018	4:12:21 PM	
creating SICAM timer	11/21/2018	4:12:21 PM	
End: Updating tag logging	11/21/2018	4:12:21 PM	
re-creating var file	11/21/2018	4:12:21 PM	
writing SICAM_RTDS_DAF_PlugIn.var file	11/21/2018	4:12:21 PM	
writing SICAM_RTDS_DAF_PlugIn.var file	11/21/2018	4:12:21 PM	
ip re-creating mxc file	11/21/2018	4:12:21 PM	
💭 re-creating aix file	11/21/2018	4:12:21 PM	
End: Update of SNMP station "SNMP"- 0 fault(s), 0 warming(s)	11/21/2018	4:12:21 PM	
TEA-X import successfully finished.	11/21/2018	4:12:21 PM	
Made backup of imported TEA-X file to "D:\Projekte\Demo_SCC_V903_WinCC_V74\GWData\SNMP\TEA-X\NW	. 11/21/2018	4:12:21 PM	
Closed connection to WinCC.	11/21/2018	4:12:22 PM	
TEA-X wizard closed.	11/21/2018	4:12:22 PM	
NWCCM - conversion successful	11/21/2018	4:12:22 PM	
NWCCM shutting down	11/21/2018	4:12:22 PM	

[sc_example_var_report, 1, en_US]

### 7.11.6.4 Starting the Runtime and Opening the Tag Management

- ♦ Start the Runtime in the **WinCC Explorer**.
- ♦ In the **WinCC Explorer**, open the **Tag Management**.
- ♦ Select your agent under SICAM SNMP Suite > SNMP Data Server > SNMP.

The linked objects are displayed.

III Tag Management - WinCC Configuration Studio							-		×
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp									
Tag Management «		Tags [ MyAgent01 ]		Find	<del>،</del> م	•	📦 Properties - Tag		»
	•	Name	Comment	Value	Data type 🧖	< E	Selection		^
🗄 🍄 Internal tags	1	MyAgent01_ComFault		1	Unsigned 32-bit val		Object type	Tag	
SICAM PAS PROTOCOL SUITE	2	MyAgent01_OprReady		2	Unsigned 32-bit val		Object name	MyA	gent(
PAS Data Server	3	MyAgent01_SNMPv2_MIBsysUpTime	1	362:23:09:16.16	Text tag 8-bit char	6	General		
SubstationSouth	4	X	1				Name	MyA	gent(
E System Info	5	i					Comment		
- II. System Info	6						ID Data to a c	6314	•
SystemInfo	7	1					Data type	Text	: tag
SICAM SNIMP Suite	8	4					Eermat adaptation	235	
SNIMD Date Carrier	9	1					AS Length	255	
SINNE Data Server	1	0					Address	200 COM	DARA
	1	1					AS tag name	COM	1740
MeinAgentU1	1	2					Name space		
SicamAdmin_5003	1	3				E	Assignment		
MyAgent01	1	4					Communication driver	SICA	M SN
alalal	1	5					Channel unit	SNM	P Dat
Tag Management	1	5					Connection	SNM	P
Alarm logging	1	7					Group	MyA	gent( 🗸
Kann logging	1	3							
Tag Logging	1	9							
222	2	0							
■ ₩ Ⅲ ● 索 법 凿 -	Ĩ	· → → Tags	1		>				
Ready		Eng	glish (United St	tates)			Table: 3 Tags   100 % 😑	-0	- ÷

[sc_example_var_managment, 1, en_US]

# 8 Client-Server Systems

8.1	Configuration of the Graphic Objects	370
8.2	Configuration of the Functions	371
8.3	Configuration of the SIMATIC WinCC Components	372

# 8.1 Configuration of the Graphic Objects



[client_serv01, 1, en_US]

Figure 8-1 Showing a server diagram on the client computer

Diagrams from various different servers can be viewed in individual screen sections. These so-called "picture windows" are displayed in the basic frame configured on the client computer. The diagrams configured on the servers are displayed in diagram windows. Each diagram is based on the data of an individual server. In order to be able to integrate a server diagram as a picture window in a basic frame on the client computer, the file name of the diagram must be preceded by the prefix of the server name. All server prefixes must be unique within the distributed system.

The packages of the corresponding servers must be imported into the client.

- ♦ Open the basic frame on the client into which you want to insert the server diagram as picture window.
- In the Graphics Designer, select the Picture window from the group of smart objects. Insert it into the basic frame.
- ♦ Double-click the picture window to open the **Properties** dialog.
- In the Miscellaneous group of the Properties tab, click the Picture name attribute in order to browse for the diagram.
- ♦ Double-click the Server prefix attribute to browse for the server.
- $\diamond$  Close the **Properties** dialog.

On the client, you can also create and show diagrams based on data from several different servers.

### NOTE

On the server computer, you create the server packages in the WinCC Explorer under the **Server** level. On the client computer, you import the server package in the WinCC Explorer under the **Server** level (see chapter 8.3 Configuration of the SIMATIC WinCC Components and WinCC Information System).

# 8.2 Configuration of the Functions

When importing data, the compatibility key script (SICAMPAS_CompKey.pas), the alarm list filter script and several other scripts are created in the **PAS** directory of the WinCC project directory. Scripts in this directory are executed by all computers of the project.

For efficient system operation, move the scripts **SICAMPAS_CompKey.pas** and **SicamPAS_AlarmList-Filter.pas** into the corresponding **PAS** directories of those computers in the project which are interfaced to the process.



### NOTE

During each import, the SICAMPAS_CompKey.pas script is created again by the SICAM PAS Wizard.

The WinCC project directory holds a subdirectory (<Computer Name>) for each computer in the project. This subdirectory comprises the same subdirectories as the project directory. Data located in these subdirectories is only assigned to the individual computer.

# 8.3 Configuration of the SIMATIC WinCC Components

### **Picture Cache**

The diagrams from a connected server can be shown in a picture window on a client computer. For a speedy build-up of the diagram on the client computer, the corresponding diagrams should be copied into a Picture Cache on the client. When using a Picture Cache, the WinCC client does not need to reload all individual diagrams from the server.

Proceed as follows to set up a picture cache on the client computer:

The necessary pictures must be stored on the Client computer which shall use the picture cache.

♦ To do this, create the PDLCache directory within the <InstallationDirectory\bin> directory on this computer and copy the pictures into this folder.

This folder is stored as the standard directory in the WinCC project. If you select a different directory, you enter this directory in the Path input field. Enter the path to the directory in which the PDLCache directory is stored.

- $\diamond$  Copy the diagrams into this folder in order to show them on the client computer.
- ♦ Open the **Computer Properties** dialog on the client.
- ♦ Select the **Runtime** tab.

Computer properties				×
General Startup Parameters	Graphics Runtime	Runtime		
VBS Debug Options - Graphics: Start debugger  Display error dialog		VBS Debug Options - Start debugger Display error dialog	Global Script:	
Design settings: Use "WinCC Classic" design Disable shadow Disable background picture / Runtime options: Enable monitor keyboard Hardware accelerated graph Activate the runtime system of	/ history in picture of ics representation ( dialogs	bject Direct2D)		_
Picture cache path: Use picture cache:	Preferred	~		_
Mouse pointer:				-
Action configured:	l			۶
Editable I/O field and action configured:				•
Editable I/O field:				
Editable text list object and action configured:				8
Editable text list object:				
		ОК	Cancel Help	•

[client_serv02, 1, en_US]

Figure 8-2 Defining a picture cache

- ♦ Enter the path of the picture cache under **Path**.
- Select **Preferred** from the **Use cache** list box.

Modified diagrams are read from the server; unmodified diagrams are read from the picture cache.

If a diagram is modified in the project on the server, it has to be manually copied into the picture cache of the client.

#### Update: example of SICAM PAS data

Changes performed in SICAM PAS must be forwarded to SICAM SCC. For a client-server system, changes must be forwarded as described below.



### NOTE

The export of the first package from the server and the import into a client have to be performed manually. All further updates of the packages on the server and the client can be performed automatically. You can define when the package is to be updated and specify a trigger event.

For more detailed information, refer to the *WinCC Information System*.

- $\diamond$  Import the new PXD file created with SICAM PAS into the WinCC server.
- ♦ Create a package on the server.

To manually load a package onto the client:

- ♦ Open the client project on the client computer.
- In the WinCC Explorer, select Server data and then select Load from the context menu. The Open File dialog displays.
- Select the package to be loaded and click OK.
   By default, the server packages are saved in the directory ...\\<Server Project Name>\<Computer Name>
   \Packages\ under the name <Project Name_Computer Name>*.pck. You can also load packages saved on any other data carrier.
- ♦ Click **Open**. The data is loaded.

To manually update a package on the client:

- ♦ Open the client project on the client computer.
- In the WinCC Explorer, select Server data and then select Update from the context menu.
   The data is updated.

# 9 Redundancy

9.1	Overview	376
9.2	Redundancy with a SICAM PAS System	378
9.3	Redundancy with SICAM RTUs	382

### 9.1 Overview

For safety reasons, a SICAM PAS system and SICAM RTUs can be implemented in redundant configuration. If required, certain components can be implemented redundantly depending on the specific requirements of the individual system. This section describes how to define the configurations illustrated below.

- Redundant SICAM PAS systems and SICAM RTUs are connected to 1 SICAM SCC Human-Machine Interface (HMI).
- 1 SICAM PAS system/SICAM RTUs are connected to 2 redundant SICAM SCC HMIs.

Further redundant configurations are possible. For example, redundant SICAM PAS systems/SICAM RTUs can also be combined with a redundant SICAM SCC system.

For more detailed information on redundancy, refer to the SIMATIC WinCC documentation.



#### NOTE

Make sure you also read 7.1.3 Configuration for Improved Message Display in the Case of Redundancy.

Settings recommended for SICAM SCC in the WinCC Redundancy

ledundancy	
neral User Archive	
Server:	
V74-WIN7X32	
☑ Default Master	
Redundant partner server:	
V74-WIN7X32_1	
Local Computer Settings	
Connection to redundant partner via network adapter:	
00.00.20.0.9.64.00 Intel/D) DDO /1000 MT Nathundruschind und	
00.00.23.A8.04.00 Inite(A) PNO71000 MIT-Net2WeikVeibindung	•
Connection to redundant partner via serial interface (optional):	•
Synchronize data of last days only:     2 days	
Optional Settings	
Synchronization of Tag Logging after the partner server comes back online	
Synchronization of Alarm Logging after the partner server comes back online	
<ul> <li>Synchronization of Alarm Logging after the partner server comes back online</li> <li>Online synchronization for Alarm Logging</li> </ul>	
<ul> <li>Synchronization of Alam Logging after the partner server comes back online</li> <li>Online synchronization for Alam Logging</li> <li>Synchronization after disruption of the process link (Tag Logging + Alam Logging)</li> </ul>	
<ul> <li>Synchronization of Alarm Logging after the partner server comes back online</li> <li>Online synchronization for Alarm Logging</li> <li>Synchronization after disruption of the process link (Tag Logging + Alarm Logging)</li> <li>WinCC client switch in case of a process connection error</li> </ul>	
<ul> <li>Synchronization of Alarm Logging after the partner server comes back online</li> <li>Online synchronization for Alarm Logging</li> <li>Synchronization after disruption of the process link (Tag Logging + Alarm Logging)</li> <li>WinCC client switch in case of a process connection error</li> </ul>	
<ul> <li>Synchronization of Alarm Logging after the partner server comes back online</li> <li>Online synchronization for Alarm Logging</li> <li>Synchronization after disruption of the process link (Tag Logging + Alarm Logging)</li> <li>WinCC client switch in case of a process connection error</li> </ul>	
<ul> <li>Synchronization of Alam Logging after the partner server comes back online</li> <li>Online synchronization for Alam Logging</li> <li>Synchronization after disruption of the process link (Tag Logging + Alam Logging)</li> <li>WinCC client switch in case of a process connection error</li> <li>mables the synchronization for all specified options and user archives:</li> <li>Activate Redundancy</li> </ul>	
<ul> <li>Synchronization of Alam Logging after the partner server comes back online</li> <li>Online synchronization for Alam Logging</li> <li>Synchronization after disruption of the process link (Tag Logging + Alam Logging)</li> <li>WinCC client switch in case of a process connection error</li> <li>WinCC client switch in case of a process connection error</li> <li>Activate Redundancy</li> </ul>	

[SCC_Redundancy_settings, 1, en_US]

Figure 9-1 WinCC Redundancy Settings Recommended for SICAM SCC

# 9.2 Redundancy with a SICAM PAS System

### 9.2.1 Connection to 2 SICAM PAS Systems

A SICAM PAS system can consist of 2 redundant SICAM PAS systems running in parallel. Bay devices and substations are connected to both SICAM PAS systems, and SICAM SCC is connected to both SICAM PAS systems via the SICAM PAS PROTOCOL SUITE (SICAM PAS channel DLL). For a redundant SICAM PAS system, the connection of SICAM SCC is active parallel to both SICAM PAS systems.



### Activating redundancy



### NOTE

With SICAM PAS V8.00 or higher, the redundancy parameters are entered automatically.

Proceed as follows to activate the redundant configuration:

- In the WinCC Explorer, right-click PAS Data Server and select Properties from the context menu.
   The Channel Unit Properties dialog opens.
- Click Properties.

The Connection properties dialog opens.

Click Properties.
 The PAS Connection dialog opens.

PAS Connection >				
SICAM PAS Configuration				
Connection parameter				
Connection type	V7 Redundancy 💌			
	SICAM PAS address port			
SICAM PAS 1	192 . 168 . 048 . 101 10501			
SICAM PAS 2	192 . 168 . 048 . 102 10501			
Link parameter				
Test frame period [ms]	1000 (250 - 60000)			
	OK Abbrechen Übernet	hmen		

[pascc404, 1, en_US]

Figure 9-3 Activating redundancy

- ♦ Select the Connection type.
- $\diamond$  Enter the IP address of the second SICAM PAS system.

The IP addresses must correspond to the IP addresses configured for the SICAM SCC interfaces in SICAM PAS. The **ports** must match the ports parameterized in SICAM PAS.

The **Test frame period** must correspond to the Test frame period parameterized in SICAM PAS for SICAM SCC.

 $\Leftrightarrow \quad \mathsf{Click} \ \mathbf{OK} \ \mathsf{to} \ \mathsf{confirm} \ \mathsf{your} \ \mathsf{settings}.$ 

### 9.2.2 Redundant SICAM SCC System

A redundant system consists of SICAM SCC Servers which run in parallel. Each SICAM SCC provides a SICAM PAS PROTOCOL SUITE connection to the SICAM PAS system.

The first SICAM SCC (e.g. WinCC1) is the **Master Server**, and the second one is the **redundant Partner Server**. Both connections are active in case of fault-free operation.

The SIMATIC WinCC redundancy package for data synchronization and for the control of the server redundancy must be installed on both SICAM SCC servers.

9.2 Redundancy with a SICAM PAS System



[Kanal_dll_1, 1, en_US] Figure 9-4

System with redundant SICAM SCC

### **Configuring SICAM PAS**

In SICAM PAS, you must enter the IP addresses of the two SICAM SCC computers. Proceed as follows:

- ♦ To open SICAM PAS UI Configuration, click
   Start > Siemens Energy > SICAM > PAS > UI Configuration.
- ♦ Insert an SCC application, an interface and a control center.
- Under Interface, enter the IP address of the Full Server via which you want to communicate with SICAM SCC.

This is particularly important for Full Servers with several network cards.

♦ Under **Control center**, enter the IP addresses of the two SICAM SCC computers.

SICAM SCC Redundancy   User logon deactivated   Configuration - Large         File       Edit       Create       View       Tools       Help         Image: The second s					SIEMENS SICAM PAS UI - Configuration		
	Configuration	Mapping	Topology	Templates	Reports	Grid Codes	
Configuration	Configuration	Mapping	Topology     SICAM SCC Redundan     General parameters     Name     Description     Compatibility key     Communication parar     SICAM SCC 1     SICAM SCC 1     SICAM SCC 2     Test frame period [ms]     Topology assignment     Assigned to:	Templates           cy > Full Server > SC           42           127.0.0.2           127.0.0.3           1000	Reports CC > Interface > Cor enter C Redundancy	Grid Codes	
			Under SICAM SCC 2 you enter t	he IP address of the SICAM S	iCC server.		
			🔁 🚺 Error(s): 0 🛛 << Previo	us Next>> 4			•

[sc_first_dip, 1, en_US]

Figure 9-5 Control center, entering IP addresses

♦ The items of information to be used in SICAM SCC must be activated in the information mapping.

#### **Exporting data**

To import the configured items of information into SICAM SCC, they must be exported from SICAM PAS UI – Configuration.

♦ Right-click Control Center and select Export from the context menu.

The export function creates a PXD file in the selected directory. Afterwards, you can import this file into SICAM SCC using the SICAM PAS Wizard.

♦ Export the configuration data.

#### **Creating WinCC projects**

- ♦ Create a new WinCC project (e.g. SCC 1) on the first computer.
- ♦ Import the PXD file of the first DIP using the SICAM Import/Export Wizard.
- ♦ Close your WinCC project.

Create the redundant WinCC project via the Project Duplicator. It must be saved on a second computer.

- ♦ To start the Project Duplicator, click Start > SIMATIC > WinCC > Tools > Project Duplicator.
- ♦ Enter SCC 1 as source project.
- $\diamond$  Enter a name for the redundant WinCC project (e. g. SCC 2).
- ♦ Click the **Duplicate** button. The redundant WinCC project is created now.



### NOTE

To start the SIMATIC WinCC Runtime, the 2 WinCC servers must be started one after the other. Start the first server and then start the second. For more detailed information, refer to the SIMATIC WinCC Information System.

## 9.3 Redundancy with SICAM RTUs

The connections between SICAM SCC and the devices of SICAM RTUs can be established on the basis of the IEC 61850 or IEC 60870-5-104 protocols. This section describes the procedure to be applied if the IEC 61850 protocol is used. The same procedure is applied to the IEC 60870-5-104 protocol.

### 9.3.1 Connection to Redundant SICAM RTU Substation Controllers

SICAM RTUs can be operated redundantly in order to ensure fail safety. Via the SICAM IEC COMMUNICATION SUITE (SICAM IEC channel DLL), SICAM SCC is connected to both SICAM RTUs. In case of redundant SICAM RTUs, the SICAM SCC connection to the two SICAM RTUs is active at the same

In case of redundant SICAM RTUs, the SICAM SCC connection to the two SICAM RTUs is active at the same time.

For SICAM RTUs, redundant and non-redundant devices can be operated in parallel.



Figure 9-6 System with redundant SICAM RTUs and redundant bay devices

#### Redundancy and connection parameters

The **redundancy** and **connection parameters** (e.g. IP addresses) are defined using the **SICAM TOOLBOX II** and integrated into the SICAM SCC project by importing the SXD file.

### 9.3.2 Redundant SICAM SCC System

A redundant system can consist of 2 SICAM SCC servers running in parallel. Each SICAM SCC provides a SICAM IEC COMMUNICATION SUITE (SICAM IEC channel DLL) connection to the devices.

One SICAM SCC (e.g. WinCC1) is the **Master server** and the other SICAM SCC (e.g. WinCC2) is the **redundant partner server**. Both connections are active in case of fault-free operation. Commands are only issued by the **Master server** 

The SIMATIC WinCC redundancy package for data synchronization and for the control of server redundancy must be installed on both SICAM SCC servers.



Figure 9-7 System with redundant SICAM SCC

### **Creating WinCC projects**

- ♦ Create a new WinCC project (e.g. SCC 1) on the first computer.
- Import the SXD file using the SICAM IEC Wizard.
   The SXD file was exported from SICAM TOOLBOX II.
- ♦ Close the WinCC project.

Create the redundant WinCC project using the Project Duplicator. It must be saved on a second computer.

- ♦ To start the **Project Duplicator**, click **Start > SIMATIC > WinCC > Tools > Project Duplicator**.
- ♦ Enter SCC 1 as the source project.
- $\diamond$  Enter a name for the redundant WinCC project (e.g. SCC 2).
- ♦ Click **Duplicate**. The redundant WinCC project is created now.

#### Synchronization of SICAM acknowledgment data

SIMATIC WinCC supports the synchronization of data between redundant servers. In order to ensure that the data of the SICAM SCC components can be synchronized between the redundant servers, be aware of the following:

• For the **IX State Sync** application, the same rules apply for SICAM RTUs and SICAM PAS/PQS systems, see 14.5 IX State Sync Application.

# 10 Different SICAM PAS Versions

10.1	Overview	386
10.2	Introduction	387
10.3	Use Cases from Daily Practice	388

### 10.1 Overview

Several **SICAM PAS systems in different versions** can be connected to a SICAM SCC. Special SICAM PAS channels are available for this purpose.

## 10.2 Introduction

The SICAM PAS and SICAM SCC substation automation system communicate with each other via a channel in SIMATIC WinCC. The SICAM PAS Protocol Suite uses components of the SICAM PAS system for communication. The versions of all components involved must be identical. A SICAM PAS Protocol Suite can only establish a connection to a specific SICAM PAS version.

For SICAM PAS CC/SICAM SCC V7.0 and higher the SICAM PAS channel supports the connection to SICAM PAS V7.0 and higher. Starting from these versions, a mixed-versions operation is possible with the SICAM PAS Protocol Suite standard channel.

For the extension of existing systems or upgrades of the SICAM SCC computer, such as a new SIMATIC WinCC version, it might be necessary to connect the SICAM PAS system of an older version or several SICAM PAS systems of different versions to a SICAM SCC.

In these cases, special SICAM PAS channels are available for the connection to SICAM PAS V5.11 and SICAM PAS V6.00. In the SIMATIC WinCC Tag Management, you can load the **SICAM PAS Protocol Suite V5** or the **SICAM PAS Protocol Suite V6**. Afterwards, during the data import using the SICAM PAS Wizard, select the desired **Channel PAS Data Server V5** or **Channel PAS Data Server V6**.

The **SICAM PAS Protocol Suite** included in the scope of delivery is intended for applications from V7 or applications with consistently identical software versions. In the SICAM PAS Wizard, you use the **Channel PAS Data Server**. For this channel, in case of an upgrade of SICAM PAS or SICAM SCC, the integrated components of the basic software are automatically exchanged in order to ensure that the project can be further edited immediately after the upgrade and without any further configuration efforts.

If data was imported into a version-specific channel or if data has to be moved to such a channel, the configuration must be modified accordingly. Data which you have imported into a channel is saved in the SIMATIC WinCC database with its ID.

For WinCC V7.3 and higher, this exchange can be done in the Configuration Studio. To do so, select the communication connection and change the communication driver in the properties.

During the upgrade from **SICAM PAS V5.11** to **V6.00/V7.00/V8.00**, not all the conversion which would be necessary to support new functions can be performed automatically.

# 10.3 Use Cases from Daily Practice

This paragraph provides a list of different examples from daily practice. Depending on the change (extension/ upgrade) to be performed on the system, a channel may or may not be exchanged. You can exchange the channel using the Configuration Tool, see 14.8 Working with the SIMATIC WinCC Configuration Tool.

- Upgrade of an existing SICAM PAS/SICAM PAS CC project
  - Upgrade of SICAM PAS and SICAM PAS CC
     Initial configuration: SICAM PAS V5.11/V6.xx with SICAM PAS CC V5.11/V6.xx
     Target configuration: SICAM PAS V7.00 with SICAM SCC V8.04
     With this upgrade scenario, a channel exchange is not necessary.
  - Upgrade of SICAM PAS CC
     Initial configuration: SICAM PAS V5.11/V6.xx with SICAM PAS CC V5.11/V6.xx
     Target configuration: SICAM PAS V5.11/V6.xx with SICAM SCC V8.04
     With this upgrade scenario, the default channel must be replaced with the version-specific V5/V6 channel.
- Connection of an additional SICAM PAS station with a different version
  - Integrating a SICAM PAS V7.00/V8.00 station into an existing SICAM PAS/PAS CC V5.11 system.
     Initial configuration: SICAM PAS V5.11 with SICAM PAS CC V5.11 and a new SICAM PAS V7.00/ V8.00 station

Target configuration: SICAM PAS V5.11 and SICAM PAS V7.00/V8.00 with SICAM SCC V8.04 For SICAM PAS CC, an upgrade from V5.11 to SICAM SCC V8.04 must be performed. With SICAM PAS V7.00/V8.00, the default channel is used.

With SICAM PAS V5.11, the default channel must be replaced with the version-specific V5 channel.

Integrating a SICAM PAS V7.00/V8.00 station into an existing SICAM PAS/PAS CC V6.xx system
 Initial configuration: SICAM PAS V6.xx with SICAM PAS CC V6.xx and a new SICAM PAS V7.00/ V8.00 station

Target configuration: SICAM PAS V6.xx and SICAM PAS V7.00/V8.00 with SICAM SCC V8.04 For SICAM PAS CC, an upgrade from V6.xx to SICAM SCC V8.04 must be performed. With SICAM PAS V7.00/V8.00, the default channel is used.

With SICAM PAS V6.xx, the default channel must be replaced with the version-specific V6 channel.

 Re-integrating an existing SICAM PAS V5.11/V6.xx station into a SICAM SCC V8.04 project Initial configuration: SICAM PAS V7.00/V8.00 with SICAM SCC V8.04 and a separate SICAM PAS V5.11/V6.xx station

Target configuration: SICAM PAS V5.11/V6.xx and SICAM PAS V7.00/V8.00 with SICAM SCC V8.04 With SICAM PAS V7.00/V8.00, the default channel is used. With SICAM PAS V5.11/V6.xx, the version-specific V5/V6 channel is used instead of the default channel.

- Integrating different SICAM PAS stations
  - Initial configuration:

The original project was based on SICAM PAS V5.11 and SICAM PAS CC V5.11. In the first expansion stage, it was complemented by a SICAM PAS V6.xx station. In the second expansion stage, the project must be complemented by another station based on SICAM PAS V7.00/V8.00.

First expansion stage:
 SICAM PAS V5.11, SICAM PAS V6.xx with SICAM PAS CC V6.xx For communication with SICAM PAS V5.11and SICAM PAS V6.xx, the version-specific V5 and V6 channels are used.

- Second expansion stage, target configuration:

The existing project is complemented by a SICAM PAS V7.00/V8.00 station. For SICAM PAS CC, an upgrade from V6.xx to SICAM SCC V8.04 must be performed. The communication for the first two SICAM PAS stations remains on the version-specific V5 and V6 channels. The default channel is used for communication with the new SICAM PAS V7.00/V8.00 station.

# 11 WinCC Web Navigator

11.1	Overview	392
11.2	Prerequisites	393
11.3	WinCC Web Navigator with SICAM SCC	394

## 11.1 Overview

Using the WinCC Web Navigator, you can operate and monitor a WinCC project from anywhere in the world via the Internet.

The WinCC Web Navigator includes special Web Navigator Server components installed on the server computer, as well as Web Navigator Client components running on the Internet computer.



### NOTE

SIMATIC WinCC Web UX cannot be used with SICAM SCC with SICAM Switch, Bay Overview or Numeric Controls. Web UX does not support the ActiveX technology.

## 11.2 Prerequisites

A Web Navigator Server and a Web Navigator Client are required in order to implement the WinCC Web Navigator function. To use the WinCC Web Navigator for SICAM SCC, certain prerequisites must be met.

### Web Navigator Server

The following requirements must be met by the computer used as a Web Navigator Server:

- SICAM SCC installed
- Web Navigator Server installed
- a user with Web Navigator rights installed
- a WinCC project installed and enabled for the WinCC Web Navigator

### Web Navigator Client

The following requirement must be met by the computer used as a Web Navigator Client:

• Microsoft Internet Explorer installed

For more detailed information on the requirements with regard to the WinCC Web Navigator, refer to the documentation and the online help of the Web Navigator. The section below describes the actions to be taken especially for SICAM SCC.



### NOTE

The display on the Web Navigator Client can be hidden or restricted by your browser's security settings.

#### **Special characters**

If you use scripts in your pictures, the names of the objects addressed by this script must not include blanks or special characters. The special character "_" is supported. This means that you may use the special character in the object name, e.g. StartPicture_1.

# 11.3 WinCC Web Navigator with SICAM SCC

To use the WinCC Web Navigator for SICAM SCC, certain prerequisites must be met. These prerequisites are illustrated in the present section and must be executed in the order described.

### 11.3.1 Making SICAM SCC Plug-Ins Available

### WinCC Web Navigator Server

The SICAM SCC setup installs the SICAM SCC software modules (plug-ins) for the WinCC Web Navigator in the corresponding directory of the WinCC Web Navigator installation.

If the WinCC Web Navigator was installed after SICAM SCC, you must make the SICAM SCC software modules for the WinCC Web Navigator Client available on the WinCC Web Navigator server computer.

If the WinCC Web Navigator server has already been installed before installing SICAM SCC, the files are copied from the SICAM SCC setup into the WinCC Web Navigator server target directory.

Upon the installation of SICAM SCC, the SICAM SCC software modules for the Web Navigator are additionally copied into the SICAM SCC installation directory on the hard disk. Afterwards, you can copy them from the hard disk into your SIMATIC WinCC installation.

♦ Copy the WebNavClientSICAMSCCVxxx.EXE and the

WebNavClientSICAMSCCVxxx.XML files from the ...\SCC\WebNavigator\Server\Web\Install\Custom directly into the ...\WinCC\WebNavigator\Server\Web\Install\Custom directory.

### Web Navigator Client

On the Web Navigator Client computer, you must download the SICAM SCC software modules for the Web Navigator from the Web Navigator Server and install them (see chapter 11.3.5 Configuring the WinCC Web Navigator Client).

### 11.3.2 Publishing Process Diagrams

To make sure that the WinCC Web Navigator can show the process diagrams of the WinCC project, these diagrams must be published on the Web Navigator Server.

To publish the process diagrams:

- ☆ In the WinCC Explorer, now open the WinCC project which you want to show using the WinCC Web Navigator.
- In the WinCC Explorer, right-click Web Navigator and then select Web View Publisher from the context menu.

The Web Publishing Wizard opens.

🗣 WinCC Web Publishing Wizard - Select dire	ctories
	SIEMENS
15.00	Select the folder containing your WinCC pictures and the folder of the WinCC Web Server to which you will publish your pictures.
	Path to your WinCC project:
	Server Prefix
	*
	C:\Users\Public\Documents\Siemens\WinCCProjects\Demo_SCC\
	Publishing folder of the WinCC Web:
	C:\Users\Public\Documents\Siemens\WinCCProjects\Demo_SCC\Wel
SIEMENS	Diagnostics:
	Show hidden objects
	Cancel < Back Next > Finish

[pascc801, 1, en_US]

Figure 11-1 Selecting Process Diagram Directories

- ♦ Enter the name of the directory which holds the process diagrams of the WinCC project (...\projectpath \projectname).
- ♦ Enter the name of the Web access directory (...\projectpath\projectname\WebNavigator).
- ♦ Click Next. The diagram selection dialog is displayed.
- ♦ Select all diagrams.
- ♦ Click Next. The function selection dialog is displayed.

11.3 WinCC Web Navigator with SICAM SCC

💁 WinCC Web Publishing Wizard - Select functions	
	SIEMENS
Add 🗙 Remove 📰 🕶	
Files	Selected files
<ul> <li>SicamSAS\Command\ta = SicamSCC\Misc\SCC_P</li> <li>SicamSAS\misc\data_ty = SicamSCC\Misc\SCC_P</li> <li>SicamSAS\misc\get_stru = SicamSCC\Misc\SCC_P</li> <li>SicamSCC\Command\SC = SicamSCC\System\SCC</li> <li>SicamSCC\Command\SC = SicamSCC\Misc\SCC_R</li> <li>SicamSCC\Misc\SCC_R</li> </ul>	<
4	
Cancel	<pre></pre>

[pascc802, 1, en_US]

Figure 11-2 Selecting a Function

- ♦ Select all SICAM PAS, SICAM SCC and self-created functions.
- ♦ Click Next.

The selection dialog of the referenced graphic diagrams opens.

- ♦ Click Next.
- ♦ Click Finish.

The diagrams are published and available for display via the Web Navigator.

### 11.3.3 Installing Users for the WinCC Web Navigator

In SIMATIC WinCC, you must install a special user which is allowed to access the Web Navigator Server from the Web Navigator Client.

To install a user for the WinCC Web Navigator:

♦ Set up a new user.
🍿 User Administrator - WinCC Configuratio	on Studio				- 0	×
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>I</u> s <u>H</u> elp						
User Administrator «	siemens ] 🗠	Find	<del>،</del> م	🖙 Properties	- Authorization	>>
🖃 👘 User Administrator	Function	Enable	^	Selection		
Administrator-Group	1 User Administration			Object type	Authorization	
Administrator	2 Value input			Object name	Process controlling	
i siemens	3 Process controlling			General		
-	4 Picture Editing			Owner	siemens	
	5 Change picture			Owner type	Benutzer	
	6 Window selection			ID	3	
	7 Hardcopy			Function	Process controlling	
	8 Confirm alarms			Enable	V	
	9 Lock alarms					
	10 Free alarms					
	11 Message Editing					
	12 Start archive					
	13 Stop archive					
	14 Edit archive values					
	15 Archive Editing					
	16 Action Editing					
	17 Project Manager					
	18 Activate remote					
	19 Configure remote					
	20 Web Access - monitoring only					
	21					
	22					
	23					
	24					
	25					
	26					
	27					
Tag Management	28					
	29					
Alarmiogging	30					
Tag Logging	31					
222	32					
📑 🎁 🛄 🐢 🛧 🔛 👻	Authorizations	<	>			
Ready NUM	English (Unite	d States) Selection: 1 A	uthorizations Table: 20	0 Authorizations	100 % 🗐 — 🖓	- + .:

Figure 11-3 Setting up New Users

- Select WebNavigator.
   The Web Options are displayed.
- ♦ Select a published diagram (e.g. ROOT.PD_) as a start picture.
- ♦ Select the rights of the individual user.



### NOTE

If the function number **1002 – Web Access – monitoring only –** is activated, the user is only allowed to monitor the WinCC project as a Web Navigator Client.

In order to display it in the SICAM Controls dialogs, an authorization must have been configured for the Control.

### 11.3.4 Configuring the WinCC Web Navigator Server

Generate a web site on the WinCC Web Navigator Server and make it available to the Web Navigator Client.

- ♦ Start your WinCC project.
- In the WinCC Explorer, right-click Web Navigator and select Web Configurator from the context menu.
   The WinCC Web Configurator opens.
- ♦ Click Next.

[[]pascc804, 1, en_US]

11.3 WinCC Web Navigator with SICAM SCC

覺 WinCC Web Configurato	r 💌
	Here, you can specify a name, IP address and TCP connection (default: 80) for your Web site: Name of the Web site: WebNavigator Port: IP Address: 80 (All not assigned) • Default Web-Page: MainControl.asp • Reconnect Interval 10 s V Start the web-site after being configured.
	Cancel < Back Next > Finish

[pascc803, 1, en_US]

Figure 11-4 Configuring the WinCC Web Navigator

As a rule, you can perform the specified settings in this dialog.

♦ Click **Finish** to finish the configuration of the server.

### 11.3.5 Configuring the WinCC Web Navigator Client

#### **Installing Plug-ins**

To install the SICAM SCC plug-ins on the client computer:

- ♦ Start the Internet Explorer.
- ♦ Enter the IP address of the server computer.
- ♦ Enter the WinCC user name and the password which have been previously set up on the server.
- ♦ Click **OK** to confirm.

The connection to the Web Navigator Server is established.

- ♦ Install the **Web Navigator-Client**.
- ♦ Navigate to the **Download Area > Download Plug-Ins**.

(=) @ http://192.168.48.139/	- ¢	Suchen		× 戀 🙂
V75-W10 - Web Navigator × 📑				
Download/Install - WinCC/WebN	avigato	r Custom F	Plugins	
Component	Size	Status Versio	on Install	
SICAM SCC V9 for WebNav V7.2 SICAM SCC V9.03 components for SIMATIC WinCC V7.2 (build: V7.2 Upd13)	2,144 K	Not installed	→ 9.3.0.0	
SICAM SCC V9 for WebNav V7.3 SICAM SCC V9.03 components for SIMATIC WinCC V7.3	2,140 K	Not installed	→ 9.3.0.0	
SICAM SCC V9 for WebNav V7.4 SICAM SCC V9.03 components for SIMATIC WinCC V7.4	2,140 K	Not installed	→ 9.3.0.0	
SICAM SCC V9 for WebNav V7.5 SICAM SCC V9.03 components for SIMATIC WinCC V7.5	2,140 K	Not installed	→ 9.3.0.0	
WinCC Advanced Process Control WinCC Advanced Process Control	1,080 K	Not installed	→ 7.5.0.0	
WinCC Basic Process Control WinCC Basic Process Control	1,418 K	Installed 7.5.0	.0 → 7.5.0.0	
→ Screens				
<				>

[[]pascc800, 1, en_US]

Figure 11-5 Web Navigator, Installing Plug-ins

- ♦ Click the arrow under Version Install.
- Click Open in the dialog which opens. The plug-ins are installed.
- After the installation in the Windows Explorer, open the path C:\Program Files (x86)\Common Files \Siemens\Bin (for Windows 32-bit C:\Program Files\Common Files\Siemens\Bin) and execute the SCCCommon.bat file with administrator rights.



### NOTE

The SICAM SCC WebPlugIn requires the Microsoft .NET Framework 4.7.2 and the Visual C++ runtime components.

If the Visual C++ runtime components do not exist on your computer, you can install them from the SICAM SCC DVD (..\SetupData\InstallationData\Prerequisites\vcredist_x86_xxxx.exe).

#### **Displaying a Process Diagram**

The WinCC project must have been started on the Web Navigator Server in order to display the process diagram on the Web Navigator Client.

♦ Navigate to Process Diagrams. The process diagram is shown in the browser.



### NOTE

Use the **Logon** and **Logoff** hotkeys in order to change the user on the Web Navigator Client. The hotkeys are defined in the Project Properties, see 3.2.2 Defining Project Properties.

# 12 System Time

12.1	Overview	402
12.2	Updating Time Zones	403
12.3	Time Synchronization	404

### 12.1 Overview

The time information for SICAM SCC can be updated by downloading the IANA time zone database.

In the SICAM SCC system, a correct time is very important. A radio clock can be used as timer. The time of this clock is distributed over the system. The functionality of time distribution will be described by means of example configurations.

### 12.2 Updating Time Zones

In the IANA time zone database the time zone information of the world is maintained. This includes changes caused by political decisions regarding time zone boundaries, UTC deviations, and changes between daylight saving time and standard time. By downloading this time zone information you can update the time zone information in the SICAM system.

To update the time zone information:

- ♦ Open the Internet site http://www.iana.org/time-zones.
- ♦ Download the current version of the time zone file tzdata20xxx.tar.gz, e.g.: Time Zone Data v. 2014g (Released 2014-08-28) tzdata2014g.tar.gz (278.2kb)
- ♦ Open the directory where the program for updating the time zone information is located.
  - For Windows 32-bit operating system:

%CommonProgramFiles%\Siemens\Energy\TimeZoneCalculations\bin

- For Windows 64-bit operating system:
  - %CommonProgramFiles(x86)%\Siemens\Energy\TimeZoneCalculations\bin
- Highlight the TimeZoneDataUpdater.cmd file and select Run as administrator from the context menu.
   The command line tool opens.
- In the following dialog, navigate to the downloaded time zone file and open it.
   The update of the time zone information is started.
- ♦ Click **OK** to close the program.

After the update the runtime loads the new time zone data within one hour. You do not have to shut down or reboot the system.

### 12.3 Time Synchronization

Time information within a SICAM SCC system can be synchronized as follows:

- Through an **NTP clock** (for example, SICLOCK, Hopf Time Server, and Meinberg Time Server), an external device connected to the SICAM PAS/PQS computer through Ethernet.
- Through a **remote terminal interface** from the control center. from the control center. This time synchronization method is not relevant for SICAM SCC.

The time synchronization of SICAM SCC is based on the NTP(Network Time Protocol) and the corresponding NTPD (Network Time Protocol Daemon) software. Under a Windows operating system, the NTPD service runs in the background. For the installation of SICAM PAS/PQS, it is referred to as the Network Time Protocol Service It is configured by means of thentp.conf ASCII file. To edit this configuration file, Siemens recommends a text editor with the YAML markup language support, for example, Notepad++. Using this editor, comments and entries are displayed in different colors. The configuration file is located in the Windows directory, subfolder \drivers\etc\, for example: C:\WINNT\system32\drivers\etc\.



### NOTE

Windows 7, Windows Server 2008 and Windows Server 2012 do not allow to edit the ntp.conf file directly within the Windows directory.

If you use one of these operating systems, copy the **ntp.conf** file to another directory (outside of the Windows directory), for example to the desktop. Edit the copied file there and save it to the Windows directory afterwards, overwriting the existing file.

The NTPD is automatically installed together with **SICAM PAS/SICAM SCC**. It is activated upon a restart of the computer.

In a SICAM SCC system, several NTPDs are simultaneously active (for example, on the external radio clock, the SICAM PAS/PQS, and the SICAM SCC computer). An NTPD can be configured as a Server or as a Client. Upon the request of a Client, the Server communicates its time information to the Client.

Based on NTP, a precision of approximately 0.1 ms can be achieved under a Windows operating system. In order to achieve this high precision, the system's NTPDs must perform extensive calculations. This process can take several hours after the system starts. If the current Time Master fails, the NTPDs use the time data determined in order to keep an utmost level of time precision for as long as possible.

For more detailed information on NTP, refer to the following web site: http://www.ntp.org.

### 12.3.1 Network Time Protocol Daemon

For the configuration of the NTPD, knowledge about its main functions is required. Some NTPD functions and terms are illustrated below.

### Server, Client, and Peer

An NTPD can be configured as a **Server** or as a **Client**. The Server uses the current time information received from a clock. The Clients poll the time information from the Server.

Besides this, an NTPD can be configured as a **Peer**. This is the case if several clocks with the same priority exist in a distributed system. The roles (Server/Client) of the individual NTPDs are not specifically defined. The peers communicate among each other in order to determine the quality of their time signal. The NTPD of the peer with the most precise time signal is the Server.

### Stratum, Offset, and Dispersion

The NTP time distribution is based on a hierarchical structure. Time information is distributed from the top level down to the lower levels. A level is referred to as a **stratum**. The clock is the top level and is referred to as Stratum 0. The Time Server, which receives its time information directly from the clock, is assigned Stratum 1. The Server, which acts as a Client of this Server is assigned Stratum 2.

The **offset** is the difference between the Client clock and the Server clock. The NTPD tries to keep the offset as small as possible. The offset is the most important criterion for the determination of the quality of time information.

The **dispersion** is another criterion used for quality determination. The dispersion defines the upper limit for the deviation of the system time from the 'real' clock time. The smaller the dispersion, the higher is the quality of the time information.

#### **Quality of Time Information**

During the SICAM PAS/PQS Runtime, the delivered time stamp is assigned a **quality** for the determination of the system time. The following 4 quality levels can be assigned:

- **High** means that the system time deviates from the 'real' clock time by less than 10 ms and that the quality of the time sources is sufficient for this determination. A dispersion of less than 10 ms is sufficient to meet the standard requirements in the field of power automation.
- **Medium** means that the system time deviates from the 'real' clock time by less than 2 s and that the quality of the time sources is sufficient for this determination. This level of precision ensures that no low-quality time stamps are produced if a switching second is inserted and the clock therefore shows a temporary deviation of ~1 second.
- Low means that the available time information does not have the required precision and that the system must therefore be considered as 'out of synchronization'.
- **Unknown** is assigned if the system detects that no NTP service runs at all or that the service was not able to detect a time source.

For compatibility reasons, a SICAM SCC-internal time stamp includes the **ClockSync** and **ClockValid** status bits. These bits are set depending on the quality of the time stamp:

• High

The ClockSync and ClockValid status bits are set.

- Medium The ClockValid status bit is set.
- Low No status bit is set.
- Unknown No status bit is set.

### 12.3.2 Configuration File for NTPD

When installing SICAM PAS/PQS or SICAM SCC, an ntp.conf configuration file is copied into the ...\%windir% \system32\drivers\etc or ...\%windir%\SysWow64\drivers\etc directory. The %windir% directory name depends on the operating system, for example, Windows or WINNT. This file is used to configure the NTPD.

The Time Servers are indicated in the configuration files of the Clients. However, the Clients are not indicated in the configuration files of the Servers. A Time Client can therefore be conveniently added to a system. Only the configuration file of the new Client needs to be edited.

The configuration file includes some comments on its contents. This paragraph provides information about important entries.

For more detailed information, refer to the following web site: http://www.ntp.org.

#### **General Settings**

```
# _ _ _
# general settings
# -- panic threshold --
# if system clock is more than that distance from the best external source,
# stop the service because something is really weird.
tinker panic 7200.0
# -- driftfile storage --
# NTPD will store the clock drift here, so after restart the service will
# lock the FLL/PLL faster. On embedded systems, make sure that file is
# writeable and on a non-write-protected file system!
driftfile %windir%\ntp.drift
# -- logfile storage --
# make sure this is a writeable file on a non-write protected file system!
#logfile D:\tmp\ntpd.log
# -- Statistic file storage --
# make sure this is a directory on a non-write protected file system!
#statsdir D:\tmp\ntpstats\
```

Tinker panic

If the clock concerned deviates by more than 7,200 s from the best external clock, time information is not synchronized. The NTPD stops automatically or does not start up.

The **Services Manager** indicates whether the NTPD has started or not. Press **<F5>** to update the Services Manager. Set the local system time manually and start the NTPD.

• Driftfile, logfile, statsdir

Activate the **logfile** and **statsdir** lines for error detection only.

The quartz drift determined is stored in the **ntp.drift** file. This allows for faster synchronization after a system start, because the clock can be set to the correct speed based on the offset value. If no writeable (and reset-proof!) file system is available, the drift file can be disabled. In this case, optimum synchronization can only be achieved some time (hours!) after a system start.

#### **Reference Clocks**

Using the lines under **local system clock**, you can define the local clock as the timer. Define a high value for the stratum. The local time is used unless another, better time base is available.

#### **Shared Memory Clocks**

```
# _ _ _ _
# shared memory clocks ('iburst' is not useful here)
#_____
# minpoll 2 -> 4s / maxpoll 6 -> 64s, mode 33 -> adaptive polling
# channel 1
server 127.127.28.0 mode 33 minpoll 2 maxpoll 6
fudge 127.127.28.0 stratum 5
# channel 2
server 127.127.28.1 mode 33 minpoll 2 maxpoll 6
fudge 127.127.28.1 stratum 5
# channel 3
server 127.127.28.2 mode 33 minpoll 2 maxpoll 6
fudge 127.127.28.2 stratum 5
# channel 4
server 127.127.28.3 mode 33 minpoll 2 maxpoll 6
fudge 127.127.28.3 stratum 5
```

These lines are required in order to use **shared memory clock drivers**. They are used for time synchronization through telecontrol protocols.

#### • Mode

Through mode 33 (see *Table 12-1*), you can define adaptive polling. During adaptive polling, the frequency of the poll is automatically adjusted to the poll result. If the result rarely changes, polls are performed less frequently.

#### • Minpoll, maxpoll

The **minpoll** and **maxpoll** parameters must be specified in such a way that the range matches the current synchronization rate of the control center as precisely as possible.

#### Peers

```
#-----
# peers: all time sync peers in a PAS installation
#------
# If the local system has reference clock access, mention all other systems
# (full servers and dips) in a PAS installation that can also access reference
# clocks. Peers will negotiate the leader of the pack...
# minpoll 2 -> 4s / maxpoll 6 -> 64s, iburst -> initial burst poll
#peer xxx.xxx.xxx minpoll 2 maxpoll 6 iburst
```

If one Full Server and one or several DIP(s) are used, the synchronization sources can be distributed among the computers used (HOPF6039 on the Full Server and telecontrol protocols on the DIP). To do this, activate the **peer** line.

In this case, the computers must determine among each other which clock time is most suitable. Since the classical Server/Client relationship cannot be applied in this context, all the computers involved must be configured as **peers** (that is, **colleagues** with the same priority). Data is exchanged on a bidirectional basis in order to ensure that synchronization can be performed by both systems.

#### Servers

# ----# servers
# ----# If the local system has no reference clock access, mention all systems that
# have reference clock access here. If there is a network path to an external
# clock source (NTP server in the control center, for example) list them
# here, too. And furthermore mention all fallback servers that can be used!
# minpoll 2 -> 4s / maxpoll 6 -> 64s, iburst -> initial burst poll
#server yyy.yyy.yyy minpoll 2 maxpoll 6 iburst

The following lines serve as examples for the definition of Time Servers. The information in these lines can be used for demo purposes only. In a **real** environment, the user must enter the parameters for Real Time Servers..

server 139.25.31.13 minpoll 2 maxpoll 6 iburst server 139.25.208.27 minpoll 2 maxpoll 6 iburst server ntp.lpz.siemens.de minpoll 2 maxpoll 6 iburst

### 12.3.3 Clock Driver for Telecontrol Protocols (Shared Memory Clock Driver)

The driver for telecontrol protocols (Shared Memory clock driver) has been modified in such a way that it ensures proper time synchronization in the SICAM PAS/PQS system.

Using a **shared memory clock driver**, the time in a SICAM PAS/PQS system can be synchronized based on telecontrol protocols.

The following 2 modes are supported:

Mode 0

Mode 0 corresponds to the mode described in the original HTML documentation. This mode cannot be used with SICAM PAS/PQS.

Mode 1

Mode 1 is a Shared Memory clock driver with an extended functionality as used for SICAM PAS/PQS.

This paragraph only describes Mode 1.

The **ntp.conf** configuration file consists of 4 blocks for time synchronization through telecontrol protocols. A typical block has the following structure:

server 127.127.28.0 mode 33 minpoll 2 maxpoll 6 fudge 127.127.28.0 stratum 5

The 3rd address section (assigned the value 28 in the example above) defines the type of clock driver. The 4th address section (0 in the example) is used to distinguish between clocks of the same type.

#### Mode

Mode 33 is an advanced mode with timeout monitoring. In the **fudge** line, the value 5 is specified for the stratum.

In a SICAM PAS/PQS, only modes 1 or 33 can be used for time synchronization through telecontrol protocols. In a SICAM PAS/PQS, only modes 1 or 33 can be used for time synchronization through telecontrol protocols. With mode 33, timeout monitoring is automatically included. This is the most convenient mode. When using Mode 1, the values of the **minpoll** and **maxpoll** parameters must be selected very carefully in order to match the synchronization frequency of the telecontrol center.

The **minpoll** parameter must be set in such a way that **2^minpoll** is greater than the synchronization interval of the control center. The **maxpoll** parameter must also be set to this value.

The **mode** parameter must be interpreted as a bit pattern (decimal value). The tables below illustrate the significance of the bits.

Bit	7	6	5	4	3	2	1	0
Bitpattern	0	0	1	0	0	0	0	1
Value	0	0	1	0	1			

Table 12-2	Parameter	mode	33
	rurumeter	mouc	55

Bit position	Meaning
Bit 0 to 3	Bits 0 to 3 define the mode.
	This half byte must have the value <b>1</b> for the cooperation with the telecontrol protocols of SICAM PAS/PQS.
Bit 4	Setting the clock time
(Bit value 16)	If this bit is set, the clock driver initiates clock setting to the value present in the clock if the difference between the system time and the time available in the clock is more than 10 s.
	This difference value can be increased, but not reduced by means of <b>fudge time2</b> .
Bit 5	Timeout monitoring
(Bit value 32)	If this bit is set, the clock driver attempts to optimize the actual poll cycle within the limits predefined by <b>minpoll</b> and <b>maxpoll</b> .
Bit 7	Writing information in the system log file
(Bit value 128)	This bit is only relevant for diagnosis. All information, warning, and error conditions are written into the system log file.
	If this bit is not set, the driver does not attempt to perform any entries in the event list of the system ('quiet mode').

#### Minpoll, maxpoll

If **automatic time monitoring** (adaptive polling) is activated, the NTPD tries to set a polling interval within the limits selected through **minpoll** and **maxpoll**. If the telecontrol protocol did not provide any value within a defined interval, the polling interval is increased by one step. If more than 2 values are transmitted within an interval, the polling interval is reduced by one step.

If synchronization based on the telecontrol protocol fails, the polling interval increases until the maximum interval value has been reached. The clock is marked as faulty and the polling interval is set to the minimum value in order to detect a recovery of synchronization as quickly as possible.

The values for **minpoll** and **maxpoll** must be selected in such a way that they include the expected time synchronization interval of the telecontrol protocol. Minpoll and maxpoll are exponents referred to a basis of 2. The following values can be used: minpoll = 2(22 = 4 s); maxpoll = 10(210 = 1024 s = 17 min)

### Fudge

• Time1

As with most clock drivers, this value is used in order to compensate a systematic (constant) offset. For example, the runtime of the telecontrol telegram between the control center and the substation can be corrected. The value is defined as a floating point value indicated in seconds.

• Time2

Time2 The difference value for clock time setting can be increased to a value greater than 10 s, see Bit 4 in the description of mode, *Table 12-1*. The value is defined as a floating point value indicated in seconds.

### 12.3.4 Example – External Radio Clock as Timer

For system configurations with an IEC 61850 Ethernet bay bus, an **external radio clock** (for example, SICLOCK, Meinberg, and Hopf) can be used as the Time Master on the Ethernet. If this clock fails or if the quality of the time information is poor, another clock available in the system becomes the Time Master. In the NTPD configuration files, you can define which clock is to become the new Time Master.

The NTPD is active on both SICAM PAS/PQS computers (Full Server and DIP) and on the SICAM SCC computer. The NTPD of the radio clock is the Time Server; the NTPDs of the SICAM PAS/PQS computers are the Clients. Additionally, time information can be transmitted from the telecontrol center.



Figure 12-1 Time Synchronization through an External Radio Clock, Example

The bay devices on the IEC 61850 bus are Clients, which poll time information from the radio clock. Their configuration is not described in the present document. For more detailed information on this topic, refer to the documentation of the corresponding devices.

All other bay devices connected through IEC 60870-5-103 receive time information from the DIP.

#### **Configuration Files**

This paragraph provides a list of the **ntp.conf** configuration files for the SICAM PAS/PQS and the SICAM SCC computers. The entries in the list have been customized for the example illustrated. Be aware that the real system configuration (for example, IP addresses) of your own environment must be considered. Changes to the predefined configuration files have been highlighted. Configuration file of the **SICAM PAS/PQS DIP**:

```
#_____
             _____
# general settings
#_____
# -- panic threshold --
# if system clock is more than that distance from the best external source,
# stop the service because something is really weird.
tinker panic 7200.0
# -- driftfile storage --
# NTPD will store the clock drift here, so after restart the service will
# lock the FLL/PLL faster. On embedded systems, make sure that file is
# writeable and on a non-write-protected file system!
driftfile %windir%\ntp.drift
# -- logfile storage --
# make sure this is a writeable file on a non-write protected file system!
#logfile D:\tmp\ntpd.log
# -- Statistic file storage --
```

```
# make sure this is a directory on a non-write protected file system!
#statsdir D:\tmp\ntpstats\
```

```
#------
# shared memory clocks ('iburst' is not useful here)
#-------
# minpoll 2 -> 4s / maxpoll 6 -> 64s, mode 33 -> adaptive polling
# channel 1
server 127.127.28.0 mode 33 minpoll 2 maxpoll 6
fudge 127.127.28.0 stratum 5
# channel 2
server 127.127.28.1 mode 33 minpoll 2 maxpoll 6
fudge 127.127.28.2 mode 33 minpoll 2 maxpoll 6
fudge 127.127.28.2 mode 33 minpoll 2 maxpoll 6
fudge 127.127.28.2 stratum 5
# channel 4
server 127.127.28.3 mode 33 minpoll 2 maxpoll 6
```

```
fudge 127.127.28.3 stratum 5
```

#_____

```
#-----
# peers: all time sync peers in a PAS installation
#------
# If the local system has reference clock access, mention all other systems
# (full servers and dips) in a PAS installation that can also access reference
# clocks. Peers will negotiate the leader of the pack...
```

```
# minpoll 2 -> 4s / maxpoll 6 -> 64s, iburst -> initial burst poll
peer 192.168.1.6 minpoll 2 maxpoll 6 iburst
```

The SICAM PAS/PQS DIP must be entered as a peer for the radio clock. If this is not possible, the radio clock must **not** be used as a peer, but as the Server:

```
# servers
# servers
# If the local system has no reference clock access, mention all systems that
# have reference clock access here. If there is a network path to an external
# clock source (NTP server in the control center, for example) list them
# here, too. And furthermore mention all fallback servers that can be used!
# minpoll 2 -> 4s / maxpoll 6 -> 64s, iburst -> initial burst poll
server 192.168.1.6 minpoll 2 maxpoll 6 iburst
```

Configuration file of the SICAM SCC computer and of the SICAM PAS/PQS Full Server:

```
# ---
# general settings
# _ _
   _____
# -- panic threshold --
# if system clock is more than that distance from the best external source,
# stop the service because something is really weird.
tinker panic 7200.0
# -- driftfile storage --
# NTPD will store the clock drift here, so after restart the service will
# lock the FLL/PLL faster. On embedded systems, make sure that file is
# writeable and on a non-write-protected file system!
driftfile %windir%\ntp.drift
# -- logfile storage --
# make sure this is a writeable file on a non-write protected file system!
#logfile D:\tmp\ntpd.log
# -- Statistic file storage --
# make sure this is a directory on a non-write protected file system!
#statsdir D:\tmp\ntpstats\
#_____
# reference clocks
#------
```

```
# -- local system clock
# the local system clock is used as level 10 fallback if everything fails and
# the server must continue to operate because of (S)NTP clients like
# IEC61850 devices et al.
server 127.127.1.0
fudge 127.127.1.0 stratum 10
```

# clocks. Peers will negotiate the leader of the pack...
# minpoll 2 -> 4s / maxpoll 6 -> 64s, iburst -> initial burst poll

#-----# If the local system has reference clock access, mention all other systems
# (full servers and dips) in a PAS installation that can also access reference

#_____

# peers: all time sync peers in a PAS installation

#peer xxx.xxx.xxx minpoll 2 maxpoll 6 iburst

fudge 127.127.28.3 stratum 5

```
#-----
# servers
#-----
# If the local system has no reference clock access, mention all systems that
# have reference clock access here. If there is a network path to an external
# clock source (NTP server in the control center, for example) list them
# here, too. And furthermore mention all fallback servers that can be used!
# minpoll 2 -> 4s / maxpoll 6 -> 64s, iburst -> initial burst poll
server 192.168.1.3 minpoll 2 maxpoll 6 iburst
server 192.168.1.6 minpoll 2 maxpoll 6 iburst
```

# **13** Converting Projects from Previous Versions

# i

NOTE

Perform the conversion steps from earlier versions to the new version one after the other.

13.1	Converting Projects Independently of the Version	416
13.2	Making Adjustments for V9.06	417
13.3	Making Adjustments for V9.04	418
13.4	Converting Topology, V9.00	419
13.5	Converting Projects, V8.04	420
13.6	Converting Projects, V8.03	421
13.7	Converting Projects, V8.02	422
13.8	Converting Projects, V8.01 or Earlier	423
13.9	Converting Projects, V8.00 or Earlier	424
13.10	Converting SICAM PAS/PAS CC Projects, V5.0 and V6.0	425
13.11	Converting Projects, V6.0x	426
13.12	Converting Projects, V5.11	427
13.13	Converting Projects, V5.10 or later	428
13.14	Converting Projects, V5.10 or earlier	429
13.15	Converting a SICAM WinCC Project	430

### 13.1 Converting Projects Independently of the Version

Perform the following steps in order to convert existing projects to the current version of SICAM SCC:

- Re-import the SICAM Graphic Object Library into your project.
- Open and save all diagrams (pictures) including SICAM objects:
  - Deactivate the SICAM Menu in the Graphics Designer (Tools > Add-In Manager > SICAM Add-in) and initiate the picture conversion. To do so, select Tools > Convert Project Data > Pictures and faceplates in the WinCC Explorer.
- The **Topological coloring** function has been revised. For information concerning versions earlier than V9.00 refer to 13.4 *Converting Topology*, V9.00.
- Run the SICAM Import/Export Wizard with the data previously imported.

In order to create the configuration data for the current SICAM Runtime with Dynamic Alarm Filter (DAF), you must execute the Import Wizard with existing import data once for each station in the project. This is also required if you do not use the DAF.

• For further steps, refer to 13.3 Making Adjustments for V9.04.

If the parameters of the SICAM objects configured in your diagram differ from the current version, a warning is shown in the Report when opening your diagram, informing you with which version the particular object was configured. Check the newly added parameters on the corresponding object.

When you open a diagram and the Report shows an error message regarding the configuration of a SICAM object, renew this object.



### NOTE

Make sure that you use the appropriate configuration licenses.



### NOTE

Perform the conversion steps from an older version to the new version sequentially.

### SICAM Import/Export Wizard

To import and export SICAM SCC configuration data, you can use the **SICAM Import/Export Wizard** for all supported import data formats. You can continue to use existing projects with the different predecessor wizards or convert to TEA-X import.

Please note: When converting a SICAM PAS/PQS connection, the TEA-X file must have the same configuration status as the previously imported PXD file. If this cannot be ensured, export both the TEA-X and the PXD file from SICAM PAS/PQS and then perform another PXD import with the SICAM PAS Wizard before converting the project via SICAM Import/Export Wizard.

During the conversion process, the name of the communication connection to SICAM PAS/PQS is changed to the name which you have defined in SICAM PAS/PQS for this connection (device level).

Please note: During the TEA-X import process, only 1 SCC connection per SICAM PAS/PQS project can be imported into an SCC project. You can import SCC connections from several SICAM PAS/PQS projects into an SCC project. The project ID of the SICAM PAS/PQS project must be different (SICAM PAS/PQS – UI Configuration – General Parameters of the Project).

### 13.2 Making Adjustments for V9.06

With the revision of the topological coloring, there are some changes to the configuration. Existing pictures work as usual in the runtime. However, if you want to make changes to a picture, you must first convert it.

Therefore, do the following:

- Open an existing WinCC project and update it with one of the Wizards. Choose the following setting:
  - Importing the SICAM graphic object library
- Open the **Topological Project Settings** dialog and make any changes (for example, apply the color for **de-energized lines** to the project settings), then close the dialog with **OK**.
- Open the picture in the **Graphics Designer**.
- Select all objects and open the Topological settings for selected objects dialog.
- The dialog's title bar additionally displays **Conversion mode**.
- If necessary, adjust the settings. Click **OK**.
- If you selected **Use topological project settings**, the settings made through **Topological Project Settings** are used for the selected objects.
- Save the picture and recreate the topological structure.

### Adjustments for Topological Coloring

Lines can now be configured in different weights; the runtime uses the configured stroke weights of the lines. It is possible to define line weights and the display mode for the lines project-wide.

When you open the **Topological settings for selected objects** dialog, the projected values of the selected objects are read in and displayed.

### 13.3 Making Adjustments for V9.04

Due to revisions and extensions of the Dynamic Alarm Filter (DAF) changes in the Alarm Logging have been necessary.

Therefore, perform the following steps:

- Open an existing WinCC project and execute and update with the Wizard, using the following options:
  - Importing the SICAM graphic object library
  - Create SICAM text library
  - Create SICAM alarm system
- Open an existing picture in the **Graphics Designer**.
- Open the **Project Library** and replace the Alarm Controls in the picture:
  - SICAM SCC Warning Message List
  - SICAM SCC Event List
  - SICAM SCC Protection Message List

### Adjustments for Using DAF

Before V9.04 every status could trigger an alarm. So for WinCC, every status change was a 'Came in' alarm which restarted the WinCC-specific algorithm. In V9.04 the treatment of the single-point indications in the DAF has been adjusted to the WinCC behavior: the single-point indication has 1 status triggering the alarm. For this, 2 new filter types have been introduced. Use the types **SI with Alarm when ON** and **SI with Alarm** 

when OFF, in order to trigger an alarm in WinCC with the ON or with the OFF status of the process value of the single-point indication. With this change the WinCC algorithm for rising/falling indications in the alarm list with the specific coloring and the acknowledge behavior is supported completely.

Therefore, move existing DAFs for single-point indications from the **Binary** node to the suitable node for single-point indications (**SI with Alarm when ON** or **SI with Alarm when OFF**).

### 13.4 Converting Topology, V9.00

A topological coloring configured with a SICAM SCC version prior to V9.00 cannot be converted automatically. This means that the configurations described in *4 Graphic Objects*, *5 Topological Coloring*, and *6 SICAM Add-In* have to be performed in order to convert an existing topological coloring.

To be able to use the topology in projects configured with a SICAM SCC version prior to V9.00, the according Import Wizard has to be executed once. This extends the data structure within SICAM SCC with the information required for the topology.

If you open an SCC project using topological coloring configured with an earlier version and start the runtime, the topological coloring will not be executed. However, in certain situations there may occur unwanted coloring. Thus, independent from topology usage, take care that all feeders are replaced by SICAM SCC V9.00 feeders.

The function Topologal coloring has been reworked. If you use the topological coloring you have to

- install the license for topological coloring,
- update the settings for the topological coloring in the SICAM Menu of the Graphics Designer,
- update the pictures of your project.

### 13.5 Converting Projects, V8.04

The SICAM PAS Protocol Suite V7 is no longer included. Change your SICAM SCC projects to the SICAM PAS Protocol Suite standard channel before updating the software.

### 13.6 Converting Projects, V8.03

Replace the message list templates (changing the fixed selection).

### 13.7 Converting Projects, V8.02

A new measured values object (SICAM Numeric) is available in order to speed up the updating times and enhance the system dimensions, see 4.8 *Measured/Metered Value Display*.

The former objects can be replaced via the SICAM SCC menu in the **Graphics Designer**. Select **Show task dialog** and perform steps 1 and 2 of the task **Measured value up to V8.01: Upgrade to SICAM Numeric Control (V8.02)**.

### 13.8 Converting Projects, V8.01 or Earlier

The function **Topological Coloring** has been revised.

If you use topological coloring, you need to update the pictures of your project. To do this, you use **Create topological structure** from the SICAM SCC menu to regenerate the topological links/scripts in the pictures.

### 13.9 Converting Projects, V8.00 or Earlier

The SICAM SCC Runtime Data Server component was introduced in order to increase the quantity scopes supported by SICAM SCC. SIMATIC WinCC, Version 7.0 SP3 or higher, is required as a prerequisite for using the SICAM SCC Runtime Data Server component.

New projects are automatically configured for operation with the SICAM SCC Runtime Data Server. Existing projects can be converted, but can also be operated without conversion.

The following conversion steps must be performed in order to convert existing projects (basis SIMATIC WinCC V7.0 SP3 or higher) for operation with the SICAM SCC Runtime Data Server:

- Delete and re-import the process data using the corresponding wizard (at least the SICAM process tags function).
- $\diamond$  Re-import the SICAM Graphic Object Library into your project.
- ♦ If you use topological coloring, remove the topological coloring via SICAM add-in.
- Upgrade the switching device objects and bay overview objects via the SICAM SCC menu in the Graphics Designer (show task execution box – perform the upgrade of V7 switching device objects and overview objects for each picture).
- ♦ If you use the topological coloring, you generate the topological coloring once again via SICAM add-in.
- ♦ Replace the Acknowledge blinking button in the pictures.

For **SICAM Switch Controls, V8.0 or later** the **AckFlashing** tag is used (the status changes are inverse to the tags for earlier versions – **QuitBlinking**).



### NOTE

When replacing objects in WinCC V7.4, connections to the connectors may be lost and the topology cannot be generated. In this case, re-connect the connectors to the switching device and bay overview objects. This does not occur for WinCC V7.3 or earlier versions.

### 13.10 Converting SICAM PAS/PAS CC Projects, V5.0 and V6.0

#### Conversion of the SICAM PAS project

During the conversion the contents (interface level) of the first SICAM PAS CC DIP of the SICAM PAS project are transferred to the Full Server, and the IP address of the DIP is entered as the device address of the SICAM PAS CC (SCC) control center.

All the other SICAM PAS CC connections are converted manually because the user cannot decide during conversion whether further DIPs are redundant SICAM PAS CC (SCC) or independent SICAM PAS CC (SCC) connections.

For redundant SICAM PAS CC connections on 2 Version 6 DIPs you only need to enter the IP address of the second DIP at **SICAM PAS CC (SCC) 2** in the communication parameters of the converted control center. Afterwards you can delete the DIP.

Next, export the control center data for SICAM PAS CC (SCC) and import the in your WinCC project. For picture objects and scripts you need to adapt the tags which include the interface ID in the name. Afterwards, the WinCC project can be duplicated to the redundancy partner using the WinCC Project Duplicator. No SICAMspecific adaptations and no data import are required in the redundant project.

In case of independent SICAM PAS CC connections you can transfer the interface from the SICAM PAS CC DIP into the SICAM PAS CC (SCC) application on the Full Server. Configure the IP address of the SICAM SCC computer (Version 6 DIP address) on the control center level. Afterwards you can delete the DIP.

Export the control center data for SICAM PAS CC (SCC) and import them in your WinCC project. For picture objects and scripts you need to adapt the tags which include the InterfaceID in their name.

After the conversion you must change the parameter settings of the SICAM PAS CC (SCC) interface. Enter e.g. the IP address for communication with the SICAM SCC system.oll.

#### **Different configuration**

Contrary to SICAM PAS V6.0 the SICAM SCC connections are configured on the Full Server and no longer as a DIP.

On the interface level you define the assignment of the switching authority group, the IP address of the Full server network card for communication (this address corresponds to the one to be entered for the SICAM PAS in the SICAM PAS channel) and the port number.

On the control center level you define the IP addresses of the SICAM SCC computer(s) and the channel monitoring time. (Make sure that an identical channel monitoring time is defined in SICAM SCC).

Redundant SICAM SCC systems are configured as a control center; the two IP addresses of the SICAM SCC computers are entered in the communication parameters.

Independent SICAM SCC systems to be connected to a SICAM PAS are configured in separate interfaces. This enables a different assignment of the switching authority group.

### 13.11 Converting Projects, V6.0x

Perform the following steps with the SICAM PAS Wizard:

- ♦ Re-import the SICAM Graphic Object Library into your project.
- $\diamond$  Update the process data using the PXD file.

### 13.12 Converting Projects, V5.11

Re-import the SICAM Graphic Object Library into your project using the SICAM PAS Wizard.

The **Topological coloring** function was completely revised and is no longer compatible with Version 5.11, but you can still use pictures in the version.

Advanced structure types are required for substitution. You must convert the structure types if you want to use the **Substitute** function supported for V6.0 or higher after the upgrade or if you use the Web Navigator in your project.

There are 2 alternatives for the conversion of the structure types:

Alternative 1

Follow the description in 14.8 Working with the SIMATIC WinCC Configuration Tool.

Alternative 2

Use the wizard to delete the **SICAM process tags** and then manually delete the structure types in your project.

Next, re-import the **SICAM process tags** using the wizard. The advanced structure types are generated during this process.

### 13.13 Converting Projects, V5.10 or later

Use the SICAM PAS Wizard to re-import the SICAM Graphic Object Library.

If problems occur during the archiving of an existing project in **TagLogging**, the **SICAM Archives** must be deleted with the wizard. Afterwards, the **MeasuredValueArchive_x** and the **MeteredValueArchive_x** created by the wizard must be deleted in **TagLogging**, and the **SICAM** time must be manually deleted. Afterwards you can re-import the archive tags using the wizard.

Advanced structure types are required for substitution. If you want to use the **Substitute** function supported for V6.0 or later after the upgrade or if you are using the Web Navigator in your project, you must convert the structure types.

There are 2 alternatives for the conversion of the structure types:

- Alternative 1 Follow the description in 14.8 Working with the SIMATIC WinCC Configuration Tool.
- Alternative 2

Use the wizard to delete the **SICAM process tags** and then manually delete the structure types in your project.

Next, re-import the **SICAM process tags** using the wizard. The advanced structure types are generated during this process.

### 13.14 Converting Projects, V5.10 or earlier

Use the SICAM PAS Wizard to re-import the SICAM Graphic Object Library in your project.

If problems occur during the archiving of an existing project in **TagLogging**, the **SICAM Archives** must be deleted with the wizard. Afterwards, the **MeasuredValueArchive_x** and the **MeteredValueArchive_x** created by the wizard must be deleted in **TagLogging**, and the **SICAM** time must be manually deleted. Afterwards you can re-import the archive tags using the wizard.

If you use the **AlarmListFilter** object from the library, replace it by the new version. The functionality of this object was swapped out to a global script. This ensures that the alarm list filter settings are also maintained after exiting the Runtime, see 7.6.7 *Global Actions*.

Advanced structure types are required for substitution. If you want to use the Substitute function supported for V6.0 or later after the upgrade or if you are using the Web Navigator in your project, you must convert the structure types.

There are 2 alternatives for the conversion of the structure types:

- Alternative 1 Follow the description in 14.8 Working with the SIMATIC WinCC Configuration Tool.
- Alternative 2

Use the wizard to delete the **SICAM process tags** and then manually delete the structure types in your project.

Next, re-import the **SICAM process tags** using the wizard. The advanced structure types are generated during this process.

### 13.15 Converting a SICAM WinCC Project

Use to SICAM Global Wizard in order to reimport the SICAM graphic object library into your project. Advanced structure types (new IXHook element) are required for projects created with SICAM WinCC V3 or earlier versions.

2 alternatives are possible for the conversion of structure types:

• Alternative 1

Proceed as described in 14.8 Working with the SIMATIC WinCC Configuration Tool.

• Alternative 2

Alternative 2: Delete the **SICAM process tags** using the Wizard. Afterwards, manually delete the structure types for the **SICAM SAS** connection (without **PAS_** in the name) in your project.

Reimport the **SICAM process tags** using the Wizard. The advanced structure types are generated during this procedure.

Replace the **IndustrialX V3** objects by the up-to-date objects (V3 objects are only available in configuration mode) using the SICAM add-in (upgrade of V3 switching device objects / overview objects).

In order to ensure that the properties of V3 switching device objects and overview objects are applied correctly, the tag names and the text for the tooltip in the properties of the tag connection must be empty in the target SAS object. Before calling up the update, open the properties of the SAS object and delete all tag names and the tooltip text under **Tag connection**.

Connected scripts are also applied when replacing the objects.

- Check whether the configured scripts function correctly (especially with regard to object properties used).
- Remove the script from the **Clicked** event of the object. This script served to open switching dialogs which are no longer required with the current object because they are integrated.

## 14 Components and Functions of Earlier SICAM PAS CC/SCC Versions

14.1	Double/Redundant Configuration in V5/V6 Projects	432
14.2	Circuit Breaker and Disconnector	442
14.3	Bay Overview	476
14.4	Showing Texts in Runtime Dialogs	481
14.5	IX State Sync Application	486
14.6	Measured-Value Display Using the Script/Project Function	491
14.7	Introduction to the SIMATIC WinCC Configuration Tool	495
14.8	Working with the SIMATIC WinCC Configuration Tool	505

14.1 Double/Redundant Configuration in V5/V6 Projects

### 14.1 Double/Redundant Configuration in V5/V6 Projects

This chapter explains the double/redundant configuration concept in SICAM PAS/SCC systems, SICAM PAS/ PAS CC V6.03 or earlier. This type of connection of double SICAM PAS systems should no longer be used with the new SICAM PAS V7.0 version. However, the parameters of systems which are upgraded from SICAM PAS V5/V6 do not necessarily need to be modified. The explanations below apply to these systems.

For safety reasons, a SICAM PAS system can be implemented in double/redundant configuration. This means that certain components can be implemented in double/redundant configuration depending on the specific requirements of the individual system. This section describes the implementation of the configurations illustrated below.

- A doubled SICAM PAS system is connected to 1 SICAM SCC Human-Machine Interface (HMI).
- 1 SICAM PAS system is connected to 2 redundant SICAM SCC HMIs.

Further double/redundant configurations are possible. For example, double SICAM PAS Full Servers can also be connected to a redundant SICAM SCC system.

For more detailed information on redundancy, refer to the SIMATIC WinCC documentation.

### 14.1.1 Connection to 2 SICAM PAS Systems

A SICAM PAS system can consist of 2 SICAM PAS Full Servers running in parallel. Bay devices and substations are connected to both SICAM PAS Full Servers. SICAM SCC is connected to both SICAM PAS Full Servers via the SICAM PAS PROTOCOL SUITE.

The connection to a SICAM PAS Full Server (e.g. to Server1) is referred to as the **normal path**; the connection to the other SICAM PAS Full Server (e.g. to Server2) is the so-called **redundant path**. During fault-free operation, the connection via the normal path is active.

For SICAM SCC, a switchover to the redundant path must be performed if one of the following 2 scenarios occurs:

• The normal path of the SICAM PAS PROTOCOL SUITE to the connected SICAM PAS Full Server is interrupted.

The active connection of the SICAM PAS PROTOCOL SUITE to the SICAM PAS Full Server is permanently monitored. When an error occurs, the system automatically switches over to the redundant path (to the other SICAM PAS Full Server), provided that this path has been configured.

• The communication between the SICAM PAS Full Server accessed by SICAM SCC and the bay devices is disturbed.

This scenario also requires a switchover to the redundant path. This fault, however, cannot be detected by the SICAM PAS PROTOCOL SUITE. The detection of the fault and the switchover to the redundant path can be realized by other means. The required procedure is described below.



### NOTE

For the connection to SICAM PAS V7.0, the configuration of the SICAM PAS PROTOCOL SUITE (SICAM PAS channel DLL) must be set to SICAM PAS V6 redundancy.


Figure 14-1 System with doubled SICAM PAS system

The following components are required for the monitoring and switchover of the connections (between the normal and the redundant path):

- a process tag
- the ConnectionState_xxx bit array (32 bits)
- the ForceConnectionState_xxx bit array (32 bits)
- the WinCC script SicamPAS_ConnectionChange.pas

#### Process tag

In order to be able to monitor the connection between the SICAM PAS system and the bay devices, a process tag must be created in SICAM PAS UI-Configuration and mapped to SICAM SCC. This process tag can be e.g. a message derived via CFC and enabling the evaluation of the quality of the connection to the bay devices. This process tag can be evaluated using the **SicamPAS ConnectionChange.pas** or **SicamPAS IsHeMaster**-

**Check.pas** WinCC script. The quality of the active connection can be assessed by means of the evaluation of the process tags.

# ConnectionState

The **ConnectionState_xxx** bit array shows the status of the active connection between the SICAM PAS PROTOCOL SUITE and the SICAM PAS system.

The bit array is defined as follows:

Bit	Meaning
0	0 = no connection
	1 = connection active
1	1 = connection via normal path
2	1 = connection via redundant path
3 to 31	System-internal use

## ForceConnectionState

The behavior of the SICAM PAS PROTOCOL SUITE can be influenced by writing the **ForceConnectionState_xxx** system tag.

The bit array can only be written completely. Read access is not possible.

The bit array is defined as follows:

Bit	Meaning
0	If this bit is set, the SICAM PAS PROTOCOL SUITE switches over to the other SICAM PAS Full Server.
	The triggering is performed using the WinCC script.
1	If this bit is set, the connection is activated via the normal path.
2	If this bit is set, the connection is activated via the redundant path.
3 to 31	Reserved

# WinCC script

The process tag is evaluated using the **SicamPAS_ConnectionChange.pas** WinCC script. The proper functioning of the SICAM PAS system (including the communication with connected devices) can be checked by means of this evaluation.

If the quality of the active connection is found to be poor, the system can switch over to the other path using the system tag **ForceConnectionState_xxx**.

A template of the SicamPAS_ConnectionChange.pas WinCC script

is copied into the ...\SIEMENS\SICAM\SCC\PAS directory during installation.

In order to be able to use the WinCC script, proceed as follows:

- $\diamond$  Copy the WinCC script into the **PAS** directory of your WinCC project.
- $\diamond$  To customize the WinCC script, use the related process tags in the script editor.

# Activating redundancy

Proceed as follows to activate the redundant configuration:

- In the WinCC Explorer, right-click PAS Data Server and select Properties from the context menu.
   The Channel Unit Properties dialog opens.
- Click Properties.
   The Connection properties dialog opens.
- ♦ Click Properties.
   The PAS Connection dialog opens.

PAS Connection		×
SICAM PAS Configuration		
Connection parameter		
Connection type	V6 Redundancy	
	SICAM PAS address	port
SICAM PAS 1	192 . 168 . 48 . 101	10501
SICAM PAS 2	192 . 168 . 48 . 102	10501
Link parameter		
Test frame period [ms]	1000 (250 - 60000)	
	OK Abbrechen	Übernehmen

[pascc404a, 1, en_US]

Figure 14-2 Activating redundancy

- ♦ Select the **Redundant Connection** option.
- ♦ Enter the IP address of the second SICAM PAS Full Server.

The **ports** must match the ports parameterized in SICAM PAS.

The **Test frame period** must correspond to the Test frame period parameterized in SICAM PAS for SICAM PAS CC/SCC.

♦ Click **OK** to confirm your settings.

# 14.1.2 Redundant SICAM SCC System

A redundant system can consist of two SICAM SCC which run in parallel. Each SICAM SCC provides a SICAM PAS PROTOCOL SUITE connection to the SICAM PAS system.

The first SICAM SCC (e.g. WinCC1) is the **Master Server**, and the second one is the **redundant Partner Server**. Both connections are active in case of fault-free operation.

The SIMATIC WinCC redundancy package for data synchronization and for the control of the server redundancy must be installed on both SICAM SCC servers.



[Kanal_dll_1, 1, en_US] Figure 14-3

System with redundant SICAM SCC

# **Configuring SICAM PAS**

In SICAM PAS, you must add two DIPs to your project and configure them accordingly. Proceed as follows:

- ♦ To open SICAM PAS UI Configuration, click
   Start > Siemens Energy > SICAM > PAS > UI Configuration.
- $\diamond$  Create a DIP (e.g. PAS CC 1).
- ♦ Insert a **PAS CC/SCC application**, an **interface** and a **control center** for the DIP.
- ♦ The items of information to be used in SICAM PAS CC/SCC must be activated in the information mapping.

Pi Fi	SICAM SCC Redundancy   User logon dea le Edit Create View Tools Help	ctivated   Configuration -	Large		SIEMENS SICAM	– ■× PAS UI - Configuration
7	Configuration Mapping	Topology	Templates	Reports	Grid Co	odes
Configuration	SICAM SCC Redundancy Full Server	<ul> <li>SICAM SCC Redundan</li> <li>General parameters         <ul> <li>Name</li> <li>Description</li> <li>Compatibility key</li> </ul> </li> <li>Communication parameters         <ul> <li>SICAM SCC 1</li> <li>SICAM SCC 2</li> <li>Test frame period [ms]</li> <li>Topology assignment             <ul></ul></li></ul></li></ul>	cy > Full Server > Contro 42 neters 127.0 127.0 1000 SICAM	SCC > Interface > Cor I center 0.2 0.3	ntrol center	
		Onder SICAM SCC 2 you enter t     Error(s): 0 << Previo	he IP address of the SICA	M SCC server.		,

[sc_first_dip, 1, en_US] Figure 14-4 First DIP, PAS CC 1

- $\diamond$  Create the second DIP (e.g. PAS CC 2).
- ♦ Insert a **PAS CC/SCC application** and an **interface** for the DIP.

The interfaces include different interface addresses and compatibility keys. They are assigned by the system and cannot be modified. The compatibility key is automatically adapted upon each change of the interface parameters.

File E	dit Create \	n <b>cy Userlogondea</b> √iew Tools Help	ictivated   Configuration -	Large		S	IEMENS SICAM	I PAS UI	- Configurat	_∎× tion
۰۵ 🧡	nfiguration	Mapping	Topology	Templa	tes	Reports	Grid C	odes		
•			> SICAM SCC Redundan	cy > SCC2						
5 7 1	• *		<ul> <li>General parameters</li> </ul>							<b>^</b>
1 🗄 👻 🛅	SICAM SCC Redur	ndancy	Name		SCC2					
<u> </u>	Full Server	-11	Description							
Ť,	= EC 61850	Client	Computer name		DIP					
ŏ	▼ 1 0000 0000 00000 00000 0000000000000		System resources		COM Port:	0, Modem: 0, CP5613/14: 0				
	🖛 🏷 Interface	e	Type of system		Device Int	erface Processor (DIP)	-			
_	Conti	rol center	IP address 1		127.0.0.2					
·	Talscc		IP address 2							
	the Control	enter	Standby buffer timeout [s]	1	30					
			<ul> <li>Project settings</li> </ul>							
			Redundancy		No		-			
			(3) (1) Error(s): 0 << Previou	us Next>> 4						*

[sc_second_dip, 1, en_US] Figure 14-5 Second DIP, PAS CC 2

 $\diamond$  Copy the control center of the first DIP and insert the copy into the second DIP.

### **Exporting data**

To import the configured items of information into SICAM SCC, they must be exported from SICAM PAS UI - Configuration.

♦ Right-click Interface and select Export from the context menu.

The export function creates a PXD file in the selected directory. Afterwards, you can import this file into SICAM SCC using the SICAM PAS Wizard.

- $\diamond$   $\;$  Export the configuration data of the first DIP.
- $\diamond$  Export the configuration data of the second DIP.

# **Creating WinCC Projects**

Create a separate WinCC project on each of the 2 computers.

- ♦ Create a new WinCC project (e.g. PAS CC 1) on the first computer.
- ♦ Import the **PXD file** of the first DIP using the SICAM PAS Wizard.

The administrative tags imported from SICAM PAS have the project and interface ID as an extension of the tag name.

Tag Management - WinCC Configuration Studio					-	
File <u>E</u> dit <u>V</u> iew <u>H</u> elp	Tage [ SigamAdmin 10201	Find		0 -		
	ags [ SicamAdmin_1020 ]	Petertere				
I ag Management	Name	Data type	Length	For ^	El Selection	Tee
🕀 💝 Internal tags	1 ActivateOnlineConfig_1020	Unsigned 32-bit value	4	Dw	Object type	Tag
🖻 - 📙 SICAM PAS Protocol Suite	2 AlarmListFilter_1020	Unsigned 32-bit value	4	Dw		Activate
🖃 👖 PAS Data Server	3 CompKey_Ext_1020	Unsigned 32-bit value	4	Dw	Name	Activator
🖻 👫 PAS	4 ConnectionName_1020	Text tag 8-bit character set	128		ID	2000
	5 ConnectionState_1020	Unsigned 32-bit value	4	Dw	Data trino	Lincianor
- SI SCCCL20 IEC 61850 Client	6 ExecGI_1020	Unsigned 32-bit value	4	Dw	Longth	onsigned
- 8 ES1 SCCCI 20 IEC 61850 Client 61	7 ForceConnectionState_1020	Unsigned 32-bit value	4	Dw	Eerrent adaptation	DwordTo
ES1 SCCCI 20 IEC 61850 Client 61	8 InitiatorCategory_1020	Unsigned 32-bit value	4	Dw	AG Longth	A
	9 MSG_Ack_1020	Raw Data Type	0		Addross	VIDOOOO
	10 MSG_Queue_1020	Raw Data Type	0			100000
SicamAdmin_1020	11 MSG_Queue_DAF_1020	Raw Data Type	0		Communication driver	STCAM D
Structure tags	12 ProjectID_Ext_1020	Unsigned 32-bit value	4	Dw	Channel unit	DAS Dat
Hard PAS_Command	13 RedundancyMaster_1020	Unsigned 32-bit value	4	Dw	Connection	DAS
PAS_CommandFloat	14 🐹				Group	SicamAd
	15			E	E Linear scaling	Jicanina
	16				Linear scaling	[FT]
AS InformationFloat	17				AS value range from	
Hard PAS InformationInternal	18				AS value range to	
PAS InformationSInt	10				OS value range from	-
	20				OS value range to	
	20				E Limit Values	
	21				Low limit	
	22				High limit	
	23				Start value	0
	24				Substitute value	
	25				Use Substitute Value	
Tag Management	26			_	Substitute value at low limit	
11 Tug munugement	27			_	Substitute value at high limit	
Alarm logging	28				Substitute value as start value	
	29					
Tag Logging	30					
	31			-		
iii 🧰 🛄 🐠 👻				►		
teady NUM	Ge	erman (Germany)			Table: 13 Tags 100 % 😑 🗸	(+)

[pascc409, 1, en_US] Figure 14-6

WinCC Project 1

Marm logging - WinCC Configuration Studio			- D >	×
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp				
Alarm logging «	Message blocks Find	<del>،</del> م	🗐 Properties - Message blocks	»
Adarm logging       **         Messages       *         SICAM Message       *         SICAM Message pl/TR/FB       *         SICAM Message with Acknowledgment       *         SICAM Protection Message       *         SICAM Protection Message TR       *         SICAM Protection Message TR       *         SICAM Protection Message TR       *         System, requires acknowledgment       *         System, vithout acknowledgment       *         System blocks       *         System blocks       *         System blocks       *         Tag Management       *         Marm logging       *	Image     Message blocks Find       Used     Message block       1     Image       2     Image       3     Image       4     Daylight Saving / Standard T       5     Image       6     Image       7     Image       8     Class       9     Type       10     Controller/CPU Number       11     Tag       12     Archiving       13     Logging       14     Comments       15     Info Text       16     Loop in Alarm       17     Computer Name       18     User name       19     Priority       20     Class Priority	Number of charc           0           0           0           0           0           0           0           0           0           0           0           0           1           1           1           1           1           10           3	Properties - Message blocks     Selection     Object type Message blocks     Object name Message blocks	<i>"</i>
■ 👬 🏭 🐠 🛧 🔛 👻	21     ✓     Message Group       H     +     H     Message blocks	64 ¥		
Ready NUM	English (United States)	Table:	40 Message blocks   100 % 😑 🗸 🕂	)

[pascc411, 1, en_US]

Figure 14-7 Alarm Logging WinCC Project 1

♦ Close your WinCC project.

Create the redundant WinCC project via the Project Duplicator. It must be saved on a second computer.

- ♦ To start the Project Duplicator, click Start > SIMATIC > WinCC > Tools > Project Duplicator.
- ♦ Enter **PAS CC 1** as the source project.
- $\diamond$  Enter a name for the redundant WinCC project (e.g. PAS CC 2).
- ♦ Click **Duplicate**. The redundant WinCC project is now created.
- ♦ Call up the SICAM PAS Wizard via the redundant WinCC project.

The administrative tags must be connected to the other interface in the redundant WinCC project.

Import the PXD file of the second DIP. Only the names of the administrative tags are changed during this step.

SICAM P	AS Wizard 🛛
2	ATTENTION In the import data file the project ID or the HMI interface ID has changed.
	Possibly a different project will be imported. Check whether the selected file is the right one.
	Former Project ID -> new: 1 -> 1 Former HMI interface ID -> new: 5 -> 7
	Do you want to make the changes and continue with the update process?
	Yes No

[pascc408, 1, en_US]

Figure 14-8 SICAM PAS Wizard, Warning

♦ The SICAM PAS Wizard issues a warning. Click Yes in this dialog.

The project ID is not changed, and the HMI Interface ID is assigned the value 9.



[pascc410, 1, en_US]

Figure 14-9 WinCC Project 2

The modified process tags include the project and interface IDs of the second DIP as an extension of the tag name. They are linked to the redundant interface.

🍠 Ala	rm Logging - [Re	edundancy_PASCC1.MC	P]				
File E	dit View Message	es Tools Help					
	X B B 🔗	º 1 🔠 🎬 🦉 🦄	i ¶ <b>№</b>				
+	Message blocks Message classes		≞				
÷	Group messages Archive Configuration	on	System blocks	User text block	Process value blocks		
[	Number	Class	Туре	Priority		MessageTag	~
►	10000015	SICAM Message DI/TR/FB	Alarm_177	0		MSG_Queue_107	Ē
	10000019	SICAM Message DI/TR/FB	Alarm_177	0		MSG_Queue_107	
	10000020	SICAM Message DI/TR/FB	Alarm_177	0		MSG_Queue_107	
	10000023	SICAM Message DI/TR/FB	Alarm_177	0		MSG_Queue_107	
	10000024	SICAM Message DI/TR/FB	Alarm_177	0		MSG_Queue_107	
	10000032	SICAM Message DI/TR/FB	Alarm_177	0		MSG_Queue_107	~
							>
Ready			Engli	sh (United Stal	tes)		11.

[pascc412, 1, en_US]

Figure 14-10 Alarm logging WinCC Project 2

The new raw data tag is linked to the messages. The CompKey of the redundant interface is used. The modifications are documented in the trace window.

#### Synchronizing SICAM acknowledgment data

SIMATIC WinCC supports the synchronization of data between redundant servers. In order to ensure that the data of the SICAM SCC components can be synchronized between the redundant servers, the following prerequisite must be met:

For the **IX State Sync** application, the same rules apply for a SICAM RTU system as for a SICAM PAS system, see 14.5 IX State Sync Application.

# 14.2 Circuit Breaker and Disconnector

This section describes the **Circuit Breaker** and **Disconnector** SICAM graphic objects for SICAM SCC V7.02 or earlier. With SICAM SCC V8.00 or higher, they were replaced by SICAM graphic objects featuring more powerful functions. However, the old SICAM graphic objects can still be used. The new circuit breakers and disconnectors are described in *4.4 SICAM Switch Controls*.

The Circuit Breaker and the Disconnector are available as switching devices. They are stored in the Switching device objects folder under Controls in the SICAM graphic object library. These IndustrialX Controls already include typical functions.



# NOTE

If user-specific bitmaps, configured without absolute path, are used for display within the switching objects (**Bitmap** option), these are not displayed during runtime in WinCC V7.2 or higher on the Web Navigator Client .

The default search path is relative to the directory **Programs (x86)\Siemens\WinCC\WebNavigatorClient \bin**.

You can reference the used bitmaps via this path or store them in this location.

# **Graphical representation**

The SICAM graphic object library provides circuit breakers and disconnectors in five different representation modes:

Circuit breaker	View	Graphic
SICAM CB	in SICAM style	
DIN CB	based on DIN 42200	
IEC 445 CB	based on IEC 445	
LSA CB	based on LSA	
Bitmap CB	individual design	
Disconnector	View	Graphic
SICAM CB	in SICAM style	•
DIN CB	based on DIN 42200	

Disconnector	View	Graphic
IEC 445 CB	based on IEC 445	
LSA CB	based on LSA	
Bitmap CB	individual design	

# 14.2.1 Graphical Representation of Circuit Breakers and Disconnectors

Each circuit breaker and disconnector must be assigned several properties.

- $\diamond$  Double-click the graphic object.
  - The SICAM SCC CB/DIS Properties dialog opens.
- ♦ The properties can be found in the Style tab.

SICAM SCC CB/DIS Prop	oerties	:	×
Style TagConnection Type: Circuitbreaker Disconnector	Color Advanced Norm: SICAM DIN 42 200 IEC 445 LSA Bitmap Op	Synchronization About General: LineWidth: 2 pt ✓ Orientation: ● 0 Degrees ● 90 Degrees ● 180 Degrees ● 270 Degrees	
		OK Cancel Apply	

[pascc336, 1, en_US] Figure 14-11 Specifying the style

#### Туре

The Circuit Breaker or Disconnector types can be selected for the graphic object.

# Standard

The following five options are available for the representation of a graphic object:

- SICAM
- DIN 42200

- IEC 445
- LSA
- Bitmap

With the Bitmap style, specific diagrams can be displayed depending on the switch position.



# NOTE

If user-specific bitmaps, configured without absolute path, are used for display within the switching objects, these are not displayed during runtime in WinCC V7.4. The default search path is relative to the folder **Programs (x86)\Siemens\WinCC\bin**. You can reference the used bitmaps using this path or store them in this location.

# Line width

The **line width** of the graphic objects can be adjusted in steps from 1 to 11. Step 1 represents the smallest line width.

The adjustment of the line width is possible for all representation styles according to DIN 42200, IEC 445 and LSA.

### Orientation

For all representation styles apart from **Bitmap**, the orientation angles 0°, 90°, 180°, and 270° can be defined.

# 14.2.2 Tag Connection of the Circuit Breakers and Disconnectors

Each circuit breaker and each disconnector must be assigned tags.

- ♦ Double-click the graphic object.
  - The SICAM SCC CB/DIS Properties dialog opens.
- $\diamond$  ~ The interfacing to the process is defined in the Tag connection dialog.

SICAM S	CC CB/DIS Prope	erties							$\times$
Style	TagConnection	Color	Advanced	Synchro	nization	About			
Tag ir	nformation:								
SICA	M_PasV808_IEC6	1850_61	850IF_SIP_7	7SL87_LS	61_Steuer	rung_Be	efehl_r	Browse	
Tagio	:ommand:								
SICA	M_PasV808_IEC6	1850_61	850IF_SIP_7	7SL87_c_	LS1_Ster	uerung	Befeh	Browse	
Tagia	icknowledge blinki	ng:							
QuitE	llinking							Browse	
Toolti	ptext:				WinCC up	odate cy	/cle		
SICA	M SCC LS/TR				2 s		~		
					ОК		Cancel	Appl	у

[pascc337, 1, en_US] Figure 14-12 Tag connection

# **Tag information**

Click the **Browse** button next to the edit field. The **Tags** dialog opens. Select the corresponding tag from the list and click **OK** to confirm.

## Tag command

If a tag name Command related to a tag name Information is indicated in the SICAM PAS import data record, the command tab is determined automatically when the tag name information is selected. In this case, the tag name Command is entered into the **Command Direction** edit field.

To select a tag, proceed as described under Monitoring Direction.



# NOTE

If you do not want to use the stored functionality in command direction, delete the prespecified tag.

# Acknowledge tag for spontaneous blinking

You can keep the predefined **QuitBlinking** tag or select another tag.

Click the **Browse** button next to the edit field to select another tag. The **Tags** dialog opens. Select the corresponding tag from the list and click **OK** to confirm.

You can also assign a tag to several switching elements in order to form a group. Spontaneous blinking can be acknowledged simultaneously for all switching elements of the group.

### **Tooltip text**

Enter a text in the edit field. This text is displayed as **Tooltip** in the active project.

### WinCC update cycle

The **WinCC update cycle** of the tags can be adjusted in time intervals from 250 milliseconds to one hour. Furthermore, the setting **For change** is possible. 2 seconds is the default setting.

# 14.2.3 Colors of Circuit Breaker and Disconnector

# Switch position

The color of the graphic object in normal state depends on its value. A specific color is set by default for each individual value. However, the color can also be freely selected from a color palette.

In the **Color** tab, you can assign colors for the individual switch positions and states of the Circuit Breaker/ Disconnector.

♦ Double-click the graphic object.

The SICAM SCC CB/DIS Properties dialog opens.

Select the Color tab.

SICAM SCC CB/DIS Properties  $\times$ Style TagConnection Color Advanced Synchronization About State: Value: ON. Not topical OFF PAS not ok Disturbed 00 Bay blocked Disturbed 11 Substituted Telecontrol blocked Background OK Cancel Apply

[pascc339, 1, en_US]

Figure 14-13 Assigning colors

The following colors are predefined for the graphic object:

Table 14-1	Switch	position
------------	--------	----------

Value	Color
ON 10, value = 2	Red
OFF 01, value = 1	Green
Intermediate position 00, value = 0	Yellow
Disturbed 11, value = 3	Yellow

The form of the graphic object in representation styles in accordance with DIN 42200, IEC 445 and LSA depends on the value.

The following forms are predefined for the graphic object in the representation style in accordance with DIN 42200 and IEC 445:

Table 14-2 In accordance with DIN 42200 and IEC 445

Value	Form
ON 10, value = 2	Switch closed
OFF 01, value = 1	Switch open
Intermediate position 00, value = 0	Switch on/off dashed
Disturbed 11, value = 3	Switch on/off dashed

Graphic object forms in the representation style in accordance with LSA:

Table 14-3 In accordance with DIN 42200 and IEC 445

Value	Form
ON 10, value = 2	Filled
OFF 01, value = 1	Not filled

Value	Form
Intermediate position 00, value = 0	Half filled
Disturbed 11, value = 3	Half filled

A red cross is indicated for values which are not indicated in the tables (e.g. Value=4).

### State

The switch status is represented with small, colored rectangles next to the switch. A default color is predefined for each status. The color can also be freely selected from a color palette.



#### [pascc340, 1, --_--]

Figure 14-14 Switch with switch status

The predefined colors of the rectangles depend on the status:

Table 14-4 Switc	ch status	
------------------	-----------	--

Status	Color	Explanation
Not topical	Cyan (turquoise)	The device state is not topical.
PAS not ok	Dark cyan (teal)	Connection between SICAM SCC and SICAM PAS disturbed.
Bay blocked	Red	Messages from this bay are no longer transmitted to SICAM PAS.
Substituted	Blue	The switch position was set manually because there is no connection to the primary system.
Telecontrol blocked	Red	Messages from this bay are no longer transmitted to the telecontrol center.

#### Background

The background color of the graphic object can be individually defined. Gray is the default color.

# 14.2.4 Advanced Properties of the Circuit Breaker and Disconnector

In the Advanced tab, you assign additional circuit breaker/disconnector properties.

- ♦ Double-click the graphic object.
  - The SICAM SCC CB/DIS Properties dialog opens.
- ♦ Select the Advanced tab.

14.2 Circuit Breaker and Disconnector

SICAM SCC CB/DIS Properties				Х
Style TagConnection Color	Advanced	Synchronization	About	
🗹 Enable State Dialog		Enable sponta	aneous blinking	
☑ 3-D Style		🗹 Enable setpoir	nt blinking	
Fix Dialog Position		Enable SET =	ACTUAL	
Position in pixel:		V Use integrated	d dialog-boxes	
X: 100 Y: 100		Write comman	nd output	
Command execution timeout:		Command mod	del 'Select before operate'	
5 s		Send QoC wit	h Command Value	
Authorization level:		not synchronized non-interlocked	Preset Visible in RT	
		ОК	Cancel Apply	

[pascc342, 1, en_US]

Figure 14-15 Advanced properties

During the connection to **SICAM RTU** or **IEC 61850 devices**, commands must be sent with Qualifiers of Command (QoC) when commands are issued. To activate the function, select **Send QoC with Command Value** in the Properties dialog of the switching device. Afterwards you can set the values to be sent in the Preset section. If you need the possibility to display and change the values in the switching dialog at runtime, select **Visible in RT**.

#### **Enable state dialog**

The display of status information by clicking with the right mouse button can be enabled or disabled.

# 3-D style

If this option is selected, circuit breakers and disconnectors can simulate a three-dimensional effect when clicked.



# NOTE

The 3-D effect highlights the selected icon. This effect is required for operation without a mouse.

#### Fix dialog position

The runtime dialogs can be anchored at a specified position on the display.

#### **Command execution timeout**

In the **command execution timeout** box, you must specify in seconds how long the system shall wait for the successful execution of a command. When this time interval has elapsed, the command is terminated and the negative command termination is logged.

#### Authorization level

Enter the **Authorization level**. For example, select the value 3 for authorization level 3. For more detailed information regarding the setting and assignment of user authorizations, refer to 3.8 Setting up User Authorizations.



## NOTE

The line number (e.g. 3) corresponds to the authorization level in the object properties of the ActiveX Controls.

#### Enable spontaneous blinking

Spontaneous blinking can be enabled or disabled.

The circuit breaker or disconnector **blinks spontaneously** if the value of the assigned tag changes and if **Spontaneous** has been entered as cause.

# Enable setpoint blinking

Setpoint blinking can be enabled or disabled.

When the command is issued, the graphic object starts to **blink** in the defined state as soon as the target switching direction (ON or OFF) has been selected. The blinking stops when the command is terminated or aborted, i.e. in the following cases:

- after the abortion of the command output
- when the monitoring time for the command output has expired
- if **Command Termination** was entered as the cause in the feedback message

### Enable SET = ACTUAL

Switching in the represented ACTUAL state can be enabled or disabled. Select this option to enable the switching direction independently of the switch position. For example, another switch-on command can be issued for a switch which has already been switched on.

#### Use integrated dialog

The display of switching dialogs during runtime can be enabled or disabled.

### Write command output

Deselect **Write Command Output** to prevent writing to the defined tag. In this case, you must define actions for the command output via the Object Properties, Events tab (see 14.2.9 Defining Object Properties).

#### Command model 'Select before operate'

A switching operation can be executed in two steps.

A select command is issued before the actual switching command. To issue the switching command, a positive acknowledgment must have been received for the select command.

# 14.2.5 Controlling Synchronized Switching for the SICAM PAS Connection

In the **Synchronization** tab, you can define the control (switching device object) for synchronized switching (e. g. in order to connect two busbars).

- ♦ Double-click the graphic object.
   The SICAM SCC CB/DIS Properties dialog opens.
- ♦ Select the Synchronization tab.



# NOTE

In case of a connection to a SICAM PAS station, additional synchronization functions can only be used with the IEC 61850 and SINAUT LSA ILSA communication protocols.

## Synchronization functions with IEC 61850

Eigenschaften von SICAM SCC CB/DIS	×
Style TagConnection Color Advanced Synchronization About	
Synchronization model: IEC61850 ~	
Tagname information 'Sync not effective'	
Station_South_10kV_Bay_2_7SJ63_cb_switch_unsynch	Browse
Tagname command 'Sync not effective'	
Station_South_10kV_Bay_2_7SJ63_c_cb_switch_unsych	Browse
OK Abbrechen	Übernehmen

[pascc341, 1, en_US]

Figure 14-16 Define synchronization

# • Synchronizing model

With the communication protocol **IEC 61850**, the user can specify whether circuit breakers shall be controlled in synchronized or unsynchronized mode. If unsynchronized switching is specified, further settings or dynamic display properties must be defined. Advanced control dialogs are displayed during runtime, and the user can determine how the switching operation is to be executed.

# • Command execution timeout

In the **Command execution timeout** box (**Advanced** tab), you must specify in seconds how long the system shall wait for the successful execution of a command. When this time interval has elapsed, the command is terminated and the negative command termination is logged.

# • Changeover Synchronized – Not Synchronized Switching tag name information

The tag to be indicated includes information on whether the device synchronization is **active** or **inactive**. This tag must always be indicated.

• Changeover Synchronized – Not Synchronized Switching tag name command marker command A tag name command can be indicated. This tag does not need to be defined if the synchronization function must not be modified during runtime.

#### Synchronization functions with SINAUT LSA ILSA

Eigenschaften von SICAM SCC CB/DIS	×
Style TagConnection Color Advanced Synchronization About	
Synchronization model: ILSA V	
Tagname command 'measurement interrogation'	
Station_South_10kV_Bay_2_7SJ63_c_start_meas Browse	]
Tagname command (not synchronized)	
Station_South_10kV_Bay_2_7SJ63_c_cb_switch_unsych Browse	]
OK Abbrechen Übernehn	ien

[pascc341a, 1, en_US]

Figure 14-17 Define synchronization

#### • Synchronizing model

With the **SINAUT LSA ILSA** communication protocol, the user can specify whether circuit breakers shall be controlled in synchronized or unsynchronized mode. If synchronized switching is specified, further settings or dynamic display properties must be defined. Advanced control dialogs are displayed during runtime and the user can determine how the switching operation shall be executed.

#### • Command execution timeout

In the Command execution timeout box (Advanced tab), you must specify in seconds how long the system shall wait for the successful execution of a command. When this time interval has elapsed, the command is terminated and the negative command termination is logged.

#### • Tag name command 'measurement interrogation'

In the **Tag name command 'measurement interrogation'** box, define the tag name command which triggers a measurement in the synchronization unit. The measured values are updated; no switching operation is performed.

#### Tag name command (not synchronized)

Define the tag name command for unsynchronized switching in the **Tag Name Command (not synchronized)** entry field. If this tag is not defined, unsynchronized switching is not possible.

# 14.2.6 Synchronized Switching for Direct Connection of Devices

If devices are directly connected via the SICAM IEC COMMUNICATION SUITE, the Qualifiers of Command (QoC) are included in the command telegrams. These QoC are defined in the **Advanced** tab.

14.2 Circuit Breaker and Disconnector

SICAM SCC CB/DIS Properties				Х
Style TagConnection Color	Advanced	Synchronization	About	
<ul> <li>Enable State Dialog</li> <li>3-D Style</li> <li>Fix Dialog Position Position in pixel:</li> <li>X: 100 Y: 100</li> </ul>		<ul> <li>Enable sponta</li> <li>Enable setpoir</li> <li>Enable SET =</li> <li>Use integrated</li> <li>Write comment</li> </ul>	nneous blinking ht blinking ACTUAL d dialog-boxes nd output	
Command execution timeout: 5 s Authorization level:		Command mod Send QoC with not synchronized	del 'Select before operate' h Command Value Preset Visible in RT	
0		non-interlocked		
		ОК	Cancel Apply	

[QoC_einstellen, 1, en_US]

Figure 14-18 Defining Qualifiers of Command (QoC)

The Qualifiers of Command can be defined with the following object properties in the object properties of the switching commands:

Preset

With this property you can define which Qualifiers of Command are preset.

• Visible in RT

With this property you can define which Qualifiers of Command are displayed in the switching dialog during Runtime and can be modified during the switching operations.

# 14.2.7 Runtime Dialogs of Circuit Breakers and Disconnectors

Dialogs are available for performing switching operations, for status display, to acknowledge blinking and for synchronization.

To call up these dialogs during runtime, click the related graphic object.

# 2-step switching operation

Click the graphic object to open the dialog for a switching operation.

SICAM SCC	LS/TR		
			^
			$\vee$
Switching			
ON		OFF	
_	Consol	_	
	Lancel		

[pascc501, 1, en_US]

Figure 14-19 Switching dialog without Qualifier of Command

The dialog below must be used for switching operations with SICAM RTUs and IEC 61850 devices and for control via the SICAM IEC COMMUNICATION SUITE.

SICAM SCC LS/TR	
	^
	$\checkmark$
Qualifier of Command	
not synchronized	
non-locked	
Switching	
ON OFF	
Cancel	

[pascc501_1703, 1, en_US]

Figure 14-20 Switching dialog without Qualifier of Command

This dialog has been complemented by 2 Qualifier of Command (QoC) setting options. Controls (switching device objects) which already support this Qualifier of Command are available in the SICAM graphic objects library, e.g. IEC 445 LS with QoC.

You can define the parameters of the **Select before operate** function via the properties of the control in the Graphics Designer, see 14.2.4 Advanced Properties of the Circuit Breaker and Disconnector.

If bay devices are connected based on the IEC 61850 protocol, the Select command is transmitted when the user clicks the **ON** or **OFF** button. Otherwise, the confirmation dialog opens directly (see *Figure 14-22*). The **ON** and **OFF** buttons are disabled until a confirmation has been received.

14.2 Circuit Breaker and Disconnector

SICAM SCC LS/T	R
Select command is	running 🔺
	~
Switching	
ON	OFF
Car	cel

[pascc505, 1, en_US]

Figure 14-21 Switching dialog, Select command is running

The select command can receive a positive or negative acknowledgment. Depending on the acknowledgment, one of the following dialogs opens.

ON	
Select positiv!	^
	~
Confirm	
Cancel	

[pascc506, 1, en_US]

Figure 14-22 Switching dialog, selection is active

The check resulted in a positive acknowledgment. The actual switching command can be issued by clicking the Confirm button.

SICAM SCC LS/T	R
Select command v	was refused! 🔥 🔨
	~
Switching	
ON	OFF
Car	ncel

[pascc507, 1, en_US]

Figure 14-23 Switching dialog, the selection was rejected

The actual switching command cannot be issued. The switching operation must be aborted.

# Synchronization functions

Based on the communication protocols IEC 61850 and SINAUT LSA ILSA, different functions for synchronized switching can be performed by means of dialog extensions. The execution of the switching operation during runtime depends on the individual protocol. For this reason, a distinction is made between these protocols in the following sub-sections.

Synchronized switching is supported by further communication protocols (e.g. IEC 60870-5-101 Master). In this context, however, the dialog extensions are not used. For more detailed information, refer to the protocol descriptions.

The extended synchronization dialog is only shown if a communication protocol (not the option -nothing-) was selected from the drop-down list box Synchronization Model in the SICAM SCC CB/DIS properties dialog.

# Synchronization functions with IEC 61850

This section describes the execution of a synchronized switching operation based on the IEC 61850 communication protocol.

Click the graphic object to open the dialog for a synchronized switching operation.

SICAM SCC LS/TR	
	^
	4
Switching	
Sync. ON	d.
Unsync. ON	1
Consel on showing the	d,
Cancel synchronization	
Synchronization feature	
🔘 synchronized	
<ul> <li>unsynchronized</li> </ul>	
Start meas Stop meas	
otal mode	
Cancel	

[pascc508, 1, en_US]

Figure 14-24 Switching dialog for synchronized switching, synchronization function disabled

For synchronized switching, the Sync effective option must be selected. This selection opens the confirmation dialog.

Activ	ate synchronization	
		^
		Ŷ
	Confirm	
	Cancel	

[pascc509, 1, en_US]	
Figure 14-25	Dialog for Confirmation

Click Confirm to send a single command with the value OFF to the tag name command Sync not effective.

At the same time, all buttons are deactivated until a command feedback is received.

SICAM SCC LS/TR
Command to 'SyncEffective' was 🔥 sent
1
Switching
Sync. ON
Unsync. ON
Cancel synchronization
Synchronization feature
<ul> <li>synchronized</li> </ul>
<ul> <li>unsynchronized</li> </ul>
Start meas Stop meas
Cancel

[pascc510, 1, en_US]

Figure 14-26 Switching dialog for synchronized switching, synchronization function deactivated

As soon as a message has arrived via the tag name information **Sync not effective**, the **Sync ON** button is active and can be clicked.

SICAM SCC LS/TR	
	^
	~
Switching	_
Sync. ON	
Unsync. ON	
Cancel synchronization	
Synchronization feature	
synchronized	
Start meas Stop mea	S
Cancel	

#### [pascc511, 1, en_US]

Figure 14-27 Switching dialog for synchronized switching, Sync ON button activated

Clicking the Sync ON button now initiates synchronized switching. The switching command is issued as usual:

♦ Click Sync ON.

The control blinks in the setpoint status and the confirmation dialog opens.

Click Confirm.
 The command is output.

This dialog remains open until the synchronized switching operation has been completed or aborted.

#### Synchronization functions with SINAUT LSA ILSA

This section describes the execution of a synchronized switching operation based on the SINAUT LSA ILSA communication protocol.

Click the graphic object to open the dialog for a synchronized switching operation.

SICAM SCC LS/TR	
	^
	$\sim$
Switching	
Sync. ON	e)
Unsync. ON	
Cancel synchronization	
Synchronization feature	
<ul> <li>synchronized</li> </ul>	
<ul> <li>unsynchronized</li> </ul>	
Start meas Stop mea	IS
Cancel	

[pascc508a, 1, en_US]

 $\diamond$ 

Figure 14-28 Switching dialog for synchronized switching, synchronization function disabled

# The **Unsynchronized** option deactivates the **Sync ON** button. Synchronized switching is not possible. The **Synchronized** option activates the **Sync ON** button.

Clicking the Sync ON button now initiates synchronized switching. The switching command is issued as usual:

- $\diamond \quad \ \ {\rm Click} \ {\rm Sync} \ {\rm ON} \ {\rm button}.$ 
  - The control blinks in the setpoint status and the confirmation dialog opens.
  - Click **Confirm**.

The command is output.

This dialog remains open until the synchronized switching operation has been completed or aborted. If a command with synchronization has been transmitted, the synchronization can be aborted by clicking on **Cancel synchronization**. Afterwards, the control sends a cancel command to the tag name command. Click **Start Meas** to issue a measurement trigger to the synchronization unit. The measured values are updated without performing a switching operation.

# Status

The status dialog can be opened by clicking with the right mouse button, provided that the status display has been activated in the Properties dialog.

SICAM SCC LS/TR	
	^
	v
PAS not ok	
Bay blocked	
Not topical	
Telecontrol blocked	
Substituted	
Substitute	
Cancel	
[pascc503, 1, en US]	



The status is indicated by a tick in the corresponding checkbox. Click **Substitute** to open the dialog for manually updating a switch position (see 14.2.8 Substituting the Switch Position).

## Acknowledge blinking

Click a blinking graphic object to open the **Acknowledging blinking** dialog.

SICAM SCC LS/TR		
State or value changed!		
	~	
Acknowledge		
This	All	
Cancel		

[pascc504, 1, en_US]

Figure 14-30 Acknowledge Blinking

Click This to acknowledge a status change or a spontaneous alarm for this switch.

Click **All** to use the **Tag Acknowledge Blinking** (under Properties) for acknowledging. All IndustrialX controls linked to this tag are acknowledged.

# 14.2.8 Substituting the Switch Position

SICAM SCC CB
🗇 Dist 00
OFF
🔘 ON
🔘 Dist 11
Substitute
Cancel

[pascc503a, 1, en_US]

Figure 14-31 Substituting the Switch Position

In this dialog, you defined how to substitute the switch position. Click **Substitute** to open the Confirm dialog. Click the **Confirm** button to execute the substitution.



# NOTE

New structure elements are required for the substitution. To continue to use projects from SICAM PAS CC Version 5.x, these projects must be converted first (see *10 Different SICAM PAS Versions*).

# 14.2.9 Defining Object Properties

The **Object properties** dialog comprises the **Properties** and the **Events** tabs. The following section describes certain parameters from these tabs.

Proceed as follows to open the **Object properties** dialog:

- ♦ Right-click the graphic object.
- $\diamond$  Select **Properties** in the context menu.

The Object properties dialog opens.

## **Properties tab**

Properties Events						
PCCIXCtrl	Attribute	Static	Dynamic	Update Indir		
Geometry	LanguageID	1031	Q			
Miscellaneous	tagname	Default tagname information	Q			
Control Properties	tagnameCMD	Default tagname command	Q			
	tagnameACK	QuitBlinking	Q			
	Tooltiptext	SICAM SCC LS/TR	Q			
	ColorON		Q			
	ColorOFF		Q			
	ColorDISTURBED00		Q			
	ColorDISTURBED11		Q			
	ColorBACKGROUND		Q			
	TagCycleTime	4	Q			
	LineWidth	2	Q			
	Norm	2	Q			
	PaintDirection	0	Q			
	PermissionLevel	0	Q			
	Efect3D	Yes	Q			
	PicOn		Q			

[pascc512, 1, en_US]

Figure 14-32 Object properties, Properties tab

The following table provides a list of certain important object properties of the circuit breakers/disconnectors.

, , , ,

Object properties	Meaning
PermissionLevel	Assigns a permission level for the IndustrialX Control. Click the control to compare this value with the permission level in SIMATIC WinCC and to disable or enable operator actions.
EnableSwitching	This property generally enables or disables switching. Example of use: Enabling user-defined switching between several workstations.
LabelButton	All properties whose name starts with Label serve for the labeling of indi- vidual buttons.
UserStringID	This property can be used to display a text which the user has freely defined from a selection of default texts. The texts must be saved in the text files for language setting. The value of UserStringID corresponds to the number of the text in the text file. If the UserStringID has the value zero, no additional text is displayed.
Timeout	This property defines the time in seconds after which the command execu- tion is aborted by SICAM PAS if no feedback is returned from the process. This value can also be modified in the <b>Advanced</b> tab.
InputValue1	Input points for topological coloring.
InputValue2	
TOPOColorINVALID	This value defines the default color for lines in the INVALID state. It is forwarded to the related connectors if the graphic object is in the INVALIFD state. Input points for topological coloring.

Object properties	Meaning
TOPOColorOFF	Default value for defining the color in case of topological coloring. This value is transferred to the corresponding connectors if the graphic object is in the OFF status.
EnableBlinkingOnNeg Confirm	If a switching command receives a negative acknowledgment (i.e. CO- is returned), the switching device object switches from command blinking to fast blinking in order to indicate that an abnormal event has occurred.
	The default value is <b>Yes</b> . The switching device object does not blink fast if this parameter has been set to <b>No</b> . The switching device object changes to the actual position after a negative acknowledgment; command blinking is terminated.

# **Events tab**

Object Properties				
Properties Events				
Control Properties	Execute on	Action		
Focus	Clicked	4		
Object Events     Object Events     Geometry     Miscellaneous	OnButtonON	4		
	OnButtonOFF	4		
	OnButtonEXECUTE	4		
	OnButtonSYNC_ON	4		
	OnButtonCANCELSYNC	4		
	OnActivateSYNCFUNC	4		
	OnDectivateSYNCFUNC	4		
	OnOutput1	4		
	OnOutput2	4		
	OnILSAStartMes	4		
	CommandResponse	4		
	OnILSAStopMes	4		
	OnButtonSubstitute	4		
🔲 Object Properties 🛛 🗠	ags 📃 Output Window	Dynamic Wizar		

[pascc513, 1, en_US]

Figure 14-33 Object properties, Events tab

The IndustrialX Control triggers the events listed in the table.

The name of the tag name command and the name of the tag name information are assigned to the **OnButton...** events in the parameter list.

These events are used for a switch with C script (see 14.2.10 Circuit Breaker/Disconnector with C Script).

Object Event	Meaning
Clicked	This event is triggered by clicking on the IndustrialX Control.
OnButtonON	This event is triggered by clicking the <b>ON</b> button in the switching dialog.
OnButtonOFF	This event is triggered by clicking the <b>OFF</b> button in the switching dialog.
OnButtonEXECUTE	This event is triggered by clicking on <b>Confirm</b> in the switching dialog.
OnButtonSYNC_ON	This event is triggered by clicking the <b>Sync ON</b> button for synchronous switching in the switching dialog.

Object Event	Meaning
OnButtonCANCELSYNC	This event is triggered by clicking the <b>Cancel Synchronization</b> button in the switching dialog for synchronous switching.
OnActivateSYNCFUNC	This event is triggered by activating the <b>Sync Effective</b> option under <b>Synchronization Feature</b> in the switching dialog for synchronous switching.
OnDeactivateSYNCFUNC	This event is triggered by activating the <b>Sync Not Effective</b> option under <b>Synchronization Feature</b> in the switching dialog for synchronous switching.
OnOutput1 OnOutput2	This event is triggered if a value change has occurred on <b>InputValue1</b> or <b>InputValue2</b> in the <b>ON</b> position.
OnILSAStartMes	This event is triggered by clicking the <b>Start Meas</b> button in the switching dialog for synchronous switching.

# 14.2.10 Circuit Breaker/Disconnector with C Script

The default circuit breakers/disconnectors feature a predefined command output mechanism for issuing pulse switching commands. The pulse duration cannot be defined.

# CB/DIS with C script

The graphic objects **CB/DIS with C Script** and **CB/DIS with CScript**, **SBO and QoC** are available in addition to these circuit breakers/disconnectors. The integrated command output mechanism of these objects is disabled and emulated by means of C scripts. These C scripts can be customized to meet specific requirements. The graphic object **CB/DIS with C Script** is provided for use with SICAM PAS connection, the graphic object **CB/DIS with CScript**, **SBO and QoC** for use with direct connection to SICAM RTU and IEC61850 devices. For example, you can perform the following actions using the **CB/DIS with C Script** and **CB/DIS with CScript**, **SBO and QoC** graphic objects:

- link the command execution to a condition
- check for an interlock prior to command execution
- check the switching authority conditions prior to command execution

# Example

The example below illustrates a C script for a command execution subject to a condition. To customize the predefined C script:

- ♦ Open the object properties of the CB/DIS graphic object with C script.
- ♦ In the Events tab, click Object Events.
- In the OnButtonON row, right-click the flash icon. Select C Action from the context menu.
   The C script is displayed.

```
14.2 Circuit Breaker and Disconnector
             #include "apdefap.h"
             void OnButtonON(char* IpszPictureName, char* IpszObjectName, char* tagCommand, char* tagInformation)
             //WINCC:TAGNAME_SECTION_START
             // svntax: #define TagNameInAction "DMTagName"
             // next TagID : 1
// WINCC:TAGNAME_SECTION_END
             //WINCC:PICNAME_SECTION_START
             // syntax: #define PicNameInAction "PictureName"
             // next PicID : 1
             //WINCC:PICNAME_SECTION_END
            long PCC_CMD_VALUE_ON = 2;
long PCC_CMD_VALUETYPE_IMPULSBEFEHL = 14;
long PCC_CMD_CAUSE_BF = 19;
             long STRING_LENGTH
                                          = 128^{\circ}
                   *
                           tagname:
             char
             extern BOOL g_debug;
             BOOL bEnableCommandExecution = FALSE;
                 ableCommandExecution = GetTaqBit("MyEnableCom
                                                                     andExecutionTa
                  nableCommandExecution == TRUE )
                    // Allocate char-memory
                   tagname = malloc (STRING_LENGTH);
                   //Write command value
                   memset (tagname, 0, STRING_LENGTH);
                   strcpy(tagname, tagCommand);
                    streat (tagname, ".Value");
                   SetTagDWord(tagname, PCC_CMD_VALUE_ON);
                                                                       //Return-Type :BOOL
                   // Write command_valuetype
                   memset (tagname, 0, STRING_LENGTH);
                    strcpy(tagname, tagCommand);
                    strcat (tagname, ".Valuetype");
                   SetTagDWord(tagname, PCC_CMD_VALUETYPE_IMPULSBEFEHL); //Return-Type:BOOL
                   //Write.command_cause
                   memset (tagname, 0, STRING_LENGTH);
                    strcpy(tagname, tagCommand);
                    strcat (tagname, ".Cause");
                   SetTagDWord(tagname, PCC_CMD_CAUSE_BF);
                                                                       //Return-Type :BOOL
                   free (tagname);
                   if (g_debug == TRUE) MessageBox ( NULL, "OnButtonOn clicked", "PASCC IX Schaltobjekt", MB_OK | MB_SYSTEMMODAL );
                     do nothina
             [pascc514, 1, -- --]
             Figure 14-34
                              C script OnButtonON, graphic object CB/DIS with Script
             ♢
                  Insert the selected rows into the C script.
                   The MyEnableCommandExecutionTag WinCC tag must include the condition for command execution.
                  Close the C script.
             \diamond
```

# 14.2.11 Indirect Addressing

The description in this section applies for IndustrialX Controls (Circuit Breakers/Disconnectors and Bay Overview) in SICAM PAS CC V5.0 and SICAM SCC V7.01.

#### Indirect addressing

Indirect addressing can be used with the attributes tagname, tagnameCMD, tagnameACK, tagnameSync, and tagnameSyncCmd.

The term "indirect addressing" signifies that the name of the SICAM tag is transferred in a string tag. In the WinCC Object properties dialog, connect an internal string tag (e.g. TagnamePlaceholder) which contains the name of the process tag during runtime and insert a & character as prefix of the tag name (e.g. &TagnamePlaceholder). The control (switching device object) then interprets the tag as a string tag for indirect addressing. During runtime, the string tag must contain the name of the process tag without extension (e.g. .Value).

Parameters for indirect addressing can be defined in the following dialogs:

- Object properties
- SICAM SCC CB/DIS properties

To specify indirect addressing in the **Object properties** dialog:

♦ Enter the name of the string tag in the **Static** column.

1	Properties Events To	exts Animation				
	SICAMSwitchCtrl	Attribute	Static	Dynamic	Update	Indir
	Geometry	LanguagelD	1031	Q		
	Miscellaneous	tagname	SICAM_PasV808_IEC61	Q		
	Control Proper	tagnameCMD	SICAM_PasV808_IEC61	Q		
		tagnameACK	QuitBlinking	Q		
		Tooltiptext	SICAM SCC LS/TR	Q		
		ColorON		Q		
		ColorOFF		Q		
		ColorDISTURBED00		Q		
		ColorDISTURBED11		Q		
		ColorBACKGROUND		Q		
		TagCycleTime	4	Q		
	< >	LineWidth	2	$\square$	I	
E	Object Properties	📹 Tags 📃 Output Window 🔓 Library	🕒 SVG library < 🔇 Dynamic Wizard			

[pascc516, 1, en_US]

Figure 14-35 Object properties, defining indirect addressing

Indirect addressing is also possible when using a server or tag prefix. The prefixes cannot be suppressed in case of indirect addressing, see 14.2.12 Addressing Using Tag and Server Prefixes. For more detailed information, refer to the WinCC Information System, Using Tag and Server Prefixes section. To define indirect addressing in the SICAM SCC CB/DIS properties dialog:

♦ Enter the names of the string tags in the entry fields for the tag names in the **Tag connection** tab.

SICAM SCC CB/DIS Properties × TagConnection Style Color Advanced Synchronization About Tag information: &TagnamePlaceholder Browse Tag command: Browse Tag acknowledge blinking: QuitBlinking Browse Tooltiptext: WinCC update cycle SICAM SCC LS/TR 2 s OK Cancel Apply

[pascc517, 1, en_US]

Figure 14-36 Properties of SICAM SCC CB/DIS, defining indirect addressing



# NOTE

In the SICAM SCC CB/DIS properties dialog, the Browse button cannot be used because string tags are filtered in the selection dialog that opens.

The indirect addressing is evaluated upon the start of the IndustrialX Control. The string tag must therefore include the name of the SICAM tag before the WinCC diagram is opened.

# 14.2.12 Addressing Using Tag and Server Prefixes

SIMATIC WinCC provides various options for the definition and structuring of tags. For a diagram window, you can assign a **tag prefix** which is placed in front of all tags used in the corresponding diagram.

In a multi-user system, integrated diagrams can be stored on any server. The server is indicated either directly when integrating a diagram using the **server prefix** or assigned later via the object properties of the diagram window. Using the server prefix, tags can also be requested from other servers.

# Addressing using a tag prefix in a diagram window

Using the **Tag prefix** attribute, you can define the character string which is placed in front of all tags included in the diagram window object.

The tag prefix only applies to tags of the diagram window object; it does not apply to identical tags in the higher-level window which includes the diagram window.

To define the parameters of the tag prefix:

- ♦ Open the diagram window object properties.
- ♦ For the Tag prefix attribute, enter the prefix text.

1	Object Properties							
ĺ	Properties Events T	exts Animation						
	Picture Window Geometry Miscellaneous	Attribute Scroll Bar Position X Scroll Bar Position Y	Static 0 0	Dynamic O O	Update	Indir		
		Scaling Factor Tag Prefix Server Prefix Header	100 SICAM_PAS_61850_7SJ	8 8 9 9				
		Menu/Toolbar Configuration Independent Window Window Mode Monitor Number Defensed micture change target	No Default 1	Ŷ				
	Dbject Properties	Tags Output Window	SVG library SVG library	¥				

[tagprefix_1, 1, en_US]

Figure 14-37 Defining tag prefix parameters in the diagram window

The properties of the Control, e.g. a circuit breaker, are defined as follows:

SICAM SCC CB/DIS Properties	×
Style TagConnection Color Advanced Synchronization About	
Tag information:	
Control_Q0_1_Position	Browse
Tag command:	
c_Ctrontrol_Q0_1Positioon	Browse
Tag acknowledge blinking:	
QuitBlinking	Browse
Tooltiptext: WinCC update cycle	
Q0 without hierarchy path 2 s ~	·
OK Can	cel Apply

[tagprefix_2, 1, en_US]

Figure 14-38 Defining Control property parameters

Sample parameterization:

- Tag prefix of the diagram window: SICAM_PAS_61850_7SJ63_
- Tag name monitoring direction of the Control: Control_Q0_1_Position

Result:

In the diagram window, the control requests the Control_Q0_1_Position tag. If the diagram window is assigned the SICAM_PAS_61850_7SJ63_ tag prefix, the SICAM_PAS_61850_7SJ63_Control_Q0_1_Position tag is requested.

## Addressing using a server prefix in a diagram window

Using the **Server prefix** attribute, you define in a multi-user system on which server the diagram to be represented in the diagram window is stored.

To define the server prefix parameters:

- ♦ Open the diagram window object properties.
- ♦ Enter the prefix text for the Server prefix attribute.

Object Properties				? 🛛
Picture Window	Picture Window1			~
Properties Events				
😑 Picture Window	Attribute		Static	Dynamic 🔼
Geometry Miscellaneous	Scaling Factor Tag prefix	100		Ş
	Server prefix	Server_1		$\hat{\Sigma}$
	Heading Menu/Toolbar configuration			Š
	Independent window	No		
	Window mode	Default		
	Monitor number	1		~
	<			>
	, .			

[serverprefix, 1, en_US]

Figure 14-39 Defining the server prefix in the diagram window

### Requesting tags without a prefix

The example below shows how to suppress a tag prefix.

You want to use the **QuitBlinking** tag without a prefix. In a multi-user system or for use in diagram windows, the server prefix or the tag prefix is always placed in front of the tag name. To use the **QuitBlinking** tag without a prefix, you can disable the prefix using the following tag addenda.

- **@NOTP::** disables the tag prefix
- @NOSP:: disables the server prefix
- **@NOP::** disables both the server prefix and the tag prefix
| SICAM SCC CB/DIS Properties                              | ×      |
|----------------------------------------------------------|--------|
| Style TagConnection Color Advanced Synchronization About |        |
| Tag information:                                         |        |
| Control_Q0_1_Position                                    | Browse |
| Tag command:                                             |        |
| c_Ctrontrol_Q0_1Positioon                                | Browse |
| Tag acknowledge blinking:                                |        |
| @NOTP::QuitBlinking                                      | Browse |
| Tooltiptext: WinCC update cycle                          |        |
| Q0 without hierarchy path 2 s ~                          |        |
|                                                          |        |
|                                                          |        |
|                                                          |        |
| OK Cancel                                                | Apply  |

[tagprefix_3, 1, en_US]

Figure 14-40 Suppressing the tag prefix for the acknowledge tag

For more detailed information, refer to the WinCC Information System, Using Tag and Server Prefixes section.

## 14.2.13 Operation via Keyboard

The **Circuit Breaker/Disconnector** graphic objects can be operated via the mouse or using the **keyboard**. To initiate a switching operation using the keyboard, **buttons** must be inserted into the display, and a **hotkey** must be configured for each button.

The switching operation is initiated by pressing the configured key or key combination during runtime. Additionally, a user right can be assigned for the operation of the button.

The **runtime dialogs** of switching device objects are not displayed for operation via keyboard/buttons. An **ordinary PC keyboard** or a **special function keyboard** can be used. To use a function keyboard, the PC keyboard must be removed from the computer and the function keyboard must be plugged in instead.

#### **Configuring a button**

A specific button for each action must be inserted into the diagram (**Object palette > Windows object**). The **Button Configuration** dialog opens as soon as the button has been inserted.

Button Configuration ?  $\times$ CB1 ON Text: Arial Font... Color... Operation: <Kein Zugriffsschutz> Authorization... Shortcut... Change Picture on Mouse Click: OK Cancel

[pascc440, 1, en_US]

Figure 14-41 Configuring a Button

- ♦ Enter the button text into the Text entry field.
- ♦ Next, click **Hotkey...** to define a hotkey for the button.
- ♦ Click **OK** to close the dialog.

For more detailed information regarding the configuration of a button, refer to the WinCC Information System.

#### Defining a C script

In order to be able to initiate an action via a button for **Circuit breaker/disconnector**, a C script has to be defined. When clicking on the button, the C script sets the attribute CommandID of the control (switching device object) to the defined value.

The following table provides a list of all permissible integer values and their meaning.

Value	Constant	Action of the Control (Switching Device Object)	
0	COMMANDID_NOTHING	No action	
1	COMMANDID_CANCEL	Cancel action	
2	COMMANDID_SELECT_ON	Preselect switch position ON	
3	COMMANDID_SELECT_OFF	Preselect switch position OFF	
4	COMMANDID_EXECUTE	Enable switching operation	
5	COMMANDID_SINGLEACK	Acknowledge blinking for the selected switch	
6	COMMANDID_MULTIACK	Acknowledge blinking for a group	
		(see 14.2.2 Tag Connection of the Circuit Breakers and Disconnectors)	

#### Table 14-7 CommandID attribute



### NOTE

Since the **Command control for synchronized/unsynchronized switching** is very complex, controlling via buttons/keyboard is not supported.

The following example illustrates how the select command for ON can be initiated for the control CB1.

- ♦ Open the **Object properties** of the button.
- ♦ In the Properties tag, select Font.
- ♦ Next, enter **CB1 ON** for the **Text** attribute.
- ♦ Select Mouse in the Event tab.

Button	Execute on	Action	
Mouse	Mouse Click	4	
Keyboard	Press Left	- C-Action	
Miscellaneous	Release Left	K VBS-Action	
Property Topics	Press Right	🗲 Direct Connection	
• Geometry	Release Right	🗲 Delete	
E Colors	v		
< >			

[pascc441, 1, en_US]

Figure 14-42 Opening the editor

- ♦ Right-click **Mouse Action** in the **Action** column.
- Select C Action from the context menu.
   The editor opens.



[pascc442, 1, en_US] Figure 14-43 Edit C action

- ♦ Edit the C script.
- $\diamond$  Compile the C script and click **OK** to close the editor.

You can now add further buttons for **deactivating**, **confirming**, and **canceling** the switching operation and configure these buttons accordingly. In this case, the diagram looks as shown below.

$\bigcirc$		
CB1 ON CB1 Cancel	CB1 OFF CB1 Confirm	CB1

[pascc443, 1, en_US]

Figure 14-44 Diagram with buttons for a switching operation

#### Switching operation during runtime

During runtime, a switching operation (OFF > ON) would be executed as follows:

- The switch is in **OFF** state. Click **CB1 ON**.
- The control (switching device object) starts blinking in setpoint state.
- Click CB1 Confirm. The switching command is executed.
- The control (switching device object) switches to the **ON** state. The switching operation is completed.

Feedback messages regarding the switching operation are shown in the event list.

## 14.2.14 Controlling Runtime Dialogs for Controls (Switching Device Objects)

Runtime dialogs can be shown individually using an additional function. Depending on specific conditions, a runtime dialog can be shown or hidden. Some additional dialogs, e.g. for user authentication, can pop up between the selection of the switch and the execution of the command.

The runtime dialog can open due to a value change of the **CommandID** attribute (in the object properties of the control/switching device object). The attribute value can be modified by means of a C script. The following table shows a list of required values.

Table 14-8	CommandID Attribute	Additional Values
------------	---------------------	-------------------

Value	Constant	Action of the Control (Switching Device Object)
20	COMMANDID_SHOWSWITCHINGDIALOG	Show the switching dialog
21	COMMANDID_SHOWSTATEDIALOG	Show the status dialog

#### Configuring the sequence

♦ Deselect the Use Integrated Dialog Boxes option in the properties of the control (switching device object).

This avoids the runtime dialog being displayed automatically.

- ♦ Open the **Object properties** of the control (switching device object).
- ♦ Select the **Object events** entry in the **Events** tab.
- ♦ Right-click Clicked in the Action column.

Object Properties			
Properties Events			
Control Properties	Execute on	Action	
Object Events     Object Events     Forces     Object Events     Geometry     Object Events     Miscellaneous	Clicked OnButtonON OnButtonOFF OnButtonEXECUTE OnButtonSYNC_ON OnButtonCANCELSYNC OnActivateSYNCFUNC OnDectivateSYNCFUNC OnOutput1 OnOutput2 OnILSAStartMes	4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4	C-Action VBS-Action Direct Connection Delete
🔲 Object Properties 🛛 🕬	īags 📃 Output Window	Dynamic Wizard 💡	💾 Library 🔚 SVG library

[pascc450, 1, en_US]

Figure 14-45 Opening the Editor

 ♦ Select C Action from the context menu. The editor opens. 14.2 Circuit Breaker and Disconnector

Edit Action		?	×
🗏 🛃   🐰 💷 🕮 🖏   🗙   🏷	👌 🖶 🍻 🏟 👌 🕞		•
Standard functions GEN GEN H H H H H H H H H H H H H	<pre>#include "apdefap.h" void OnLButtonDown(char* lpszPictureName, char* lpszObjectName, char* lpszPropertyName, UINT nFL { // wINCC:TAGNAME_SECTION_START // syntax: #define TagNameInAction "DMTagName" // next TagID : 1 // WINCC:TAGNAME_SECTION_END // WINCC:PICNAME_SECTION_START // syntax: #define PicNameInAction "PictureName" // next PicID : 1 // WINCC:PICNAME_SECTION_END } #define COMMAND_SHOWSWITCHDIALOG 20 SetPropWord(LPCTSTR lpszPictureName,</pre>	ags, int x,	int y]
	ОК	Cano	:el
Ready	Line: 21	Colum	n: 48 🔡

[pascc451, 1, en_US] Figure 14-46 Editing the C Script

The **Clicked** function has the **wmbutton** parameter assigned. Via this parameter, you can check which mouse button has been clicked.

Table 14-9	wmbutton parameter
------------	--------------------

Value	Constant	Meaning
0x0201	WM_LBUTTONDOWN	the left mouse button was clicked
0x0204	WM_RBUTTONDOWN	the right mouse button was clicked

♦ Edit the C script.

Add the **SetPropWord()** function, your test functions and all applicable conditions.

♦ Save and compile the script.

#### Sequence during runtime

The following sequence applies during runtime:

- Click the control (switching device object).
- The runtime dialog opens. The **Clicked** event is triggered. The C script is executed.
- The functions defined in the C script are processed. Depending on the relevant conditions, the **CommandID** attribute is set in the properties of the control (switching device object).
- The switching dialog is shown if the **CommandID** attribute includes the value 20.

## 14.2.15 Response to the Change of the CommandID Attribute

As soon as a control (switching device object) has processed the value change of the **CommandID** attribute, it transmits a **CommandResponse** event. The event includes three parameters which provide information about the processed action.

The **CommandResponse** function in the C script has the following structure:

```
void CommandResponse(char* lpszPictureName, char* lpszObjectName,
long CommandID,
long ResponseID,
char* msg)
{
...
}
```

IpszDisplayName and IpszObjectName are default parameters of WinCC and are not described in this section.

The **CommandID** parameter includes the value of the **CommandID** attribute which triggered the action. The value of the **ResponseID** parameter describes the result of the action. In case of error, the **msg** parameter includes an error description in text form.

The following table provides a list of the ResponseIDs and their meanings.

Value	Constant	Action of the Control (Switching Device Object)
0	RESPONSEID_OK	The action could be executed without errors.
1	RESPONSEID_NOT_IMPLEMENTD	The action specified via the CommandID attribute has not been implemented.
2	RESPONSEID_NOT_SELECTED	The control (switching device object) has been enabled without preselecting the switch position (ON, OFF).
3	RESPONSEID_WRONG_MODE	The runtime dialog could not be displayed, as the control (switching device object) is in <b>Synchronized switching</b> mode
4	RESPONSEID_WRONG_STATE	The runtime dialog could not be displayed, as the control (switching device object) is in <b>Fast blinking</b> mode. The blinking must be acknowledged first.
5	RESPONSEID_NO_CMD_TAG	For the control (switching device object), no tag name has been selected in command direction.
6	RESPONSEID_SETISACTUAL_ VIOLATION	SET- ACTUAL violation
		For example, the user has tried to execute an OFF command although the ACTUAL position is OFF.
99	RESPONSEID_ANY_ERROR	Another error has occurred.

Table 14-10 ResponseID

## 14.3 Bay Overview

This section describes the **Bay overview** SICAM graphic objects for SICAM SCC V7.02 or earlier. For SICAM SCC V8.00 or higher, they were replaced by SICAM graphic objects featuring more powerful functions. However, the old SICAM graphic objects can still be used. The new Bay Overview SICAM graphic object is described in *4.7 SICAM Bay Overview*.

The **Overview** folder in the SICAM graphic object library includes the Bay Overview user object. It is implemented as an IndustrialX Control and already contains typical functions.

You can use a bay overview to show the status of an entire bay by means of a single graphic object.

#### **Graphical representation**

4 bay overview variants are available in the SICAM graphic object library:

Bay overview	View	Graphic
LSA rounded	LSA representation with circular symbol	
LSA boxed	LSA representation with rectangular symbol	
Sicam rounded	SICAM representation with circular symbol	
Sicam boxed	SICAM representation with rectangular symbol	

Table 14-11Graphical representation of the bay overview

#### Maximum bay extension

A bay overview diagram can show one single bay with the following maximum extension:



[pascc515, 1, en_US]

Figure 14-47 Maximum bay extension shown in one bay overview

## 14.3.1 Properties of the Bay Overview

Each bay overview must be assigned several properties.

♦ Double-click the graphic object.
 The SICAM SCC BAY properties dialog opens.

The properties are shown in the **General** tab.

#### Display

The following five options are available for the representation of a graphic object:

- SICAM boxed
- SICAM rounded
- LSA boxed
- LSA rounded
- Bitmap

In the Bitmap representation mode, individual diagrams can be shown depending on the value. The file formats **BMP**, **WMF**, **EMF**, **JPG**, and **GIF** are supported for diagrams.

#### Line width

The **line width** of the graphic objects (LSA only) can be selected in steps from 1 to 10. Step 1 represents the smallest line width.

#### WinCC update cycle

The **update cycle** of the tags can be set in time intervals from 250 milliseconds to one hour. Furthermore, the setting **For change** is possible. 2 seconds is the default setting.

#### Value

In the normal state, the color and the shape of the graphic object depend on its value. A specific color is set by default for each individual value. It is also possible to select the color from a color palette.

In the **SICAM** representation mode, only the color and not the shape is changed depending on the corresponding value.

The following colors are defined by default for the graphic object in the **SICAM** and in the **LSA** representation modes:

Value	Color	Meaning
ON	Red	The circuit breaker, the line disconnector and at least one busbar disconnector are switched on.
OFF	Green	The circuit breaker, the line disconnector or all busbar disconnectors are switched off.
Intermediate posi- tion	Yellow	At least one of the connected devices in the bay has a fault.
Grounded	Pink	The bay is grounded.

Table 14-12 SICAM and LSA representation modes

#### Status

The switch state is indicated by small, colored rectangles next to the graphic object. A specific color is set by default for each individual state. The color can also be freely selected from a color palette. The following colors of the rectangles are set by default for the representation of the individual states:

Table 14-13 Status

Status	Color	Meaning
Not topical	Cyan (turquoise)	At least one of the devices in the bay has the status <b>Not Topical</b> .
PAS not OK	Dark cyan (petrol)	The connection between SICAM SCC and SICAM PAS or SICAM RTU is disturbed.

The default background color is gray. It can also be freely selected.

## 14.3.2 Tag Connection to Bay Overview

The bay overview must be assigned tags.

- Double-click the graphic object.
   The SICAM PAS CC Bay Properties dialog opens.
- ♦ Open the Tags tab.

SICAM SCC BAY Properties	×	<
General Tags About		
Tagname BBDC1		
BusBar_Disconnector1	Browse	
Tagname BBDC2		
BusBar_Disconnector2	Browse	
Tagname BBDC3		
BusBar_Disconnector3	Browse	
Tagname CB		
CircuitBreaker	Browse	
Tagname LNDC		
Line_Disconnector	Browse	
Tagname EDC		
Ground_Disconnector	Browse	
Grounded only with CB closed Tooltiptext:		
SICAM SCC Bay overview		
OK Cancel	Apply	

[pascc324, 1, en_US]

Figure 14-48 Defining the Bay Overview

#### Tagname BBDC1

Assign a tag to **Busbar Disconnector 1**:

- Click the Browse button next to the edit field.
   The Tags dialog opens.
- $\diamond$  Select the corresponding tag from the list and click **OK** to confirm.

#### Tagname BBDC2

Assign a tag to Busbar Disconnector 2:

- Click the Browse button next to the edit field.
   The Tags dialog opens.
- ♦ Select the corresponding tag from the list and click **OK** to confirm.

#### **Tagname BBDC3**

Assign a tag to Busbar Disconnector 3:

- Click the Browse button next to the edit field.
   The Tags dialog opens.
- ♦ Select the corresponding tag from the list and click **OK** to confirm.

#### Tagname CD

Assign a tag to the circuit breaker:

- Click the Browse button next to the edit field.
   The Tags dialog opens.
- ♦ Select the corresponding tag from the list and click **OK** to confirm.

#### Tagname LNDC

Assign a tag to the line disconnector:

- Click the Browse button next to the edit field.
   The Tags dialog opens.
- $\diamond$  Select the corresponding tag from the list and click **OK** to confirm.

#### Tagname EDC

Assign a tag to the ground disconnector:

- Click the Browse button next to the edit field.
   The Tags dialog opens.
- Select the corresponding tag from the list and click **OK** to confirm.

# 1

Delete the default tag link for switching devices which do not exist in the bay.

- Double-click the tag to be deleted. The tag is selected.
- Press the **Del** key to delete the selected tag.

This ensures that the elements in question are no longer considered for the determination of the bay state, i. e. the value and the status of the **bay overview** are independent of the deleted elements.

#### Grounded only with CB closed

NOTE

Specify whether the grounding shall only be shown when the circuit breaker is closed.

#### **Tooltip text**

Enter a text in the edit field. This text is displayed as **Tooltip** in the active project.

## 14.4 Showing Texts in Runtime Dialogs

Freely defined texts, e. g. notes for the operator, can be shown in runtime dialogs of switches. The texts must be saved in the **PCCIX_xxx.txt** text files.

Texts can be shown statically or dynamically. In this context, the term "statically" means that the text defined via the object properties is shown during runtime.

If a dynamic display is defined, the displayed text is entered during runtime. To do this, an entry field must be configured in the display. Via this entry field, the value of the **UserStringID** can be changed dynamically.

#### **Creating/editing texts**

Open the ...\Siemens Energy\SICAM\SCC\bin\PCCIX_xxx.txt file in a text editor. xxx is used as a wildcard for the language code.

// user defined strings	
1001 Synchronisierung	"Synchronisiert"
1002 Synchronisierung deadline	"Synchronisiert + deadline"
1003 Synchronisiert deadbus	"Synchronisiert + deadbus"
1004 Synchronisiert deadline+deadbus	"Synchronisiert + deadline + deadbus"
1005 userdefined_5	"Text01"
1006 userdefined_6 ""	

[pascc420, 1, en_US] Figure 14-49 Entering user-defined texts

- ♦ Under User-defined strings, enter your text (e.g. Text01) between quotation marks.
   Values between 1000 and 1198 can be used as text IDs.
- $\diamond$  Save and close the file.

## 14.4.1 Showing Static Texts

Proceed as follows to show a static text:

#### Defining the object properties

♦ Open the **Object properties** of the switch in the Graphics Designer.

14.4 Showing Texts in Runtime Dialogs

Object Properties			?×
- PCCIXCtrl	CB_2		-
Properties Events			1
	Attribute	Static Dynami	ic 🔺
Geometry	EnableSyncDialog	No 💦	
Miscellaneous	tagnameSync	Defa Value Input	
Control Properties	tagnameSyncCmd LabelButtonSyncON	Defa	
	UserStringID LabelButtonSyncCancel	0 1005	
	LabelStaticSyncEffective EnbleSelectBeforeOperate	No OK Cancel	
	<u>, , , , , , , , , , , , , , , , , , , </u>		

[pascc421, 1, en_US]

Figure 14-50 Defining the Object Properties

Enter the text ID for the attribute UserStringID in the Properties tab. The text ID corresponds to the number of the text in the text file.

If the UserStringID has the value zero, no additional text is displayed.

♦ Close the **Object properties** dialog and save your display.

#### **Text display**

The defined text is shown in the runtime dialog of the switch during runtime.

- ♦ Start the runtime.
- ♦ Click the switch. The runtime dialog is displayed with the defined text.

SICAM SCC LS/TR				
Text01			$\wedge$	
			~	
Switching				
ON		OFF		
	Cancel			
[pascc422, 1, en US]				

Figure 14-51 Showing Text

### 14.4.2 Showing Dynamic Texts

To show a dynamic text, the text ID must be changed in the **UserStringID** attribute of the control object during runtime. The ID can be changed via a direct connection, a C script or a VB script. This paragraph explains how to change the attribute using a button or a direct connection.

Proceed as follows to show a dynamic text:

#### Defining a button

Add a Windows object of the **Button** type to your display.
 The **Button configuration** dialog opens.

Button Configuratio	n	?	$\times$
Text:	Text 1005		
Font	Arial		
Color			
Operation:	<no access="" prote<="" td=""><td>ection&gt;</td><td></td></no>	ection>	
Shortcut			
Change Picture on M	ouse Click:		ិ
	ОК	Can	cel

[pascc426, 1, en_US]

Figure 14-52 Configuring a button

- ♦ Enter a button text in the **Text** box.
- ♦ Click **OK** to close the dialog.
- ♦ Right-click the button and select **Properties** from the context menu.
- ♦ Select the **Events** tab in the **Object properties** dialog.
- ♦ Select Mouse.
- Right-click Action in the Mouse Action row and select Direct connection from the context menu.
   The Direct connection dialog opens.

rect Connection			? >
Source Constant Text 100 Property Tag Direct Indir	05	Target O Current Window Object in Picture Tag Direct Indirect	t Operator input msg
Object: This object Bildfenster 1 Button2 SCC V7 LS SCC V7 LS QoC SCC V7 TR SCC V7 TR1 SCC V7 TR2 SCC V7 TR3 SICAMBO_q SICAMSwitch_IEC_CB	Property: 3D Border Color 3D Border Weight 3D Shadow Color Adapt Border Authorization Background Color Background Color Background Flash Fr Bold Border Background ( Border Color Configured Languag Display Display options Draw border inside	Object: This object Bildfenster 1 Button2 SCC V7 LS SCC V7 LS QoC SCC V7 TR SCC V7 TR1 SCC V7 TR3 SICAMBO_q SICAMSwitch_IEC_CB	Property: tagnameACK tagnameCMD tagnameSync tagnameSyncCmd Timeout Tooltiptext TOPOColorINVALID TOPOColorOFF Type UseIntegratedDialog UserStringID Width WinCCState WriteCommandOutp ¥
			OK Cancel

[pascc427, 1, en_US]

Figure 14-53 Configuring a direct connection

- ♦ Enter the text ID under Source, Constant.
- Select the Object in picture option under Target.
   The objects are shown in a list.
- ♦ Select the control object in order to show the text in the related runtime dialog.
- ♦ Select UserStringID under Property.
- ♦ Click **OK** to close the dialog and save the display.

#### **Text display**

The defined text is shown in the runtime dialog of the switch during runtime.

- ♦ Start the runtime.
- Click the button.
   The text ID is written into the UserStringID attribute of the switch.
- ♦ Click the switch.
   The runtime dialog is displayed with the defined text.

SICAM SCC LS/TR		
Text01		^
		$\sim$
Switching		
ON	OFF	
Cancel		

[pascc422, 1, en_US] Figure 14-54 Showing text

To deactivate the text, write the value **0** with a direct tag into the **UserStringID** attribute.

## 14.5 IX State Sync Application

The **IX State Sync** application synchronizes the blinking of switching devices. For a redundant SICAM SCC system, it must have been installed on both servers and configured accordingly. It synchronizes operator control actions, such as acknowledgment of spontaneous blinking, on both computers. This also applies for the acknowledgment of spontaneous messages on a switching device object.



#### NOTE

If V7 switching device objects are still used in existing SICAM SCC projects, the **IX State Sync** application can be continued to be used.

With SICAM SCC V8.00, the related functions for the new switching device objects (ActiveX Controls) are performed by the new **SICAM SCC Runtime Data Server** component.



[synctool, 1, en_US]

Figure 14-55 IX State Sync

The IX State Sync application consists of a data connection to WinCC, a database and a network connection to the IX State Sync of the other server.

#### Installation

The **IX State Sync** application is not part of the default installation of SICAM SCC. For the user-defined installation, you can select the installation of this application as **SICAM PAS Redundancy components**. A subsequent installation of the **IX State Sync** application is also possible.

To install the IX State Sync application:

- ♦ Select Start > Settings > Control Panel > Add/Remove Programs.
- ♦ Select SICAM SCC in the list of programs and then click Uninstall/Remove.
- ♦ In the setup of SICAM SCC, select the Change option.
- ♦ Select User-defined setup.
- Activate IX State Sync and click Next.
   The IX State Sync application is installed.

#### Starting the IX State Sync application

For operation, you can enter the **IX State Sync** application in the startup list of WinCC Runtime in order to be able to start and stop this application automatically together with WinCC Runtime. To perform the entry in the startup list, select **WinCC Project > Computer Properties > Startup > Additional Tasks/Applications**. The default path of the IX State Sync application is **C:\Programs\Siemens Energy\SICAM\SCC\bin**.

If WinCC Runtime is not running, the **IX State Sync** application shuts down automatically. For this reason, WinCC Runtime must be activated in order to be able to configure **IX State Sync**. The icon of the started **IX State Sync** application is shown in the Windows task bar.

#### Configuring the connection

The **IX State Sync** application synchronizes data via a special TCP connection. To set up this connection, one computer is configured as server, and the other computer is configured as client. The configuration is independent of the function of the computer in the redundant system (master/standby). In this context, the term "Server/ Client" only refers to the TCP connection. It must not be confused with the client-server terminology used for SIMATIC WinCC.

This connection must be set up as described below:

Right-click the icon of the IX State Sync application. Select Control Center from the context menu.
 The PAS CC IX State Sync dialog opens.

PAS CC I	X State Sync	
		Enable trace output
- Socket o	connection	
State:	Socket state: 0 Closed	Synchronize
Startup:	C Server C Client 💿 OFF	Socket info
Server:	DefaultServer Port: 51119	Chat
 	connection	
State:	Waiting for WinCC Runtime	Reset
- Databas	e	
State:	- unknown -	Add tags
		View tables
	Close	

[synctool01, 1, en_US]

Figure 14-56 Configuring a TCP connection

The state of the TCP connection is shown under State.

- ♦ Select the option **OFF** next to **Startup**.
- ♦ On the first computer, enter the name or the IP address of the second computer in the Server entry field.

- Continue to use the default **Port**.
   If you have any problems with your connection, contact your network administrator to request a valid port number.
- ♦ Select **Client**. The application now tries to establish a connection to the other computer.
  - The connection can only work properly if it has been set up also on the second computer.
- ♦ Enter the same **port** number on the second computer and then select **Server**.

The computers try to set up the connection. The status **Connected** shows that the connection is up. User information/error messages are displayed in the **Report**. If the **Enable trace output** option is selected, all actions are shown in the Report. In addition, status indications are shown in the internal **SICAMPASCCSynch-State** WinCC tag.

The **Synchronize** and **Chat** buttons are enabled as soon as the connection to the other computer has been established.

Click the **Synchronize** button to delete the entries from the database tables on the other computer and to replace them with entries from the local computer.

Click **Socket info** to show current information about the connection in the trace window.

Click **Chat** to open a dialog window for contacting the partner computer. The current state of the connection is shown in the status bar.

Click Reset to clear the connection to the WinCC Data Manager and to re-establish it afterwards.

♦ Click Close to close the PAS CC IX State Sync dialog window.

All settings performed are saved when closing the application. They are still available when the application is started again later. Click **Exit** in the context menu to exit the application.

#### Configuring the IX State Sync database

You must determine which data is to be included in the data synchronization process. These are mainly tags used for the representation of switching devices in the monitoring direction whose IX Hook tags must be synchronized.

To do this, the names of the WinCC tags including this data must be entered in the database. As a rule, the **IXHook** elements of structured tags of the PAS_Informationtype must be entered.

For more detailed information about how to change the IX State Sync database, refer to (*Modifying the IX State Sync database, Page 490*).

To configure the database:

- ♦ Start the **WinCC Explorer** with your WinCC project.
- ♦ Start WinCC Runtime.

If no WinCC project is running, the IX State Sync application shuts down automatically. For this reason, WinCC Runtime must be activated in order to be able to configure IX State Sync.

- Right-click the icon of the IX State Sync application and select Control Center from the context menu.
   The PAS CC IX State Sync dialog window opens.
- In the PAS CC IX State Sync dialog, click the Add Tags button.
   The WinCC Tag Selection dialog window opens.
- Click the **Refresh List** button.

All tags which meet the filter criteria are shown in the list.

The asterisk symbol (*) for the filter can be replaced, but the filter name must have the extension **.IXHook**. For each entry, the application searches the name of the tag structure and the name of the corresponding tag name command structure. This combination is shown in the list. Information tags for which no tag name command is available are ignored.

💀 WinCC tag selection		×
[_] SICAM_1_Fullserver_1_Automatisierung_CFC_Info_aus_CFC_Bef_an_CFC_IamMaster.IXHook		^
[] SICAM_1_Fullserver_1_Automatisierung_CFC_Info_aus_CFC_Bef_an_CFC_Toggle1.XHook		
L) SILAM_I_FUISEVYE_I_Automatisetung_LFU_Into_aus_LFU_Ber_an_LFU_HealthT.IXHook		
ÜVariable_01.IXHook		
U Vanable_UUT.IXHook		
() Variable form 1 Variable 11 KHook		
C VariableGroup 1 Variable 02. Whook		
UVariableGroup_2_Variable_01.IXHook		
() VariableGroup_2_Variable_02.IXHook		
U Vanable Group_1_UB_VanableU1.XHook		
L) VariabeGroup []_EUL_VariabeU1XHook		
() VariableGroup 1, BDC1 VariableD1 XHook		~
Filter: http://titeshist Add selected Items to DB	Close	
15:51:13 Tags in list: 27; Tags selected: 0		

[synctool02, 1, en_US]

Figure 14-57 Selecting tags

- ♦ Select the elements which you want to transfer to the database.
- ♦ Click Add selected items to DB.

The elements are entered in the database.

- $\diamond$  Click **Close** to close the dialog.
- To check the entries in the database, click the View tables button in the PAS CC IX State Sync dialog.
   The Main Table, Information.IXHook dialog opens. The content of the database is shown.

Ma	in table,	Info	rmation.	іхноок			
Clo	se Confiç	ure	Subtables				
	Cookie	Tag	Informa	tion.Counter		DMQuality	Value
▶	1	SIC4	Commar	nd.Counter	ig_CFC_Info_aus_CFC_Bef_an_CFC_Health1.IXHook		
	2	SIC/	Commar	nd.ReplyCounter	ig_CFC_Info_aus_CFC_Bef_an_CFC_Toggle1.IXHook		
	3	SIC/	Informal	tion elements 🛛 🔪	ig_CFC_Info_aus_CFC_Bef_an_CFC_IamMaster.IXHook		
*				N	1		
	1						•
İ.	A Becor	d- 1 v	on 3				b bi
	- neco	u. 1 Vi	ono				

[synctool03, 1, en_US]

Figure 14-58 Showing the content of the database

Table 14-14	Description of t	he menu items	s available in th	e Main Table	e, Information.IXHook	dialog windov	N
-------------	------------------	---------------	-------------------	--------------	-----------------------	---------------	---

Menu Item		Meaning
Close		Closes the dialog.
Configure	Delete values	Deletes the entries in the <b>DMQuality</b> and <b>Value</b> columns.
	Delete table	Deletes the contents of the database, i. e. all tags are removed.
Subtables	Information.Counter	Shows the corresponding database table. Changes in
	Command.Counter	these tables are not possible.
	Command.ReplyCounter	These functions are only used for diagnostic purposes.
	Information elements	

♦ Click **Close** to close the dialog.

#### Synchronizing the IX State Sync databases

Following the configuration of the database on the first computer, the database has to be synchronized with the one on the second computer.

To synchronize the database on the second computer:

- Select Control center from the context menu.
   The PAS CC IX State Sync dialog opens.
- Click the Synchronize button to stop the application on both computers.
   The database on the second computer is deleted; the tables of the local database are transmitted to this computer. Afterwards, the application is restarted on both computers.



#### NOTE

After each change of the local database, this database has to be synchronized with the one on the partner computer.

#### Modifying the IX State Sync database

To add a tag in the database or to remove it, proceed as described below.

- Modify the configuration of the IX State Sync database on a SICAM SCC server (refer to Configuring the IX State Sync database, Page 488).
- Synchronize the databases of the two SICAM SCC servers (refer to Synchronizing the IX State Sync databases, Page 490).

Following synchronization, the application is restarted on both servers. The data is synchronized according to the new configuration.

## 14.6 Measured-Value Display Using the Script/Project Function

The **Measured/Metered Values** folder in the SICAM graphic object library includes the **Measured value integrated C script** and **Measured value project function** user objects. These user objects already include typical functions.

Use these objects to show measured values with an upper and a lower limit.



Use the **Measured value integrated C script** objects to implement various functions by means of script changes to individual objects.

Use the **Measured value project function** objects to control the behavior of the objects from a central level.

## 14.6.1 Defining the Measured-Value Output

Proceed as follows to define the measured-value output:

- Right-click the object and select **Properties** from the context menu.
- The parameters are located in the **Properties** tab under **SICAM**.



#### NOTE

NOTE

Scripts stored in the user objects must not be changed in the **Events** tab.

#### Value (*.Counter)

Right-click the green bulb icon in the Value (*.Counter) row of the Dynamic column. Select Tag from the context menu in order to assign the output box a SICAM PAS tag (e. g. MW1.Counter).



#### NOTE

Always use the Counter structure element for Value (*.counter).

#### Limit Max/Min

You can define 2 upper and 2 lower limits for the measured value. The text color changes when the value exceeds the first upper limit or falls below the first lower limit. The display starts blinking when the value exceeds the 2nd upper limit or falls below the 2nd lower limit.

- Double-click Limit Max/Min in the Attribute column.
- ♦ Enter the limit value.

#### Update

For the **Value (*.Counter)** attribute, a parameter is entered in the **Current** column. With this parameter, you can define the refresh cycle of the measured value.

The following parameter values can be defined: **Picture cycle**, **Window cycle**, **Upon change** and time values between 250 ms and 1 hour. Besides this, user cycles can be defined. 500 ms is the default setting.

The refresh cycle of the diagram can be defined using the **Update Cycle** attribute under **Miscellaneous** in the **Properties** of the diagram.

Recommendation: 2 s.

Double-click the entry in the Current column. Select the parameter from the drop-down list box which opens.

14.6 Measured-Value Display Using the Script/Project Function

#### **Tooltip text**

The tooltip text shows the name of the object on which the mouse cursor is positioned during runtime.

- ♦ Double-click **Tooltip text** in the **Attribute** column.
- $\diamond$  Enter the desired text.

#### Divider

The measured value is divided by the entered value and shown.

- ♦ Double-click **Divider** in the **Attribute** column.
- $\diamond$  Enter the desired value.

#### Digits

The measured value is shown with the number of entered digits.

- ♦ Double-click **Digits** in the **Attribute** column.
- ♦ Enter the desired value.

#### Font color value

The font color and the background color of the value can be selected. White is the default setting for the background color. The font color depends on the state. A specific font color is set by default for each of the following states:

Color	State	Meaning
Black	Normal state	
Cyan (turquoise)	Not topical	The measured value is not topical.
Gray	Not Connected	The measured value object is not linked to a tag.
Dark cyan (petrol)	PAS not ok	The connection between SICAM SCC and SICAM PAS is disturbed.
Red	Limit Max 1	The defined first upper limit of the measured value has been exceeded.
Blue-gray	Limit Min 1	The measured value has fallen below the defined first lower limit.
Pink	Overflow	A measured value overflow has occurred.
Blue	Substituted	The measured value has been substituted.

#### Table 14-15 Font color value

#### Unit

The font color and the background color of the unit can be selected. Black and white are the default settings. Proceed as follows to enter the text to be shown as unit:

- ♦ Double-click Unit in the Attribute column.
- $\diamond$  Enter the text to be shown as unit.

#### Unit

The font color and the background color of the unit can be selected. Black and white are the default settings. Proceed as follows to enter the text to be shown as unit:

- ♦ Double-click **Unit** in the **Attribute** column.
- ♦ Enter the text to be shown as unit.

#### Value range of the measured-value object

Figures with up to 7 digits can be shown using the measured value object. The WinCC data type does not allow more digits.

The substitute dialog is set for the display of 5 positions before and 2 positions after the decimal point. It must be reconfigured if another format is required. The dialog is a user object which has been configured according to WinCC conventions.

## 14.6.2 Substitute Functionality

The measured value object from the SICAM graphic object library uses the **PAS_Substitute_Float_V600** SICAM function for substituting.

#### Setting parameters for value substitutions

To set the parameters for the substitution of a floating point value:

Add the Measured value display measured-value object from the SICAM graphic object library to your diagram.

It is available under Measured/metered value.

♦ Insert the Substitution dialogs graphic object from the same folder.

The **DlgSubstitute** graphic object opens the dialog for entering the substitute value. The **DlgConfirm** graphic object opens the dialog for the confirmation of the substitution.

The CloseMeasuredValueDialoges graphic object automatically closes the value substitution dialogs.

The measured-value object is always visible during runtime. By default, the two dialogs are not shown during runtime. They are only shown if required.

Several measured-value objects can be included in the same diagram. The **Value Substitution Dialogs** graphic object must be inserted only once in each WinCC diagram.

During runtime, the dialogs are shown next to the measured-value object when you right-click the measured-value object (provided that all conditions for the substitution are met). The position of the dialogs can be defined in the C script of the measured-value object (**PAS_ShowDialogSubstitute_V600 function**).



#### [pascc530, 1, en_US]

Figure 14-59 Inserted graphic objects

During runtime, the dialogs show the second half of the tag name at the **<name>** position. int is shown if the tag has the name **Fullsever1_measuredvalue_int.***.

14.6 Measured-Value Display Using the Script/Project Function

A process tag must now be linked to the measured-value object.

- $\diamond$  Right-click the EA field and select **Properties** from the context menu.
- Select **SICAM** in the **Properties** tab of the **Object properties** dialog.
- Right-click the bulb icon in the Value (*.Counter) row of the Dynamic column. Select Tags... from the context menu.
- Select the desired tag of the ***.Counter** type and click **OK**.
- ♦ Close the **Object properties** window.

#### Substitution during runtime

A value substitution during runtime is performed as follows:

- ♦ Start WinCC runtime.
- Click the output box of the measured-value object.
   The dialog for entering the substitute value opens. The current tag value is shown by default.



### NOTE

This dialog is not shown if the status of a message does not allow for a value substitution. Unless an operator action is performed, the value substitution dialogs are closed automatically after 30 seconds. In this case, the substitution is not executed.

Substitu	iting of
in	t
3,0	)0
OK	Cancel

[pascc531, 1, en_US]

Figure 14-60 Dialog for entering a value

Enter the value and click OK to confirm.
 The dialog for confirming the value substitution opens.



[pascc532, 1, en_US]

Figure 14-61 Confirmation dialog

♦ Click Execute to confirm the action.

The value is now substituted. The substitute value is shown in the measured-value object in the color of the **Substituted** status.

The actions requested in the dialogs can also be performed by pressing the **ENTER** and **ESC** keys on the keyboard.

## 14.7 Introduction to the SIMATIC WinCC Configuration Tool

#### Overview

The **Configuration Tool** is subject to the system requirements of SIMATIC WinCC and Microsoft Excel. It is also possible to use the Configuration Tool without SIMATIC WinCC. In this case, you cannot write data to SIMATIC WinCC.

Starting from SIMATIC WinCC V7.3, the functions of the Configuration Tool of the **WinCC Configuration Studio** are integrated in the SIMATIC WinCC UI.



#### NOTE

For Microsoft Excel, you require the **Office Wizard** in order to output warnings from the SIMATIC WinCC Configuration Tool.

## 14.7.1 Installing the SIMATIC WinCC Configuration Tool

The SIMATIC WinCC Configuration Tool can be installed in two different ways.

#### Approach 1

During the setup of SIMATIC WinCC, select the WinCC V7.0 complete entry in the Programs dialog.
 SIMATIC WinCC is installed by means of the SmartTools, the SIMATIC WinCC Configuration Tool and the SIMATIC WinCC Archive Configuration Tool.
 To start the SIMATIC WinCC Configuration Tool.

To start the SIMATIC WinCC Configuration Tool, click **Start > SIMATIC > WinCC > Tools**.

#### Approach 2

- On the SIMATIC WinCC DVD, change to the InstData\WinCC\setup\Products\ConfigurationTool directory.
- ♦ Double-click the setup.exe routine.
- Follow the instructions in the different dialogs of the routine.
   The SIMATIC WinCC Configuration Tool is installed.

After the installation, a file with SICAM SCC-specific extensions must be copied into the installation directory of the Configuration Tool. On the SICAM SCC DVD in the **ConfigurationTool**, you will find version-specific zip files. Each of them holds a **resource.xla** file.

- Select the zip file with the corresponding version and extract the **resource.xla** file.
- Copy this file into the installation directory of the Configuration Tool (... SIEMENS\WinCC\Configuration-Tool).

The existing file must be overwritten.

For more detailed information on how to use the SIMATIC WinCC Configuration Tool, refer to the **Help** menu item in Microsoft Excel.

14.7 Introduction to the SIMATIC WinCC Configuration Tool

	licrosoft Ex	ccel - Bo	ook1					
:0)	<u>File E</u> dit	⊻iew	<u>I</u> nsert F <u>o</u> rma	t <u>T</u> ools [	<u>D</u> ata <u>W</u> indow	Win <u>C</u> C	Help	_ 8 ×
	🚆 🕴 Arial		- 10	BI	<u>u</u>   ≣ ≣ ₹	🐏 Cr	eate project folde	er. 💾
	A1	•	fx			Ch	ange language	Ē
	A	В	C	D	E	👔 Не	lp N	~
1						In	:0 K	1.00
3								
4								1
5								
6 7								
8				-	2			
9								
10								
11				-			-	
14 4	▶ N\Sh	eet1/S	iheet2 / Shee	et3 /	<			>
Read	ly .		,		-			

[pas01, 1, en_US]

Figure 14-62 SIMATIC WinCC Configuration Tool, calling up the help menu

## 14.7.2 Creating an Excel Project Folder

♦ Start Microsoft Excel.

In the menu bar, you will find the **WinCC** entry.

Here you can:

- obtain information on the SIMATIC WinCC Configuration Tool (About)
- call up the SIMATIC WinCC help for the Configuration Tool (Help)
- select the language for the Configuration Tool (Change language)
- create an Excel folder with the data of an existing or new project (Create project folder)

	licrosoft	Excel - E	look1				-				×
:	<u>File E</u> d	it <u>V</u> iew	Insert	F <u>o</u> rmat	<u>T</u> ools	<u>D</u> ata	<u>W</u> indow	Win	<u>C</u> C <u>H</u> elp		×
1	🔋 🗄 Arial			<b>-</b> 10 <b>-</b>	BI	U	≣≣	3	Create project fo	lder.	**
	A1	-	fx					- I.	Change language	, ~	
	A	В		С	D		E	8	Help		~
1		_						-	Info		F
$\frac{2}{3}$											1
4											
5											
6											
8											-
9											
10											
11											
	► H\S	Sheet1 🗸	Sheet2	/ Sheet3	37		<			>	~
Read	ly .										

[pas02, 1, en_US]

Figure 14-63 SIMATIC WinCC Configuration Tool, WinCC menu

♦ Select Create project folder.

You can create a project folder

- with a connection to an existing SIMATIC WinCC project
- without a connection to an existing SIMATIC WinCC project
- with a connection to a new SIMATIC WinCC project

The following tables are created by the SIMATIC WinCC Configuration Tool:

- Project properties
- DM_default values
- Connections
- Tags
- Structure tags
- Structure types
- ALG_default values
- Message blocks
- Message classes
- Group indications
- Single-point indications
- Limit-value monitoring
- Texts
- TLG_default values

- Times
- Process value archives
- Compression archives
- Error list (only if errors occur when writing tags)

All tables can be edited using Excel functions.

#### 14.7.2.1 Project Folder with Connection to an Existing SIMATIC WinCC Project

If **Establish connection to existing project** is selected, all the data of the SIMATIC WinCC project is transferred to the Excel project folder, i.e. all alarms, message classes, data types, structures, structure types, limit values, etc.

New project folder	×
<b>Connect project folder</b> Select the connection status off the new project folder.	
<ul> <li>No connection</li> <li>Establish connection to new project</li> <li>Establish connection to existing project</li> </ul>	
Cancel Back Continue	

[pas03, 1, en_US]

Figure 14-64 Creating a project folder



[pas04, 1, en_US]

Figure 14-65 Connecting a project folder with a SIMATIC WinCC project

Elle Edit View Insert Figmat Tools Data Window WinQC Help Type a question for help <th>Microsoft Excel - Book3</th> <th></th>	Microsoft Excel - Book3	
A   A35   A   B     I   Project properties   WinCC Project   WinCC Project   Single-user project   Single-user project   Establish connection   Manual   Connection status   Connected   I   Data input   B     Use default values     Yes	· ■) File Edit View Insert Format Tools Data Window WinCC	Help Type a question for help 🗸 🖉
A35 A Project properties WinCC Project WinCC Project Project name WVMWAREV5WinCC60_Project_SubstationSouth_1\SubstationSouth.mcp Project type Single-user project Sestablish connection Manual Connection status Data input B Use default values Yes		10 - B / H 三 三 三 同 國 % , % - % - 德 定
A B C C C Project properties ViVMWAREV5WinCC60_Project_SubstationSouth_1\SubstationSouth.mcp Single-user project Stabilish connection Manual 6 Connection Manual 6 Connected 7 C Connected 7 Data input 8 Use default values Yes 10		
Project properties       WinCC Project       Project name       WinCC Project       Project type       Single-user project       Establish connection       Manual       Connected       7       Data input       9       Use default values       Yes		В
Project properties         2       WinCC Project         3       Project name         4       Project type         5       Establish connection         6       Connection status         7       0         9       Use default values         9       Use default values         Yes       10	Ducie et aurentie e	<u>_</u>
WinCC Project     2       3 Project name     \\\\VMWAREV5\\\VinCC60_Project_SubstationSouth_1\\SubstationSouth.mcp       4 Project type     Single-user project       5 Establish connection     Manual       6 Connection status     Connected       7	Project properties	
2     WVMWAREV5WinCC60_Project_SubstationSouth_1\SubstationSouth.mcp       3     Project name       4     Project type       5     Establish connection       6     Connected       7     Image: Connected       9     Use default values       10     Image: Connected	WinCC Project	
Project name     NVMWARE volvminCbul_Project_SubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_INSubstationSouth_	2 2 Decircle and a	WARRANDEN (WARRANDED Desired Outpatrice Oracle AND destration Oracle and
Forection	3 Project hame	Single user project SubstationSouth_ISubstationSouth.mcp
Connection status     Connection status     Connection status     Data input     Use default values     Yes	5 Establish connection	Manual
7     Data input       8     9       9     Use default values       10     10	6 Connection status	Connected
Data input       8       9     Use default values       10	7	
8 9 Use default values 10	Data input	
9 Use default values Yes 10	8	
	9 Use default values	Yes
Add-in	Add-in	
12 Max. number of lines 65536	12 Max. number of lines	65536
13	13	
Create message		
15 Delete existing messages Yes	15 Delete existing messages	Yes
16 Display dialog Yes	16 Display dialog	Yes
17	17	
18 Create limit value monitoring	18 Create limit value monitoring	
19 Delete existing limit values Yes	19 Delete existing limit values	Yes
20 Display dialog Yes	20 Display dialog	Yes
22 Create archive tags	22 Create archive tags	
23 Delete existing archive tags Yes	23 Delete existing archive tags	Yes
24 Urisplay utalog Tes	24 Display dialog	162
as Alarm logging	Alarm logging	
20 Training and the second sec	Project properties / DM default values / Connections /	Tags / Structure tag
Current WinCC project: WWWAREVS WINCCG0 Project: SubstationSouth InstationSouth mon	Current WinCC project: \\\YMWAREV5\WinCC60, Project, SubstationSouth, 1\Substat	tionSouth.mcn

[pas05, 1, en_US]

Figure 14-66 Properties of a project connected to a SIMATIC WinCC project

14.7 Introduction to the SIMATIC WinCC Configuration Tool

<b>E</b> 1	🗷 Microsoft Excel - Book3						
:1	। अध्य Tipe a question for help →						
: n	▶ ◎ ■ ▶   ④   ◎   ◎   ○ Adal + 22 + B / H   三字三詞  國 % + % - %   守守  □ - % + A +						
		B	C C	D	F		
			Ŭ				
1	Structure types	Structure type elements					
2	Name		Communication driver	hannel uni	t		
2		Name	Data type	Length	Offset		
4	DAS Information						
4	PAS_iniormation	Value	22 hit value without eign	4			
0		Value	32-bit value without sign	4			
7		Valuatyna	32-bit value without sign	4			
8		Cauco	32-bit value without sign	4	12		
a		AddCauea	32-bit value without sign	4	16		
10		Counter	32-bit value without sign	4	20		
11		Alarm	Binary tan		20		
12		IXHook	32-bit value without sign	2			
13	PAS InformationSInt	IN TOOR	Sz-bit valde without sign				
14		Value	32-bit value with sign	4	0		
15		Validity	32-bit value without sign	4	4		
16		Valuetyne	32-bit value without sign		8		
17		Cause	32-bit value without sign	4	12		
18		AddCause	32-hit value without sign	4	16		
19		Counter	32-hit value without sign	4	20		
20		Alarm	Binary tag	2	24		
21		IXHook	32-bit value without sign				
22	PAS InformationFloat		3				
23		Value	Floating point number 32-bit IEE	4	0		
24		Validity	32-bit value without sign	4	4		
25		Valuetype	32-bit value without sign	4	8		
26		Cause	32-bit value without sign	4	12		
27		AddCause	32-bit value without sign	4	16		
28		Counter	32-bit value without sign	4	20		
29		Alarm	Binary tag	2	24		
30		IXHook	32-bit value without sign				
• •	▶ N / Connections / Tags / Struct	:ture tag 🔪 Structure types 🖉 ALG_default values 🏒 属			>		
Curn	ent WinCC project: \\VMWAREV5\WinCC60	Project SubstationSouth 1\SubstationSouth.mcp					

[pas06, 1, en_US]

Figure 14-67 SICAM structure data types of a project connected to a SIMATIC WinCC project

## Components and Functions of Earlier SICAM PAS CC/SCC Versions

14.7 Introduction to the SIMATIC WinCC Configuration Tool

🗷 Microsoft Excel - Book3						
📳 Ele Edit View Insert Format Iools Data Window WinCC Help Type a question for help 🔹 🗗 🗙						
🗋 📴 🔒 🕘 瀺 • 🗐 • 🞯 🍟 Arial 🛛 • 22 • B I U 匡 🦉 薯 翊 🥮 % , 🗯 繰 譯 譯 🖽 • 💩 • 🗛 •						
IV1 ▼ fk 20						
A	В	С	C /			
Message categories	lessage type	s				
2 Name		Acknowledgement arrived	Acknowledger			
3	Name	Message arrived coloration	Message depa			
4 Error	2	Yes	No			
5	Alarm	Arrived	Departed			
6	Warning	Arrived	Departed			
7	Failure	Anived				
8 SICAM Message		No	No			
9	Event_161	Arrived	Departed			
10 SICAM Meldung DM/WM/RM		No	No			
11	Event_177	Arrived	Departed			
12 SICAM message with acknowledgement		Yes	Yes			
13	Event_193	Arrived	Departed			
14	VVarning_194	Arrived	Departed			
15	Error_195	Arrived	Departed			
16 SICAM message with acknowledgement on raising		Yes	No			
17	Event_209	Arrived	Departed			
18	Warning_210	Arrived	Departed			
19	Error_211	Arrived	Departed			
20 SICAM protection message		No	No			
21	Event_225	Arrived	Departed			
22 SICAM protection message TR		No	No			
23	Event_241	Arrived	Departed			
24 System, requires acknowledgment		Yes	No			
25	Process control system	Arrived	Departed			
26	System messages	Arrived	Departed			
27 System, without acknowledgment		No	No			
28	Process control system1	Arrived	Departed			
29	Operator input messages	Arrived	Departed			
30		( Leen				
I    ■    ■	oup messages / Single mes	sages / I	>			
Jurrent WinCC project: \\VMWAREV5\WinCC60_Project_SubstationSouth_1\SubstationSouth.mcp						

[pas07, 1, en_US]

Figure 14-68

SICAM message classes and their formatting of a project connected to a SIMATIC WinCC project

14.7 Introduction to the SIMATIC WinCC Configuration Tool

#### 14.7.2.2 Project Folder without Connection to an Existing SIMATIC WinCC Project

New project folder
<b>Connect project folder</b> Select the connection status off the new project folder.
<ul> <li>No connection</li> <li>Establish connection to new project</li> <li>Establish connection to existing project</li> </ul>
Cancel Back Complete

[pas08, 1, en_US]

Figure 14-69 Creating a project folder

If **No connection** is selected, a project folder is created which includes the default values for the project settings. It does not include any SICAM-specific project settings and no connections, tags, structure types and alarms/messages.

Kicrosoft Excel - Book2	
ː File Edit ⊻iew Insert Format Iools Data Window Win⊆C	Type
🚹 🚰 🚽 🔹 🕜 🖌 🕜 🦉 🖁 Arial 🔹 10 🔹 🖪 🖌	u 🗐 🗐 🐨 📰 📑 👋 🐝 🐝
A35 🔻 fx	
A	В
Project properties	
2 WinCC Project	
3 Project name	
4 Project type	
5 Establish connection	Manual
6 Connection status	No connection
7	
Data input	
9 Use default values	Yes
10	
Add-in	
12 Max. number of lines	65536
13	
Create message	
15 Delete existing messages	Yes
16 Display dialog	Yes
17	
18 Create limit value monitoring	
19 Delete existing limit values	Yes
20 Display dialog	Yes
21	
22 Create archive tags	
23 Delete existing archive tags	Yes
24 Display dialog	Yes
25	
26 Alarm logging	
27 Check bits for use	Yes
28 Display request for modification of all identical status texts	No
29 Display request for modification of all identical message texts	Yes
30 Delete unused texts	Yes
31 Delete limit values when deleting your single message	No
32	
33 Comments	
34 Display comments	Yes
35	
36	
	/ Tags / Stru
Current WinCC project: \\VMWAREV5\WinCC60_Project_SubstationSouth_1\Subst	tationSouth.mcp

[pas09, 1, en_US]

Figure 14-70 Predefined properties of a project without a connection to a SIMATIC WinCC project

You can now have a WinCC project created from the Excel project folder.

✤ To do this, select Create WinCC project in the WinCC menu of Microsoft Excel.

14.7 Introduction to the SIMATIC WinCC Configuration Tool

🛛 Microsoft Excel - Book2				
:1	<u>File E</u> dit <u>V</u> iew Insert F <u>o</u> rmat <u>T</u> ools <u>D</u> ata <u>W</u> indow	°₩ir	n <u>C</u> C <u>H</u> elp	_ 8 ×
1	Arial ▼ 10 ▼ B I U ≡ ≡ :	1	Create project folder. 🛛 👌	- A - 🚆
	A35 <b>▼ f</b> ≈	1	Change language	
	A	8	Help	<u> </u>
1	Project properties		Info	
	WinCC Project	1	Create WinCC project	
2			Establish project connection 👋 📃	
3	Project name		Add table	
4	Project type		Statistics	
5	Establish connection		Changes BT language	
7	Connection status			
Data input				
8	Data input			
9	Use default values	_	Yes	
10				~
H + + H Project properties / DM_default values / Connectic <				
Current WinCC project: \\VMWAREV5\WinCC60_Project_Substat				

[pas10, 1, en_US]

Figure 14-71 Creating a SIMATIC WinCC project

♦ Define the **project type** (single-user project, multiple-user project or multi-client project), a **project name** and a **path**.

All the files required for the SIMATIC WinCC project are created. In addition, the project properties, including the project name and project type, are entered in the Excel project folder.

You can now modify the project using the WinCC Explorer (i.e. insert alarms, structure types, connections, etc.) or further edit the Excel project.

#### 14.7.2.3 Project Folder with Connection to a New SIMATIC WinCC Project

The result of a project folder with connection to a new SIMATIC WinCC project is the same as the creation of a project folder **without connection** to a SIMATIC WinCC project and the subsequent **Create WinCC project**, see chapter 14.7.2.2 Project Folder without Connection to an Existing SIMATIC WinCC Project
## NOTE

The following sub-chapters are only relevant for WinCC V7.2 or earlier! The **WinCC Configuration Tool** is no longer supported for WinCC V7.3 or later.

For SIMATIC WinCC V7.3 or later, the functions of the Configuration Tool of the **WinCC Configuration Studio** are integrated in the SIMATIC WinCC UI.

In WinCC Configuration Studio, open the connection properties and select the suitable communication driver.





## NOTE

This is only possible for different SICAM PAS versions!

# 14.8.1 Modifying the Channel Version

When working with different versions of the SICAM PAS system, e.g. after an upgrade, version-specific channels must be used. To do this, it might be necessary to reconfigure existing project data. The following SICAM SCC communication drivers are supported by SIMATIC WinCC:

Table 14-16	SICAM SCC communication drivers supported
-------------	-------------------------------------------

SICAM PAS PROTOCOL SUITE (default channel)	Channel for communication with a SICAM PAS of the same version as the currently installed SICAM SCC version; and default channel for all versions of SICAM PAS/PQS V7 and higher, SICAM SCC V7 and higher
SICAM PAS PROTOCOL SUITE V5	Channel for communication with SICAM PAS V5.11
SICAM PAS PROTOCOL SUITE V6	Channel for communication with SICAM PAS V6.xx
SICAM IEC COMMUNICATION SUITE	Channel for communication with IEC 61850 and IEC 60870-5- 104 devices



#### NOTE

When using different channels, you must ensure that you only integrate channels of different versions in SIMATIC WinCC. The default channel cannot be operated with a version-specific channel of the **same** version.

Only if different versions of SICAM PAS are connected to a SICAM SCC project, must different channels be used. Several SICAM PAS with the same version can communicate with SICAM SCC via the same channel.



# NOTE

If data was imported into a version-specific channel or if data has to be moved to such a channel, the configuration must be modified accordingly. Data which you have imported into a channel is saved in the SIMATIC WinCC database with its ID. Data therefore cannot be moved from one channel to another on the SIMATIC WinCC user interface.

The standard solution in SICAM SCC would be to delete the data using the wizard and to re-import it into the other channel. During this process, all data configured after the import will be lost. For this reason, this approach does not always make sense. Using the SIMATIC WinCC Configuration Tool, it is possible to exchange one channel for the existing data. To do this, the SIMATIC WinCC project must be loaded into **Microsoft Excel** and further edited using the Configuration Tool in this program.

It is possible to exchange one channel for the existing data using the SIMATIC WinCC Configuration Tool. To do so, the SIMATIC WinCC project must be loaded into **Microsoft Excel** and further edited using the Configuration Tool in this program.

#### Notes on parameterization

- During an upgrade, an update in the default channel is performed **automatically**. There is no need to change the parameter settings.
- Data in version-specific channels with the versions 5 or 6 can only be moved by means of a manual change of the connection either to the default channel or a channel with a different version (as described in the following paragraph).

The following paragraphs describe a change of the channel version for an existing SIMATIC WinCC project.

#### 14.8.1.1 Creating a Project Folder

- Create an Excel project folder for the existing project and then connect it to the SIMATIC WinCC project. To do this, the SIMATIC WinCC project does not need to be open.
- ♦ Open the Connections table.

#### 14.8.1.2 Selecting a Channel

The channel currently used for a station is indicated in the **Communication Driver** column.

- SICAM PAS PROTOCOL SUITE for the default channel
- SICAM PAS PROTOCOL SUITE V5 for a channel for communication with SICAM PAS V5.11
- SICAM PAS PROTOCOL SUITE V6 for a channel towards SICAM PAS V6.xx

The default channel is used in the example below.

# Components and Functions of Earlier SICAM PAS CC/SCC Versions

14.8 Working with the SIMATIC WinCC Configuration Tool

	Microsoft Excel - Book3					
: 121	1911 Elle Edit View Teach Extract Teals Data Window Window Window Hale					
. 🔤	The for New Treer Linuar Tools Fors Window wild's Teh					
	🚰 🛃 👌 🎒 🛍 • 🤊	- 🕐 🚰 Arial - 10 - B I 🖳 🚍	E 🗏 🔤 🕎 % , 號 🕫 🕯	Ĕ ∰   🗄 + 🌺 + 🛕 + 🛓		
	C11 ▼ f≈ =[Re	ssource.xla]_Sys_Channel!\$U\$2				
	A	В	С	D 🔨		
1	Connections	Groups				
2	Name		Communication driver	Channel unit Par		
3		Name				
4	Internal tags		Internal tags	Internal tags		
5		Script	-			
6		TagLoggingRt				
7		SICAMAdmin				
8		SICAMAdminInt_109		E		
9		SICAMAdminV3				
10		SICAMAdminV4		<b>1</b>		
11	SubstationSouth		SICAM PAS PROTOCOL SUITE	PAS Data Server 0000		
12		SicamAdmin_109				
13		SICAM_PAS_Demo_PC_IEC_60870_5_103_Master_Port_1				
14		Station_South_TUKY_Day_1_7SUb3				
15		SICAM PAS_Demo_FC_Adjuntation_CFC_FLC_Master				
17		SICAM PAS Demo Automation CEC PLC Master				
18		SICAM PAS				
19		SICAM PAS nb2q001c IEC 60870 5 103 Master Port 1				
20		SICAM PAS nb2g001c Automation CFC PLC Master				
21						
H 4	▶ N Project properties /	DM_default values Connections / Tags / Structure tag   <		>		
Curr	Current WinCC project: \\VMWAREV5\WinCC60_Project_SubstationSouth_1\SubstationSouth.mcp					

[pas11, 1, en_US]

Figure 14-72 SICAM PAS PROTOCOL SUITE communication driver

In the WinCC Explorer, the connection of StationSouth is represented as follows:



Figure 14-73 Representation of the connection in the WinCC Explorer

#### ♦ In the Excel table, double-click SICAM PAS PROTOCOL SUITE.

A selection menu with all the communication drivers available under SIMATIC WinCC opens:

: 🔮 Eile : 🗅 🧀	Edit View Insert Form	nat <u>T</u> ools <u>D</u> ata <u>W</u> indow Win <u>⊂</u> C <u>H</u> elp		and the second			
: n 🙉 I			🖳 Bile Edit View Insert Format Tools Data Window WinCC Help 🛛 Type a question for help 🗸 🗗 🗙				
		: 1 2 日 A 子 R - 1 - 1 0 - 1 0 - 1 B - 7 U 三 三 三 河 呵 % ・ % ※ 注 注 田 - () - A - 1					
★ =/Ressource x/a) Sys Channell\$U\$2							
	A	B	C	D 🔺			
	onnections	Groups					
2	Name		Communication driver	Channel uni			
3		Name					
4 Intern	nal tags		Internal tags	Internal tags			
5		Script					
5		TagLoggingRt					
/		SICAMAdmin CICAMAdministra 400					
a		SICAMAdminInt_105					
10		SICAMAdmin//4					
11 Subs	stationSouth		SICAM PAS PROTOCOL SUITE	▼\S Data Serve			
12		SicamAdmin 109	SIMATIC TI Ethernet Laver 4				
13		SICAM_PAS_Demo_PC_IEC_60870_5_103_Master_Port_1	SIMATIC TI Serial				
14		Station_South_10kV_Bay_1_7SJ63	Sipart				
15		SICAM_PAS_Demo_PC_Automation_CFC_PLC_Master	System Info				
16		SICAM_PAS_Demo_IEC_60870_5_103_Master_Port_1	WINDOWS DDE				
17		SICAM_PAS_Demo_Automation_CFC_PLC_Master	SICAM PAS PROTOCOL SUITE VE	·			
18		SICAM_PAS	I SICAM PAS PROTOCOL SUITE V6				
20		SICAM_PAS_ND2gUUIC_IEC_60870_5_103_Master_Port_1					
20		SIGAM_FAS_ID2g0010_Automation_CFC_FEC_Master					
	N Project properties /	DM_default_valuesConnections / Tags /Structure_tag		×			
Current Win	PCC project (VMWAREVE) wind	CC60 Broject SubstationSouth 1/SubstationSouth mon					

[pas13, 1, en_US]

Figure 14-74 Selection of the communication drivers

♦ Select the corresponding communication driver.



# NOTE

If several stations exist, you must either select the default channel for each station or select one of the version-specific channels. You can select the same channel for several connections. The combination of a default channel and a version-specific channel of the **same** version is not permissible. No check is performed. A potentially incorrect parameterization is not blocked by SIMATIC WinCC.

#### Working with the default channel

In the example, the **SICAM PAS PROTOCOL SUITE** channel has been selected for all connections (stations). Upgrades are performed automatically for this variant. It is not necessary to perform a manual parameterization by means of the SIMATIC WinCC Configuration Tool.

WinCCExplorer - D:\Projects\WinCC\Demo_PASCC\SubstationSouth.MCP File Edit View Tools Help X 🖻 🖻 ്ല 2 12 D) ₽<u>_</u>____ 🔢 Tag Management Ė ~ Name Parameters Thernal tags
 SICAM PAS PROTOCOL SUITE SubstationSouth SubstationNorth 0000000000-PAS Data Server É 🖻 🀶 SubstationSouth 🖰 SicamAdmin 109 SICAM_PAS_Demo_PC_IEC_60870_5_103_Master_Port Station_South_10kV_Bay_1_75J63 SICAM_PAS_Demo_PC_Automation_CFC_PLC_Master 📑 SICAM_PAS 🖻 🎭 SubstationNorth 📑 SicamAdmin_2012 🖰 SICAM PAS2 SICAM_PAS2_Demo_PC_IEC_60870_5_103_Master_Por Station_North_10kV_Bay_1_75J63 SICAM_PAS2_Demo_PC_Automation_CFC_PLC_Master 🖻 🗒 Structure tag < > > SubstationSouth\Tag Management\SICAM PAS PROT@COL SUITE\PAS Data Server\ External Tags: 754 / License: 64K

[pas14, 1, en_US]

Figure 14-75 Permissible parameterization: several stations on the default channel in the WinCC Explorer

	🖬 Microsoft Excel - Book2				
:19	1991 Ele Edit View Insert Format Iools Data Window WinC⊂ Help Type a question for help - 6 ×				
10	🗋 💕 🛃 👌 🙈 🖃 🖉 📲 Arial 💿 💈 🗷 🖪 🗶 🙂 🖪 🖉 👋 🖇 🏭 హ 🖉 🖌 🗛				
_	IV1 <b>▼ f</b> × 8				
	A	В	С	D 🔥	
1	Connections	Groups			
2	Name		Communication driver	Channel unit	
3		Name			
4	Internal tags		Internal tags	Internal tags	
5		Script			
6		TagLoggingRt			
7		SICAMAdmin			
8		SICAMAdminInt_109 Standard channel Is			
9		SICAMAdminV3 used for both Stations			
10		SICAMAdminV4	<b>k</b>		
11		SICAMAdminInt_2012		<b>D</b> 40 D 4 0	
12	SubstationSouth		SICAM PAS PROTOCOL SUITE	PAS Data Server	
13		SicamAdmin_109	Ν		
14		SICAM_PAS_Demo_PC_IEC_60870_5_103_Master_Port_1	1		
15		Station_South_TUKV_Bay_1_7SJ63			
10		SICAM_PAS_Demo_PC_Automation_CFC_PLC_Master	<b>₩</b>		
10	SubstationNorth	SICAM_FAS		DAS Data Service	
10	SubstationNorth	SicamAdmin 2012	SICAM FAS FROTOCOL SUITE	FAS Data Server	
19		SicamAumin_2012			
20		SICAM DAS2 Dama DC IEC 60870 5 103 Maatar Bart 1			
21		Station North 101/7 Bay 1 75 63			
22		SICAM PAS2 Demo PC Automation CEC PLC Master			
23		oronam_rinez_bend_rio_Automation_orio_rico_Master			
24			1	×	
14 4	I ► ►I \ Project properties /	DM_default values Connections / Tags / Structure tag <		>	
Curr	ent WinCC project: \\VMWAREV5\W	'inCC60_Project_SubstationSouth_1\SubstationSouth.mcp			

[pas15, 1, en_US]

Figure 14-76 Permissible parameterization: several stations on the default channel in Excel

#### Working with version-specific channels

- ♦ Based on the explanations in the Cases from Daily Practice paragraph, you must decide which channels you want to use.
- $\diamond$  ~ Select the correct channel for the connections to your SICAM PAS systems:
- SICAM PAS PROTOCOL SUITE V5 for communication with SICAM PAS V5.11
- SICAM PAS PROTOCOL SUITE V6 for communication with SICAM PAS V6.xx

You can combine the different channels.

♦ Save the table.

	🛛 Microsoft Excel - Book2				
:1	🖼 File Edit View Insert Format Iools Data Window WinCC Help 🗸 🗗 🗙				
÷n	🖻 🔲 🖪 🖓 📲 🥱 📲 🧐	- @ Z Arial - 10 - <b>B</b> Z U   ≡	E 🚍 🗃 💷 % , 🐄 🕫 崖	: 🖅   📖 - 💩 - A - 📘	
	C19 <b>*</b>				
	A	В	С	D 🔺	
1	Connections	Groups	-		
2	Name		Communication driver	Channel unit	
3		Name			
4	Internal tags		Internal tags	Internal tags	
5		Script			
6		TagLoggingRt			
7		SICAMAdmin Version specific channe	is are		
8		SICAMAdminInt_109 used to connect stations	s of		
9		SICAMAdminV3 different versions			
10		SICAMAdminV4			
17	SubstationSouth	SICAMAdminini_2012		DAS Data Samer VE	
12	SubstationSouth	SicomAdmin 109	SICANI FAS PROTOCOL SOITE VS	FAS Data Server VS	
14		SICAM PAS Demo PC IEC 60870 5 103 Master Port 1	<b>\</b>		
15		Station South 10kV Bay 1 75.63	N		
16		SICAM PAS Demo PC Automation CFC PLC Master	1		
17		SICAM PAS	Ň		
18	SubstationNorth	-	SICAM PAS PROTOCOL SUITE V6	PAS Data Server V6	
19		SicamAdmin_2012		1	
20		SICAM_PAS2			
21		SICAM_PAS2_Demo_PC_IEC_60870_5_103_Master_Port_1			
22		Station_North_10kV_Bay_1_7SJ63			
23		SICAM_PAS2_Demo_PC_Automation_CFC_PLC_Master			
24				×	
14 4	→ N \ Project properties /	DM_default values Connections / Tags / Structure tag /		>	
Curre	ent WinCC project: \\VMWAREV5\W	inCC60_Project_SubstationSouth_1\SubstationSouth.mcp			

[pas16, 1, en_US]

Figure 14-77 Parameterization: several stations on version-specific channels in Excel

#### Combination of the default channel and a version-specific channel

The combination of a default channel and a version-specific channel of the **same** version is not permissible. However, no check is performed. A potentially incorrect parameterization is not blocked by SIMATIC WinCC.



#### NOTE

Be aware that different versions must be used when combining the default channel with a version-specific channel. This check is particularly important for all upgrade scenarios.

1	Microsoft Excel - Book2			
ļ	Eile Edit Yiew Insert Format	<u>T</u> ools <u>D</u> ata <u>W</u> indow Win <u>C</u> C <u>H</u> elp	Type a q	uestion for help 🛛 🚽 🗖
1	📴 🚽 🖪 🎒 🛝 - 🔊 - 1	Σ • 🕡 🚆 Arial • 12 • 🖪 Ι 🗓	≣ 🔳 💀 🦉 % , 號 📲	= 🖅   🖽 - 🔕 - <u>A</u> -
	C2 - 🖈 =[Ress	purce.xla] Sys Headings!\$D\$25		
	A	B	С	D
	Connections	Groups		
	Name		Communication driver	Channel unit
-		Name		[
	Internal tags		Internal tags	Internal tags
_		Script		
		TagLoggingRt		
		SICAMAdmin Combination of version	specific and	
		SICAMAdminInt_109 standard channel		
		SICAMAdminV3 Check whether versions	are different!	
)		SICAMAdminV4		
		SICAMAdminInt_2012		
2	SubstationSouth		SICAM PAS PROTOCOL SUITE V5	PAS Data Server V5
3		SicamAdmin_109		
1		SICAM_PAS_Demo_PC_IEC_60870_5_103_Master_Port_1	A	
5		Station_South_10kV_Bay_1_7SJ63	<u>↓</u>	
ŝ		SICAM_PAS_Demo_PC_Automation_CFC_PLC_Master	- <u>\</u>	
,		SICAM_PAS		540 B + 0
5	SubstationNorth	0	ISICAM PAS PROTOCOL SUITE	PAS Data Server
2		SicamAdmin_2012		
1		BICAM BAS2 Domo BC IEC 60970 5 102 Montos Dort 1		
2		Station North 1007 Boy 1 75 63		
2		SICAM PAS2 Demo PC Automation CEC PLC Moster		
1		Dioxim_r Acz_Denio_r C_Adtomation_or C_FEC_Master		
÷				-
1	<ul> <li>Project properties / DM</li> </ul>	i_derault values \Connections { Lags { Structure tag { St ]	(Su)u)	>

[pas17, 1, en_US]

Figure 14-78 Parameterization: combination of a version-specific channel with a default channel in Excel

#### 14.8.1.3 Writing Connections Back into the SIMATIC WinCC Project

After selecting a valid combination for the channels, you can write the modified settings back into the SIMATIC WinCC project.

If the SIMATIC WinCC project to be edited is open:

♦ In Microsoft Excel, select the **WinCC > Write connections** menu item.

If the SIMATIC WinCC project to be edited is not open:

- Select the Establish project connection menu item.
   A connection is established with the SIMATIC WinCC project assigned to the project folder. To do this, the WinCC Explorer is, however, not opened.
- ♦ In Microsoft Excel, select the WinCC > Write connections menu item. You only need to write the changes.

<b>N</b>	Aicrosoft Excel - Book2				
:	<u>File E</u> dit <u>V</u> iew Insert Fo	rmat <u>T</u> ools <u>D</u> ata <u>W</u> indow	Win	I <u>C</u> C <u>H</u> elp	- 8 ×
: 🔒	🚆 Arial 📼 10	) • <b>B</b> <i>I</i> <u>U</u> = = =	8	Create project folder.	• <u>A</u> • 🚆
	C13 🔻 🖈			Change language	
	. A		8	Help	^
1	Connections	Gi	· .	Info	1
	Name		1	Create WinCC project	Con
2				Establish project connection	
2		I		Add table	
	Internel tege			Statistics	Internal to
5	internar tays	Script		Change RT language	
6		TagLoggingRt	R	Write connections	
7		SICAMAdmin			~
I					
Curre	ent WinCC project: \\VMWAREV5\W	/inCC60_Project_Subs			

[pas18, 1, en_US]

Figure 14-79 Writing connections

You can now check the new connections in the WinCC Explorer.

After writing back the connections into the SIMATIC WinCC project, the version-specific channels with the stations are displayed as soon as the view has been refreshed. The default channel originally used is empty.

III Tag Management - WinCC Configuration	tudio	- 1	a	×
<u>F</u> ile <u>E</u> dit <u>V</u> iew Too <u>l</u> s <u>H</u> elp				
Tag Management «	Find Properties			»
Tag Management	Name Comment C A 🖻 Selection			
🗄 🍄 Internal tags	1 @ConnectedRTClients U Object type			
Structure tags	2 @CurrentUser Dbject name			
· ·	3 @CurrentUserName 1			
	4 @DatasourceNameRT 1			
	5 @DeltaLoaded u			
	6 @LocalMachineName 1			
	7 @PHServer_Mirror_Details			
	8 @PHServer_Mirror_State			
	9 @PHServer_Principal_Details			
	10 @PHServer_Principal_State			
	11 @RedundantServerState			
	12 @SCRIPT_COUNT_ACTIONS_IN_QUEUES U			
	13 @SCRIPT_COUNT_REQUESTS_IN_QUEUES U			
	14 @SCRIPT_COUNT_TAGS L			
	15 @ServerName			
	16 @ServerVersion 1			
	17 @TLGRT_AVERAGE_TAGS_PER_SECOND F			
	18 @TLGRT_SIZEOF_NLL_INPUT_QUEUE F			
	19 @TLGRT_SIZEOF_NOTIFY_QUEUE F			
	20 @TLGRT_TAGS_PER_SECOND F			
	21 💥			
	22			
Tag Management	23			
111	24			
Alarm logging	25			
	26			
Tag Logging	27			
📼 🗱 111 📣 📩 💷 🗸	28			
	H + H Connections Groups < >			
Ready NUM	German (Germany) Table: 20 Tags 100 % —			÷.,

[pas19, 1, en_US]

Figure 14-80 WinCC Explorer after the change to version-specific channels

The **SICAM PAS PROTOCOL SUITE** driver previously used is still displayed in the Tag Management of the WinCC Explorer. This information cannot be automatically deleted from the system, but you can remove the driver manually.

The **SubstationSouth** station now uses the **SICAM PAS PROTOCOL SUITE V5** driver, whereas the **Substation North** station uses the **SICAM PAS PROTOCOL SUITE V6** driver.

# 14.8.2 Editing Structure Types

For a migration of SICAM PAS/SICAM PAS CC from V5.xx to SICAM SCC V8.04, the structure types must be extended in order to be able to use new functions of SIAM PAS V7.00/V8.00 or the SIMATIC WinCC WebNavigator.

For SICAM PASCC V6.00 or higher, you require an extension of the structure types by the **DWORD WBCounter** element in order to be able to execute the **Substitute** function.

Structure properties (Instances exist! Read only.)	
General OS Use additional Format Adaptations from	_AS
No unit         PAS_Information         DW0RD Value         DW0RD Validity         DW0RD Valuetype         DW0RD Cause         DW0RD AddCause         DW0RD Counter         BIT Alarm         DW0RD IXHook             Type Conversion             ShortToSignedWord	Length Offset Bit
Linear scaling     Process Value Range     Value1     Value2     Choose OS structure elements.     OK Cancel	Help

[pas20, 1, en_US]

Figure 14-81 PAS_Information V5.xx structure type

Structure properties	
General OS Use additional Format Adaptations from	AS
No unit         DWORD Value         DWORD Validity         DWORD Valuetype         DWORD Cause         DWORD AddCause         DWORD Counter         BIT Alarm         DWORD WBCounter         DWORD IXHook         External tag         Internal Tag         New Element         Delete Element	Length Offset Bit
Linear scaling   Process Value Range   Value1   Value2   Choose OS structure elements.	
OK Cancel	Help

[pas21, 1, en_US]

Figure 14-82 PAS_Information V6.xx/V7.00 structure type

Additional structure element for the PAS_Information V6.xx/V7.00 structure types:

• WBCounter

Structure properties	×
General	
OS Use additional Format Adaptations from	AS
No unit  PAS_Information  DWORD Value  DWORD Value  DWORD Valuetype  DWORD Cause  DWORD AddCause  DWORD Counter  BIT Alarm  DWORD WBCounter  DWORD COVCounter  DWORD COVCounter  DWORD IXHook  TEXT8 RTInfo  TEXT8 RTSync	Length Offset Bit
External tag     Internal Tag     New Element     Delete Element	
Choose OS structure elements.	
OK Cancel	Help

[SCC_PAS_Information, 1, en_US]

Figure 14-83 PAS_Information V8.00 structure type

Structure properties	
General	
Use additional Format Adaptations from	AS
No unit	Length
PAS_Command 	Offset
DWORD Valuetype     DWORD Cause     DWORD AddCause     DWORD ReplyCounter     DWORD ReplyCounter	Bit
DWORD CMacounter DWORD COVCounter TEXT8 RTCmd	
External tag     O Internal Tag     New Element     Delete Element	
Linear scaling	
Value1 Value2 Value2 Value2	
Choose OS structure elements.	
OK Cancel	Help

[SCC_PAS_Command, 1, en_US]

Figure 14-84 PAS_Command V8.00 structure type

From SICAM SCC V8.00 (SIMATIC WinCC V7.0 or higher), an extension of the structure types by further elements is required in order to be able to establish the connection to the SICAM Runtime Dataserver, see chapter7.8 SICAM SCC Runtime Data Server.

Additional structure elements for the **PAS_Information V8.00** structure type:

- WBCounter
- COVCounter, external
- RTInfo, internal
- RTSync, internal

Additional structure elements for the PAS_Command V8.00 structure type:

- COVCounter, external
- RTCmd, internal
- $\diamond$  Add/modify the structure types described in the paragraph below.

#### 14.8.2.1 Modifying Structure Types

Using the SIMATIC WinCC Configuration Tool, it is also possible to modify structure types and the corresponding structure elements.

Proceed as follows in order to add a new structure element, e.g. **WBCounter**, to the **PAS_Information** structure type:

- ♦ Select the **Structure types** table in Microsoft Excel.
- ♦ Click Insert > Rows in order to insert a new row for the PAS_Information structure type.
- ♦ In the new row under **Structure elements**, enter **WBCounter** in the **Name** column.
- ♦ Double-click in the **Data type** column and select the **32-bit value without sign** data type from the list.
- Double-click in the External tag column and select Yes.
   Internal tags are only visible in SIMATIC WinCC on the internal, local or project level. The channel and SICAM PAS cannot "see" them.

🛛 Microsoft Excel - Book2							×			
:2)	<u>File E</u> dit ⊻iew Insert	F <u>o</u> rmat <u>T</u> ools <u>D</u> ata	<u>W</u> indow Win <u>⊂</u> C <u>H</u> elp				Type a que	estion for help 🔍 .	- 8	×
Ξ'n		Σ - Q	💾 : Arial 🔹 10	- B	τυ 🗏	E 🗄 🗃 📷	🥶 % , 👬 😳	🖅   111 - 🏷 -	Α.	
<u></u>	A12 - &								_	-
	A	В	с	D	E	F	G	Н		^
1	Structure ty	Structure	type elements							
2	Name		Communication driver	Channe	el unit					
3		Name	Data type	Length	Offset	Offset bit	Format adaptation	External tag	Lir	
4	PAS_Information									1
5		Value	32-bit value without sign	4	0		DwordToUnsignedDword	Yes	No	
6		Validity	32-bit value without sign	4	4		DwordToUnsignedDword	Yes	No	
7		Valuetype	32-bit value without sign	4	8		DwordToUnsignedDword	Yes	No	
8		Cause	32-bit value without sign	4	12		DwordToUnsignedDword	Yes	No	
9		AddCause	32-bit value without sign	4	16		DwordToUnsignedDword	Yes	No	
10		Counter	32-bit value without sign	4	20		DwordToUnsignedDword	Yes	No	
11		Alarm	Binary tag	2	24	0		Yes		
12		WBCounter	32-bit value without sign	4	26		DwordToUnsignedDword	Yes	No	
13		IXHook	32-bit value without sign					No		
14	PAS_InformationSInt									
15		Value	32-bit value with sign	4	0		LongToSignedDword	Yes	No	
16		Validity	32-bit value without sign	4	4		DwordToUnsignedDword	Yes	No	
17		Valuetype	32-bit value without sign	4	8		DwordToUnsignedDword	Yes	No	
18		Cause	32-bit value without sign	4	12		DwordToUnsignedDword	Yes	No	Y
14 4	▶ N / Connections / Tag	gs ( Structure tag ) S	tructure types / ALG_default va	lues / Me	ssag <				>	
Curre	ent WinCC project: \\VMWAREV5	5\WinCC60_Project_Subst	ationSouth_1\SubstationSouth.mcp				Sum=30			

[pas22, 1, en_US]

Figure 14-85 Defining a new structure element

♦ In Microsoft Excel, select the WinCC > Write structure types menu item.

	🗷 Microsoft Excel - Book2										
:8	<u>File E</u> dit <u>V</u> iew Insert	Format <u>T</u> ools <u>D</u> ata	Window	Win	n⊆C <u>H</u> elp	Help Type a question for help					-8×
£ n		- 🗳 - Σ - 🥥	🔛 🗄 A	*	Create project folder.		U		🧊 % , 號 👯 🗐	🛊 🗉 • 💩 •	A -
	A12 - fx				Change language					·····	
	A	В		2	Help		E	F	G	Н	^
1	Structure ty	Structure	type		Info				•		
	Name		Comr	1	Create WinCC project		l unit				
2					Establish project conne	ection					
		Name			Add table		Offset	Offset bit	Format adaptation	External tag	Lir
3					Statistics						
4	PAS_Information	N /= l	22.63.001		Change RT language		-	)	Descend Tables in a siDescend	V	b.L.
		Value	32-bit val				L	J	DwordToUnsignedDword	Yes	NO
<u>b</u>		Validity	32-bit val	Ť.	Write structure types	N	4		DwordToUnsignedDword	Yes	NO
4		Valuetype	32-bit val	ue v	vitriout sign	43 4	8	1	DwordToUnsignedDword	Yes	INO
8		Cause	32-bit val	ue v	vithout sign	4	12	2	DwordToUnsignedDword	Yes	No
9		AddCause	32-bit val	ue v	vithout sign	4	16	i	DwordToUnsignedDword	Yes	No
10		Counter	32-bit val	ue v	vithout sign	4	20	)	DwordToUnsignedDword	Yes	No
11		Alarm	<u>Binarγ</u> ta	g		2	24	0		Yes	
12		WBCounter	32-bit val	ue v	vithout sign	4	28	i	DwordToUnsignedDword	Yes	No
13		IXHook	32-bit val	ue v	vithout sign					No	
14	PAS_InformationSInt										
15		Value	32-bit val	ue v	vith sign	4	0	1	LongToSignedDword	Yes	No
16		Validity	32-bit val	ue v	vithout sign	4	4		DwordToUnsignedDword	Yes	No
17		Valuetype	32-bit val	ue v	vithout sign	4	8	3	DwordToUnsignedDword	Yes	No
18		Cause	32-bit val	ue v	vithout sign	4	12	2	DwordToUnsignedDword	Yes	No 🔽
14 4	। ▶ ▶ / Connections / Tag	gs / Structure tag $\lambda$ S	tructure	typ	es / ALG_default val	ues / Me:	sag <				>
Curr	ent WinCC project: \\VMWAREVS	5\WinCC60_Project_Subst	ationSouth_	1\Su	bstationSouth.mcp				Sum=30		

[pas23, 1, en_US]

Figure 14-86 Writing a structure type

It is sufficient only to write changes - select the Changes only checkbox for writing connections.

- ♦ Open the Tags table.
- ♦ Select the WinCC > Write tags menu item.

The new tags are transferred back into the SIMATIC WinCC project.

	🛛 Microsoft Excel - Book2										
:3	Eile Edit View Inser	rt F <u>o</u> rmat <u>T</u> o	ols <u>D</u> ata	Window	Win	⊆C <u>H</u> elp				Тур	e a question for help 🛛 🚽 🗗 🗙
£n		🙈 + 🖉 + I	Σ - 🙆	💾 i A	8)	Create proje	ect folder.	<b>υ</b> ∎		· · · · · · · · · · · · · · · · · · ·	8 🗄 🖅 I 🖙 - 🗞 - A -
	A27 - f	Station Sou	th 10kV B	av 1.7S		Change land	luage			1 00 00	
	A	B	0	<u>aj_1_10</u>	Ð	Help		F	G	Н	
	-				<u>1</u> 5	nop					·
1	lags					Info					
	Name	Data t∨pe	Length F	ormat	1	Create WinG	IC project	Group	Address	Update	Linear scaling ves
2				••••••		Establish pro	ject connection				
3	@SCRIPT_COUNT_TA	32-bit value v	4			Add table		cript		Local computer rela	ted
4	@SCRIPT_COUNT_RE	32-bit value v	4			1100 (0010		cript		Local computer rela	ted
5	@SCRIPT_COUNT_AC	32-bit value v	4			Statistics		cript		Local computer rela	ted
6	@TLGRT_SIZEOF_NO	Floating poin	8			Change RT I	anguage	agLogging	gRt	For entire project	
7	@TLGRT_SIZEOF_NLL	Floating poin	8		-51	Weike kning	-	agLogging	gRt	For entire project	
8	@TLGRT_TAGS_PER	Floating poin	8		J	white tays		agLogging	gRt	For entire project	
9	@TLGRT_AVERAGE_	Floating poin	8				Internal tags	TagLogging	gRt	For entire project	
10	@CurrentUser	Text tag, 8-bi	0				Internal tags			Local computer rela	ted
11	@DeltaLoaded	32-bit value v	4				Internal tags			For entire project	
12	@LocalMachineName	Text tag, 8-bi	0				Internal tags			Local computer rela	ted
13	@ConnectedRTClients	16-bit value v	2				Internal tags			Local computer rela	ted
14	@RedundantServerStat	16-bit value v	2				Internal tags			Local computer rela	ted
15	@DatasourceNameRT	Text tag, 16-I	0				Internal tags			Local computer rela	ted
16	@ServerName	Text tag, 16-I	0				Internal tags			For entire project	
17	@CurrentUserName	Text tag, 16-l	0				Internal tags			Local computer rela	ted
18	TextIDOffset	32-bit value v	4				Internal tags	SICAMAdr	nin	For entire project	
19	CompKey_Ext_109	32-bit value v	4 D	wordToU	nsigi	nedDword	SubstationSouth	SicamAdm	VID0000000	0009,TID70,V50001,	No 😽
H.	I → N / Connections )	Tags / Structu	ure tag 🖌 S	Structure :	type	s / ALG_d	efault values 🔏 I	Messag 🔇			>
Curi	Current WinCC project: \\WMWAREVS\WinCC60_Project_SubstationSouth_1\SubstationSouth.mcp										

[pas24, 1, en_US] Figure 14-87 Writing tags

#### 14.8.2.2 Deleting Structure Types/Tags

When exchanging a V8 default channel by a version-specific V5 channel, you can use the Configuration Tool in order to delete V6-specific structure elements (if existing). If only SICAM PAS V5.xx is connected, the **WBCounter** structure element can be deleted.

In Microsoft Excel, do not use the **Edit > Delete cells** function in order to delete tags, structure types or structure type elements.



NOTE

Before each delete action, save the SIMATIC WinCC project because the delete action cannot be undone.

To delete tags, structure types, or structure type elements:

- ♦ Highlight the rows which you want to delete.
- ♦ Right-click the highlighted rows and then select **WinCC Delete selection** from the context menu.

	🛛 Microsoft Excel - Book2								
:8	<u> Eile E</u> dit <u>V</u> iew Insert	Format <u>T</u> ools <u>D</u> ata	<u>W</u> indow Win <u>⊆</u> C <u>H</u> elp				Type a qu	estion for help 🔍 ,	_ 8 ×
÷n			P Arial - 10	- P	7 TT I≣		= 0, • •,0 .00 =		Δ -
22			5 Hildi 10		<u> </u>		33 /0 / .00 ⇒.0 =≓		<u> </u>
_	A12 🔻 🏄	-	•	_	_	-			
	A	В	U	U	E	F	l G	н	<b></b>
1	Structure ty	Structure	type elements						
2	Name		Communication driver	Channe	el unit				
2		Name	Data type	Length	Offset	Offset bit	Format adaptation	External tag	Lir
<u> </u>	DAD Information								
4	PAS_Information	Value	20 hitualus without size		0		Durard Tallingian ad Durard	Vaa	Na
6		Value	32-bit value without sign	4	0		DwordToUnsignedDword	Vee	No
10 7		Valuatura	32-bit value without sign	4	4		DwordToUnsignedDword	Vee	No
6		Cauco	32-bit value without sign	4	10		DwordToUnsignedDword	Vee	No
		AddCoupo	22-bit value without sign	4	12		DwordToUnsignedDword	Vec	No
10		Counter	22-bit value without sign	4	20		DwordToUnsignedDword	Vec	No
11		Alorm	Diport tog	4	20	0	DwordToOnsignedDword	Vec	INU
12		WBCounter	32-bit value without eign		24	0	DwordTol IncignedDword	Vec	No
1	WinCC - write selection	XHook	32-bit value without sign		20		Dword100nsignedDword	No	140
			32 bit value without sign					140	
H	WinCC - delete selection	Value	32-hit value with sign	4	n		LongToSignedDword	Yes	No
	🖌 Cu <u>t</u>	/alidity	32-bit value without sign	4	4		DwordTol InsignedDword	Yes	No
1	Copy	/aluetyne	32-hit value without sign	4	. 8		DwordToUnsignedDword	Yes	No
1		Cause	32-hit value without sign	4	12		DwordToUnsignedDword	Yes	No
1	<u>P</u> aste	AddCause	32-hit value without sign	4	16		DwordToUnsignedDword	Yes	No
2	Paste Special	Counter	32-bit value without sign	4	20		DwordToUnsignedDword	Yes	No
2	Incort	Alarm	Binary tag	2	24	0		Yes	
2	Tuperr	XHook	32-bit value without sign					No	
2	Delete								-
2	Clear Contents	/alue	Floating point number 32-bit IEEI	4	0		FloatToFloat	Yes	No
2	E	/alidity	32-bit value without sign	4	4		DwordToUnsignedDword	Yes	No
2	Eormat Cells	/aluetype	32-bit value without sign	4	8		DwordToUnsignedDword	Yes	No
2	<u>R</u> ow Height	Cause	32-bit value without sign	4	12		DwordToUnsignedDword	Yes	No
2	Hide	AddCause	32-bit value without sign	4	16		DwordToUnsignedDword	Yes	No
2		Counter	32-bit value without sign	. 4	, 20		DwordToUnsignedDword	Yes	No 💌
H	Unnide	$\lambda$ Structure tag $\lambda$ S	tructure types / ALG_default va	lues / Me	ssag <				>
Curr	rrrent WinCC project: \\VMWAREV5\WinCC60_project_SubstationSouth_1\SubstationSouth.mcp Sum=30								

[pas25, 1, en_US]

Figure 14-88 Deleting a structure element

When deleting structure types and structure elements, the corresponding structure tags are deleted automatically.

# A Appendix

A.1	Structures	522
A.2	Quality Codes of Variables	531
A.3	Character Conversion	532
A.4	Additional Information in Message Lists	536
A.5	Performance Measurements	543

# A.1 Structures

In SICAM SCC, the items of PAS information (tags) is (are) processed as structures; a structure consists of several elements. There are 6 different structure types.

When importing tags from SICAM PAS, the tags are automatically assigned to the corresponding structure type.

In SICAM SCC, you directly access structure type elements, i.e. tags and relevant additional information. This chapter provides a list of the structure types and an overview of the meaning of the structure elements.

#### **External Structure Types**

The following external SICAM SCC structure types are created by the SICAM PAS Wizard:

- PAS_Information
- PAS_InformationFloat
- PAS_InformationSInt
- PAS_Command
- PAS_CommandFloat
- PAS_CommandSInt

#### **Structure Elements**

The structures are composed of elements.

Table A-1	PAS_Information structure	(monitoring direction)
-----------	---------------------------	------------------------

Double word (4 bytes)	Value
Double word (4 bytes)	Validity
Double word (4 bytes)	Valuetype
Double word (4 bytes)	Cause
Double word (4 bytes)	Additional cause (AddCause)
Double word (4 bytes)	Counter
Bit	Alarm
Double word (4 bytes)	WBCounter
Double word (4 bytes)	IXHook
Double word	COVCounter
8-bit character set text variable	RTInfo
8-bit character set text variable	RTSync
8-bit character set text variable	RTTopo



# NOTE

**WBCounter** is only available for newly created projects. Old projects can be adjusted accordingly (see 14.8.2 Editing Structure Types)

#### Table A-2 Structure PAS_InformationFloat (monitoring direction)

Floating point (4 bytes)	Value
Double word (4 bytes)	Validity
Double word (4 bytes)	Valuetype
Double word (4 bytes)	Cause
Double word (4 bytes)	Additional cause (AddCause)

Double word (4 bytes)CounterBitAlarmDouble word (4 bytes)WBCounterDouble word (4 bytes)IXHookDouble wordCOVCounter		
Bit     Alarm       Double word (4 bytes)     WBCounter       Double word (4 bytes)     IXHook       Double word     COVCounter	Double word (4 bytes)	Counter
Double word (4 bytes)     WBCounter       Double word (4 bytes)     IXHook       Double word     COVCounter	Bit	Alarm
Double word (4 bytes)     IXHook       Double word     COVCounter	Double word (4 bytes)	WBCounter
Double word COVCounter	Double word (4 bytes)	IXHook
	Double word	COVCounter
8-bit character set text variable RTInfo	8-bit character set text variable	RTInfo
8-bit character set text variable RTSync	8-bit character set text variable	RTSync
8-bit character set text variable RTTopo	8-bit character set text variable	RTTopo

## Table A-3 PAS_InformationSInt structure (monitoring direction)

Long (4 bytes)	Value
Double word (4 bytes)	Validity
Double word (4 bytes)	Valuetype
Double word (4 bytes)	Cause
Double word (4 bytes)	Additional cause (AddCause)
Double word (4 bytes)	Counter
Bit	Alarm
Double word (4 bytes)	WBCounter
Double word (4 bytes)	IXHook
Double word	COVCounter
8-bit character set text variable	RTInfo
8-bit character set text variable	RTSync
8-bit character set text variable	RTTopo

#### Table A-4 PAS_Command structure (command direction)

Double word (4 bytes)	Value
Double word (4 bytes)	Validity
Double word (4 bytes)	Valuetype
Double word (4 bytes)	Cause
Double word (4 bytes)	Additional cause (AddCause)
Double word (4 bytes)	ReplyCounter
Double word (4 bytes)	Command counter (CmdCounter)
Double word	COVCounter
8-bit character set text variable	RTCmd

# Table A-5 PAS_CommandFloat structure (command direction)

Floating point (4 bytes)	Value
Double word (4 bytes)	Validity
Double word (4 bytes)	Valuetype
Double word (4 bytes)	Cause
Double word (4 bytes)	Additional cause (AddCause)
Double word (4 bytes)	ReplyCounter
Double word (4 bytes)	Command counter (CmdCounter)
Double word	COVCounter
8-bit character set text variable	RTCmd

Long (4 bytes)	Value
Double word (4 bytes)	Validity
Double word (4 bytes)	Valuetype
Double word (4 bytes)	Cause
Double word (4 bytes)	Additional cause (AddCause)
Double word (4 bytes)	ReplyCounter
Double word (4 bytes)	Command counter (CmdCounter)
Double word	COVCounter
8-bit character set text variable	RTCmd

#### Table A-6 PAS_CommandSInt structure (command direction)

For monitoring and controlling, you specifically access the elements of the structures.

#### **Structure Elements**

Value

The possible variants are indicated for each **Value Type**. The description does not mention all possible types, but is restricted to the most important types.

Value Type 1: Organizational message Freely defined, according to information address.

#### Value Type 2: Double-point indication

Highword		
Lowword		D
	·	

D:	00	Intermediate position
	01	OFF
	10	ON
	11	Fault

#### Value Type 3: Single-point indication

Highwo	ord			
Lowwo	ord			S
S:	1	OFF		
	2	ON		

#### Value Type 5: Transformer tap indication

Highword				
Lowword		LZ	LK	8 bits Transformer tap (binary)
LZ: 0 LZ: 1 LK: 0 LK: 1	Runtime monitoring not act Runtime monitoring activate Moving contact does not mo Moving contact moves (inte	ivated ed ove (fin rmedia	al positi te posit	ion) ion)

#### Value Type 6: Message with value

Highword	32 bits real value
Lowword	

Value Type 7: Bit pattern indication, 8 bits

#### Appendix A.1 Structures

Highword	
Lowword	8 bits bit pattern (binary)

Value Type 8: Bit pattern indication, 16 bits

Highword		
Lowword	16 bits bit pa	ttern (binary)

#### Value Type 9: Bit pattern indication, 24 bits

Highword	
Lowword	24 bits bit pattern (binary)

#### Value Type 10: Bit pattern indication, 32 bits

Highword	32 bits bit pattern (binary)
Lowword	

#### Value Type 12: Metered value

Highword	32 bits value, two's complement
Lowword	

#### Value Type 13: Persistent switching command

Highword		
Lowword		S

S: 0 OFF 1 ON

#### Value Type 14: Pulse switching command

Highwo Lowwo	ord rd		24 bits Duration in ms		S	5
S:	0	OFF				

If 0 ms is used as the period, the time sent by the CFC is used.

#### Value Type 17: Transformer tap positioning command

Highword	
Lowword	8 bits Transformer tap (binary)

#### Value Type 18: Setpoint digital, 8 bits

Highword	
Lowword	8 bits setpoint value (binary)

#### Value Type 19: Setpoint digital, 16 bits

Highword	
Lowword	16 bits setpoint value (binary)

Value Type 21: Setpoint digital, 32 bits

# Value Type 22: Setpoint value analog, floating point

Highword	32 bits real value
Lowword	

Values which cannot be represented as a 16 Bit-value are not output. They are BF-acknowledged with a plausibility error as an additional cause.

# Value Type 24: Setpoint value analog, fixed point

Highword		
Lowword	Val	lue

16 bits value, two's complement

# Value Type 28: Measured value, floating point

Highword	32 bits real value
Lowword	
	L

# Value Type 30: Measured value, fixed point

Highword		
Lowword	Val	lue

16 bits value, two's complement

# • Status

The **Status** element is composed of two parts. Byte 0 and Byte 1 include the **Status**, Byte 2 and Byte 3 indicate a **Timeout** in seconds.

The timeout is the system-internal monitoring time for the command output.

Value	Meaning
(Byte 0 and Byte 1)	
Bit O	Reserved (System)
Bit 1	Reserved (System)
Bit 2	Bit 2 within the status means that the process data have been written into SICAM SCC for the first time after a restart (SICAM PAS or SICAM SCC). This informs all components about the system restart. The components then check if they can continue from the last known status or if they have to re-initialize.
Bit 3	Reserved (System)
Bit 4	Reserved (System)
Bit 5	Reserved (System)
Bit 6	Reserved (System)
Bit 7	Counter state
Bit 8	Bay blocking set
Bit 9	Reserved (System)
Bit 10	Not updated (not topical)
Bit 11	Substituted
Bit 12	Reserved (System)
Bit 13	Remote monitoring direction blocked
Bit 14	Invalid
Bit 15	Overflow

#### • Value Type

Value	Meaning
1	Organizational indication
2	Double-point indication
3	Single-point indication
4	Event indication
5	Transformer tap position indication
6	Indication with value
7	Bit pattern indication, 8 bits
8	Bit pattern indication, 16 bits
9	Bit pattern indication, 24 bits
10	Bit pattern indication, 32 bits
11	Organizational acknowledgment
12	Metered value
13	Persistent switching command
14	Pulse switching command
15	Continuous control command
16	Auto-reclose command
17	Regulating step command
18	Scheduled value digital, 8 bits
19	Scheduled value digital, 16 bits
20	Scheduled value digital, 24 bits
21	Scheduled value digital, 32 bits
22	Setpoint analog, floating point
23	Setpoint analog, standardized
24	Setpoint analog, fixed point
25	GI request
26	Restore command
27	Organizational command
28	Measured value, floating point
29	Measured value, normalized
30	Measured value, fixed point
31	Sequence

#### Cause

Group / Value	Meaning
0	Irrelevant
1	Spontaneous
2	Cyclic, periodic
3	Initialized/default
4	Buffered
8	General interrogation
9	Request
10	Metered-value interrogation
16	Check

Group / Value	Meaning
17	Positive check result
18	Negative check result
19	Command execution
20	Command acceptance positive
21	Command acceptance negative
23	Return information negative
24	Command feedback intermediate position
25	Cancellation
26	Positive abortion procedure
27	Cancellation negative
28	Command execution ending
29	Release request
30	Positive release request
31	Negative release request
32	Organizational information
33	Information loss
34	Return Information
35	Command termination positive
36	Command termination negative
Bit 7	Direction bit

## • Additional Cause

Value	Meaning
0	No error
32	Release control
33	Reset command
34	Incorrect output time
35	Error on command check
36	Error in counter release
37	Unknown I/O channel
38	Too many commands active
39	Incorrect command type
40	Incorrect data type
41	Command not accepted
64	1-out-of-n error (hardware)
65	Target check
66	Voltage command relay
67	Release relay cannot be terminated
68	Output register not plausible
80	De-energized
81	Switching current check
82	Incorrect operational output
83	Command output voltage missing
96	Interlock finding
97	Switching error protection interlock
98	Parameter error

Value	Meaning
99	Violation of switching authority
100	Command too old
101	No process output object
102	Output disabled
103	Hardware error module
104	Hardware error I/O channel
105	Overload
112	Upper limit
113	Lower limit
114	Plausibility error
115	Sync. prerequisite missing
116	Device state preventing command
117	SCHEDULED = ACTUAL
118	Monitoring time elapsed (timeout)
119	Acquisition disabled
120	Chatter disabling active
121	1-of-n error (software)

#### Counter

#### For process indications

The **counter** is increased by the SICAM PAS PROTOCOL SUITE whenever a new item of information has been transmitted.

The **WBCounter** is increased by the WinCC object whenever an item of information must be substituted on the SICAM PAS server.

#### For commands

For SICAM SCC to send a command, the **command counter** (CmdCounter) must be increased. In this way, the SICAM PAS PROTOCOL SUITE detects that the information has changed.

The **ReplyCounter** is increased by the SICAM PAS PROTOCOL SUITE whenever a new item of information, e.g. a CO+ or COE command feedback, has been transmitted.

#### System-wide centralized counter (COVCounter)

The **COVCounter** is managed consistently on a system-wide level in SICAM PAS and SICAM SCC and enables the precise assignment of information.

#### • Alarm

This element is only relevant for old systems. For old projects in which the alarms are triggered by changes of the process tags (bit message procedure), the alarm bit of the corresponding tag is used as a trigger.

- 0 OFF
- 1 ON

#### IXHook

The IXHook tag is created as an internal tag of an ActiveX Controls. It comprises the current status of the ActiveX Controls during the runtime of the project.

#### • RuntimeDataServer Tags

The **RTInfo** and **RTCmd** tags are required for the internal communication of the graphic objects via the RuntimeDataServer. Process values and command outputs are routed via the RuntimeDataServer which processes them.

The **RTSync** tag is used in order to match items of SICAM information between redundant WinCC servers. The **RTTopo** tag is used in order to transfer the topological information from the topology component (colors, style, topological status).

# A.2 Quality Codes of Variables

The following table lists the quality codes that are set by the SICAM PAS PROTOCOL SUITE.

Hex value	Quality	Meaning	Q	Q	S	S	S	S	L	LA
00	Bad	Non-specific - There is no specific 0 reason why the value is bad. Used for propagation.		0	0	0	0	0	-	-
0C	Bad	Device Failure - Set if the source of the value is affected by a device failure.	0	0	0	0	1	1	-	-
14	Bad	No Communication, with last usable value - Set if this value had been set by communication, which has now failed.	0	0	0	1	0	1	-	-
18	Bad	No Communication, with no usable value - Set if there has never been any communication with this value since it was last "Out of Service".	0	0	0	1	1	0	-	-
44	Uncertain	ast Usable Value - Whatever was 0 vriting this value has stopped doing so. his is used for fail safe handling.		1	0	0	0	1	-	-
48	Uncertain	Substitute value - Predefined value is used instead of the calculated one. This is used for fail safe handling.	0	1	0	0	1	0	-	-
4C	Uncertain	Initial Value - Value of volatile parame- ters during and after reset of the device or of a parameter.	0	1	0	0	1	1	-	-
80	Good (Non-Cascade)	OK - No error or special condition is associated with this value.	1	0	0	0	0	0	-	-

Table A-7	Quality codes	of variables

The 2 low-order bits are set optionally in the quality codes.

Table A-8 Limits - optionally in the quality codes

Meaning	Q	Q	S	S	S	S	L	L
O.K The value is free to move	-	-	-	-	-	-	0	0
High limited - The value has exceeded its high limits	-	-	-	-	-	-	1	0

The abbreviations in the table columns mean:

- Q Quality
- S Substatus of the quality
- L Limits, this value is optionally

# A.3 Character Conversion

When importing SICAM PAS process tags or SICAM PAS archive tags from SICAM PAS or SICAM plusTOOLS, the tag names are adapted to the conventions of SIMATIC WinCC.

This paragraph contains conversion tables showing how the names are changed during the import process.

#### **Process Tags**

For SICAM PAS CC and SICAM SCC, the type of special character conversion is defined in the SICAM PAS Wizard. For SICAM SAS, it is defined in the SICAM Global Wizard.

#### • Character conversion in SICAM SCC

In order to create a new station in SICAM SCC, the **SICAM**, **V5.0** (or later) conforming parameter must be selected in the SICAM PAS Wizard under **General settings**. The special characters in tag names are converted as follows during the import process:

SICAM PAS	SICAM SCC
1	_ (underscore)
Blank character	is deleted
•	_
;	_
1	_
:	_
=	EQ
<	SM
>	GR
{	(
}	)
[	(
]	)
*	_
и	_
×	_
'	_
&	_
1	_
+	_
-	_
1	_
?	_
!	_
\$	_
%	_

Table A-9Character conversion in SICAM SCC

The special character conversion includes special characters of the German and English keyboard. All other special characters which are represented on keyboards for other languages are converted to the corresponding ASCII codes.

# i

# NOTE

Special features in SICAM IEC Wizard:

Texts being too long are cut automatically. For resulting identical entries warnings are displayed during import. This behavior may occur especially for direct SCD import, without editing via SICAM TOOLBOX II. Observe the warnings.

## • SICAM WinCC V2.xx character conversion

To update an existing station created with SICAM WinCC V2.xx, the **Special character conversion SICAM WinCC to V2.1x conforming** parameter must be selected in the SICAM Global Wizard under **General settings**. The special characters in tag names are converted as follows during the import process:

WinCC
_
is deleted
_
ae
oe
ue
AE
OE
UE
_
_
##
#_
_#
_
_
_
_
_
_
_
_
_
_
_
_
_

Table A-10	SICAM WinCC V2.xx character	conversion
------------	-----------------------------	------------

#### Character conversion SICAM WinCC V3.1

In order to create a new station with SICAM WinCC V3.1, the **Special character conversion SICAM WinCC, V3.1x (or later) conforming** parameter must be selected in the SICAM Global Wizard under **General settings**. The special characters in tag names are converted as follows during the import process:

Table A-11	Character	conversion	SICAM	WinCC	V3.1

SAS	WinCC
1	_
Blank character	is deleted
•	_
; ;	_
:	_
{	_
}	_
[	_
]	_
*	_
"	_
`	_
,	_
1	_
+	_
-	_

#### Archive Tags

Special characters in message names are converted during the import process as described below.

## • SICAM SCC character conversion

T     A 40					
Iahle A-17	(haracter	conversion	ın	message na	mec
	Character	CONVENSION		message na	IIIC J
				9	

SICAM SCC
_
is deleted
_
_
_
_
EQ
SM
GR
(
)
(
)
_
_
_
_
_
_
_
_
_

SICAM PAS	SICAM SCC
1	_
?	_
!	_
\$	_
%	_

The special character conversion includes special characters of the German and English keyboard. All other special characters which are represented on keyboards for other languages are converted to the corresponding ASCII codes.

## • SICAM WinCC character conversion

T     A 4 0	<u> </u>				
Table A-13	(haracter	conversion	In	message	names
	churacter	conversion		message	numes

SAS	WinCC
1	_
Blank character	is deleted
•	_
ä	ае
ö	oe
ü	ue
Ä	AE
Ö	OE
Ü	UE
;	_
,	_
:	_
=	EQ
<	SM
>	BG
{	_
}	_
[	_
]	_
*	_
"	_
`	_
,	_
&	_
1	_
+	_
-	<b>_</b>
@	

# A.4 Additional Information in Message Lists

This paragraph describes which additional items of information are written into which columns of the SICAM SCC message lists.

The list refers to the text library which is included in the program.

Column	Textlib-ID (Offset in Value Text Group)	Process Value	German Text	English Text
Value	0	0	Zwischenstellung Doppelmeldung	interm. state double indication
	1	1	AUS Doppelmeldung	OFF double indication
	3	2	EIN Doppelmeldung	ON double indication
	22	3	Störstellung Doppelmeldung	bad state double indication
	3	2	KOM Einzelmeldung	RAISED single indication
	4	1	GEH Einzelmeldung	CLEARED single indication
	5	0	Ereignis Statusänderung	event state change
	6	2	Wischer	transient
	7	SICAM SAS	Trafostufenstellbefehl RC	tap position RC
	8	SICAM SAS	Trafostufenstellung Laufkontakt	tap position moving contact
	9	SICAM SAS	Messwert TCB (Total Count Bit)	metered value TCB
	10	SICAM SAS	Messwert IEB (Internal Error Bit)	metered value IEB
	11	SICAM SAS	Messwert RB (Restore Bit)	metered value RB
	12	1	AUS Befehl	OFF static output command
	13	2	EIN Befehl	ON static output command
	14	0/3	STOP Dauerbefehl	STOP continous command
	15	1	MINUS Dauerbefehl	MINUS continous command
	16	2	PLUS Dauerbefehl	PLUS continous command
	17	2	EIN Impulsbefehl	ON pulse output command
	18	1	AUS Impulsbefehl	OFF pulse output command
	19	1	TIEFER Trafostufenstellbefehl	DOWN tap position command
	20	2	HOEHER Trafostufenstellbefehl	UP tap position command
	21	_	nicht initialisiert	not initialized

Table A-14 Additional information in message lists - Value

Table A-15 Additional information in message lists - Block Status

Column	Textlib-ID 2030 (+ Offset)	German Text	English Text
Block status	9	Aus Feld- und Fernwirksperre	Not blocked bay and telecontrol
	10	Feldsperre	bay blocked
	11	Fernwirksperre	telecontrol blocked
	12	Feld- und Fernwirksperre	bay and telecontrol blocked
	13	ignoriere Fernwirksperre	ignore telecontrol blocking
	14	werte Fernwirksperre aus	evaluate telecontrol blocking

Column	Textlib-ID 1700 (+ Offset)	German Text	English Text
Location	0	Irrelevant	irrelevant
	1	Vorort	local
	2	Nah	near
	3	Fern	remote
	4	Automatisch	automatic
	5	Automatisch (Feld)	automatic (bay)
	6	Prozess	process
	10	DIGSI Vorort	DIGSI local
	11	DIGSI Fern	DIGSI remote
	20	Gerät ungültig	device invalid
	21	Gerät gesperrt	device locked

Table A-16	Additional information in message lists - Location
	radicional información in message isos Eocación

Table A-17	Additional information in message lists - Cause
	C C

Column	Textlib-ID 1000 (+ Offset)	German Text	English Text
Cause	0	Ursache irrelevant	cause irrelevant
	1	spontan	spontaneous
	2	periodisch	periodic
	3	initialisiert	initialized
	4	Generalabfrage	buffered
	8	Generalabfrage	general interrogation
	9	Anfrage	request
	10	Zählwertabfrage	counter value request
	16	Prüfung	check back
	17	Prüfung +	check back +
	18	Prüfung -	check back -
	19	Befehl	command
	20	Befehl +	command +
	21	Befehl -	command -
	22	Rückmeldung +	feed back +
	23	Rückmeldung -	feed back -
	24	Rückmeldung stör	feed back intermediate
	25	Abbruch	abortion
	26	Abbruch +	abortion +
	27	Abbruch -	abortion -
	28	Befehlsende	command execution end
	29	Freigabeanforderung	release request
	30	Freigabeanforderung +	release request +
	31	Freigabeanforderung -	release request -
	32	Organisatorische Meldung	organisatory indication
	33	Meldungsverlust	information loss
	34	Rückmeldung	feed back
	35	Befehlsende +	command execution end +
	36	Befehlsende -	command execution end -
	37	Abbruch Ende +	abortion end +
	38	Abbruch Ende -	abortion end -
	39	Prüfungsende +	check back end +
	40	Prüfungsende -	check back end -
	41	Freigabeanf. Ende +	release reg end +
	42	Freigabeanf. Ende -	release reg end -

Column	Textlib-ID 2100 (+ Offset)	German Text	English Text
Status	5	Umspeicherbit	metered value freeze bit
	6	Internes Fehlerbit	internal Error bit
	7	Zählerstand	metered value
	8	Feldsperre	bay blocked
	9	Externer Fehler	external error
	10	Nicht aktuell	not topical
	11	Nachgeführt	substituted
	12	Flattersperre	debounced
	13	Fernwirksperre	telecontrol blocked
	14	Ungültig	invalid
	15	Überlauf	overflow
	16	Status Ok	status ok

Table A-18	Additional information in message lists - Status
------------	--------------------------------------------------

A.4 Additional Information in Message Lists

Table A-19	Additional information in message lists - Additional Cause
------------	------------------------------------------------------------

Column	Textlib-ID 1200 (+ Offset)	German Text	English Text
Additional cause	0	Kein Fehler	no error
	32	Freigabeansteuerung	release control
	33	Rücksetzen Befehl	reset command
	34	Falsche Ausgabezeit	output time error
	35	Fehler bei Befehlskontrolle	control error
	36	Fehler Zählerfreigabe	counter release error
	37	Unbekannter I/O-Kanal	unknown I/O channel
	38	Zu viele Befehle aktiv	too many active commands
	39	Falscher Befehlstyp	command type error
	40	Falscher Datentyp	datatype error
	41	Befehl wird nicht angenommen	command not accepted
	64	1 aus n-Fehler (Hardware)	1 out of n-error (hardware)
	65	Zielkontrolle	target check
	66	Spannung Befehlsrelais	command relay voltage
	67	Freigaberelais nicht absteuerbar	release can not be terminated
	68	Ausgaberegister nicht plausibel	output register not plausible
	80	Spannungsfreiheit	de-energized
	81	Schaltstromkontrolle	terminal allocation
	82	Falscher Betriebsausgang	operational output error
	83	Befehlsausgabespannung fehlt	command output voltage missing
	96	Verriegelungsbefund	interlocking
	97	Schaltfehlerschutzverriegelung	switchgear interlocking
	98	Parameterfehler	parameter error
	99	Verstoß Schalthoheit	authority violation
	100	Befehl zu alt	command too old
	101	Kein Prozessausgabeobjekt	no process output object
	102	Ausgabesperre	output disable
	103	HW-Fehler Baugruppe	HW error module
	104	HW-Fehler I/O-Kanal	HW error I/O channel
	105	Überlast	overload
	112	Obere Grenze	upper limit
	113	Untere Grenze	lower limit
	114	Plausibilitätsfehler	plausibility error
	115	Voraussetzung für Sync. fehlt	sync. precondition missing
	116	Gerätezustand verhindert Befehl	dev. state disables command
	117	SOLL = IST	set = actual
	118	Überwachungszeit abgelaufen	monitoring time expiredset = actual
	119	Erfassungssperre	acquisition disable
	120	Flattersperre aktiv	debouncing active
	121	1 aus n-Fehler (Software)	1 out of n-error (software)
	196	Verriegelt, synchronisiert	interlocked, synchronized
	197	Verriegelt, nicht synchronisiert	interlocked, not synchronized
	198	Unverriegelt, synchronisiert	non-interlocked, synchronized
	199	Unverriegelt, nicht synchronisiert	non-interlocked, not synchronized
Column	Textlib-ID 1900 (+ Offset)	German Text	English Text
-----------------------------	-------------------------------	----------------------------------	----------------------------------
ID number	0	Identifikationsnummer irrelevant	identification number irrelevant
	1	Implizit bestimmt	implicitly determined
	2	Rückmeldungsidentifikator	return information identifier
	3	Fehlernummer	fault number
Additional informa- tion	4	Zusatzinformation irrelevant	suppl. info irrelevant
	5	Zusatzinformation impl. bestimmt	suppl. info impl. determined
	6	Relativzeit in ms	relative time in ms
	7	Quelladresse	initiator address
	8	Ein Laufkontakt	ON transition information
	9	Gemeldet von:	Reported by:

#### Table A-20 Additional information in message lists - ID number, Additional information

Table A-21	Additional information in message lists - Time Status IEC Communication Suite
------------	-------------------------------------------------------------------------------

Column	Textlib-ID 1170 (+ Offset)	German Text	English Text
Time status IEC Communication Suite	0	W   EXT	W   EXT
		(Winterzeit, Prozess - extern)	(Standard time, process - extern)
	1	S   EXT	S   EXT
		(Sommerzeit, Prozess - extern)	(DST, process - extern)
	2	W   INT	W   INT
		(Winterzeit, Kanal - intern)	(Standard time, channel - intern)
	3	S   INT	S   INT
		(Sommerzeit, Kanal - intern)	(DST time, channel - intern)

A.4 Additional Information in Message Lists

Column	Textlib-ID 1180 (+ Offset)	German Text	English Text
Time status PAS	0	W JGN	W   VN
channel		(Winterzeit, gültig, nicht synchroni- siert)	(Standard time, valid, not synchron- ized)
	1	S  GN	S   VN
		(Sommerzeit, gültig, nicht synchroni- siert)	(DST, valid, not synchronized)
	2	W  GS	W   VS
		(Winterzeit, gültig, synchronisiert)	(Standard time, valid, synchronized)
	3	S  GS	S   VS
		(Sommerzeit, gültig, synchronisiert)	(DST, valid, synchronized)
	4	W JUN	W   IN
		(Winterzeit, nicht gültig, nicht synchro- nisiert)	(Standard time, not valid, not synchronized)
	5	S JUN	S   IN
		(Sommerzeit, nicht gültig, nicht synchronisiert)	(DST, valid, not synchronized)
	6	W JUS	W   IS
		(Winterzeit, nicht gültig, synchroni- siert)	(Standard time, not valid, synchron- ized)
	7	s ius	S   IS (DST, not valid, synchronized)
		(Sommerzeit, gültig, synchronisiert)	
	8	e (von SICAM PAS ersetzt)	r (replaced by SICAM PAS)
	-	(WinCC) Zeitstempel von SICAM SCC erzeugt	(WinCC) Time stamp generated by SICAM SCC

Table A-22	Additional information in message lists - Time Status PAS Channel
------------	-------------------------------------------------------------------

 Table A-23
 Additional information in message lists - Time Status SIMATIC S7 Channel

Column	Textlib-ID 1190 (+ Offset)	German Text	English Text
Time status SIMATIC S7 channel	0	GN (gültig, nicht synchronisiert)	VN (valid, not synchronized)
	1	GS (gültig, synchronisiert)	VN (valid, synchronized)
	2	UN (ungültig)	IN (invalid)
	3	S (Sommerzeit)	DST (Daylight Saving Time)
	4	W (Winterzeit)	noDST (Standard time)

## A.5 Performance Measurements

For a Core i5 3470 with 8 GB of RAM, you get the following results during the performance measurement:

Measurement	Value
Average process-value changes per second	max. 800
Short-term (< 1 h) value count	1900
	NOTE: The maximum number of 800 values/s must not be
	exceeded.

When using a 32-bit application, more memory and more cores do not necessarily improve performance. Less high-performance PCs reduce throughput. Therefore, Siemens recommends that when approaching the tested limits, you check whether the required response times can be achieved.

Since SICAM SCC uses structure variables for the process data-points and each structure variable has about 10 WinCC variables, Siemens recommends distributing the project for more than about 25,000 data points to several WinCC servers.

# Literature

- /1/ SICAM PAS, Overview E50417-X8976-C431-C1
- I2/ SICAM PAS/PQS, InstallationE50417-M8976-C432-C1
- I3I SICAM PAS/PQS, Configuration and Operation E50417-P8976-C433-C2
- I4I SICAM SCC, Human Machine Interface SICAM SCC E50417-H8976-C501-B4
- ISICAM Valpro, Measured/Metered Value Processing Utility SICAM Valpro E50417-H8976-C479-A4
- /6/ SICAM PAS, Redundancy E50417-H8976-C441-B9
- I7I
   SICAM Station Unit V2.40

   E50417-H8976-C381-A5
- /8/ SIMATIC HMI WinCC, System description A1900-L531-B996-X-7600
- III SIMATIC Security concept PCS 7 and WinCC Basic document A5E02128732-01
- /10/ SICAM SCC for SICAM SAS E50417-H8900-C515-A1
- /11/ SICAM PQ Analyzer, Incident Explorer E50417-H8976-C465-C2

## Index

#### 1,2,3 ...

1-of-N Command Interlocking 283 1-pole 183 2-pole 183

## Α

Adjustments for DAF 418 Alarm systems extension 17 Anwendungsbeispiele 201 Anzeige Messwert/Zählwert 153 Assignment Tables DAF 306 Aufgaben benutzerdefiniert 214 Automated Installation 28

## В

Basic Hardware 22

## С

Client-Server-Systeme 369 Coloring 181 Command Interlocking 283 Configuration DAF 298 Connector 181

## D

DAF adjustments 418 Assignment Tables 306 Configuration 298 Filter Criteria 300 Filter criterion actions 302 Mapping 304 Data Analysis 181 Defining SICAM Electrical Device Controls 178 Demo Mode 26 Demo Project 34 Design Variants 26 Detailbild erstellen 75 Dynamic Alarm Filter Assignment Tables 306 Configuration 298 Mapping 304 Dynamic Network Coloring 166

#### F

Feeder 169, 181 Supply 175 Tag connection 175 Fehlersuche 199 Feldübersicht 145 Frühere SICAM PAS CC/SCC-Versionen 431

### G

Grafikobjekte 103 Ground 169

## I

IEC 60870-5-104 236 IEC 61850 236 IEC tags 238 Installation Automated 28 SICAM SCC components 27 SIMATIC WinCC 25 Installation Requirements 22

## Κ

Konvertieren vorheriger Projekte 415

#### L

Licensed Version 27 Licensing SICAM SCC components 28 SIMATIC WinCC 25 Line Node 183 List tag prefix 197

#### Μ

Mapping DAF 304 Microsoft .NET Framework 22

#### Ν

Neues Projekt anlegen 35

#### 0

Operating System 22

### Ρ

Parametrierung 181 Picture window 197 Product Overview Redundant system 19 SICAM functions 19 SICAM graphic object library 17 SICAM Graphics Designer Extension 19 SICAM SCC Components 17 SICAM Valpro 19 SICAM Wizard 18 Product Overwiev Alarm systems extension 17

#### R

Redundant system 19 Redundanz 375 Removing the license SICAM SCC components 30 SIMATIC WinCC 31

#### S

Schalterleiste erstellen 93 Sequence of Installation 22 SI with Alarm when OFF 418 SI with Alarm when ON 418 SICAM Add-In 203 SICAM Bay Overview 145 SICAM Electrical Device Control 169, 169 SICAM functions 19 SICAM graphic object library 17 SICAM Graphics Designer Extension 19 SICAM IEC COMMUNICATION SUITE 281 SICAM Import/Export Wizard 250 SICAM RTU 236 SICAM SCC components 27 SICAM SCC Components 17 SICAM SCC-Komponenten und Funktionen 233 SICAM Schaltobjekte 108 SICAM Switch Controls 108, 179, 179 SICAM Topologie 169 SICAM Valpro 19 SICAM Wizard 18 SIMATIC WinCC installation 25 Source 181 Structure tags 178 Supply 175 Systemzeit 401

## Т

TEA-X files 250 Termination 169, 181 Topological Elements 181 Topologische Einfärbung 165 Topologische Elemente 168 Transformer 169 Trial Mode 27

#### U

Uninstallation SICAM SCC components 30 SIMATIC WinCC 31

#### V

Verschiedene SICAM PAS-Versionen 385 Volume Requirements 44

## W

WinCC Web Navigator 391 WinCC-Projekt initialisieren 43